

Interactive System Productivity Facility (ISPF)



# Dialog Tag Language Guide and Reference

*z/OS Version 1 Release 6.0*



Interactive System Productivity Facility (ISPF)



# Dialog Tag Language Guide and Reference

*z/OS Version 1 Release 6.0*

**Note**

Before using this document, read the general information under "Notices" on page 539.

**Fourth Edition (September 2004)**

This edition applies to ISPF for Version 1 Release 6.0 of the licensed program z/OS (program number 5694-A01) and to all subsequent releases and modifications until otherwise indicated in new editions.

Order publications by phone or fax. IBM Software Manufacturing Solutions takes publication orders between 8:30 a.m. and 7:00 p.m. eastern standard time (EST). The phone number is (800) 879-2755. The fax number is (800) 284-4721.

You can also order publications through your IBM representative or the IBM branch office serving your locality. Publications are not stocked at the address below.

A form for comments appears at the back of this publication. If the form has been removed, and you have ISPF-specific comments, address your comments to:

IBM Corporation  
Department J87/D325  
555 Bailey Avenue  
San Jose, CA 95141-1003  
U.S.A.

Internet: [comments@us.ibm.com](mailto:comments@us.ibm.com)

If you would like a reply, be sure to include your name, address, telephone number, e-mail address, or FAX number.

Make sure to include the following in your comment or note:

Title and order number of this document  
Page number or topic related to your comment

The ISPF development team maintains a site on the World Wide Web. The URL for the site is:  
<http://www.ibm.com/software/awdtools/ispf/>

© Copyright International Business Machines Corporation 1989, 2004. All rights reserved.

US Government Users Restricted Rights – Use, duplication or disclosure restricted by GSA ADP Schedule Contract with IBM Corp.

---

# Contents

<b>Figures</b> . . . . .	<b>ix</b>
--------------------------	-----------

<b>Preface</b> . . . . .	<b>xi</b>
--------------------------	-----------

About This Document . . . . .	xi
Who Should Use This Document . . . . .	xi
Using LookAt to look up message explanations . . . . .	xi

<b>Summary of Changes</b> . . . . .	<b>xiii</b>
-------------------------------------	-------------

ISPF Product and Library changes . . . . .	xiii
ISPF Dialog Manager component changes . . . . .	xiii
Dialog Tag Language (DTL) changes. . . . .	xiv
ISPF PDF Component changes. . . . .	xiv
ISPF SCLM Component changes . . . . .	xiv
ISPF Client/Server Component changes. . . . .	xv
ISPF Migration Considerations . . . . .	xv

<b>What's in the z/OS V1R6.0 ISPF library?</b> . . . . .	<b>xvii</b>
z/OS V1R6.0 ISPF. . . . .	xvii

<b>The ISPF User Interface</b> . . . . .	<b>xix</b>
--	------------

Some Terms You Should Know . . . . .	xix
How to Navigate in ISPF Using the Action Bar	
Interface . . . . .	xx
Action Bars . . . . .	xx
Command Nesting . . . . .	xxii
Action Bar Choices . . . . .	xxiii
Point-and-Shoot Text Fields . . . . .	xxiv
Function Keys . . . . .	xxv
Selection Fields . . . . .	xxvi
How to Navigate in ISPF without Using Action Bars . . . . .	xxvi

---

<b>Part 1. Guide to the Dialog Tag Language (DTL)</b> . . . . .	<b>1</b>
---	----------

<b>Chapter 1. Introduction to the Dialog Tag Language (DTL)</b> . . . . .	<b>3</b>
---	----------

Why the Dialog Tag Language (DTL)? . . . . .	3
What Is the Dialog Tag Language? . . . . .	4
Dialog Elements . . . . .	5
Application Panels . . . . .	5
Help Panels. . . . .	7
Messages . . . . .	8
Application Command Table . . . . .	8
Key Mapping Lists . . . . .	9
Variables and Variable Classes . . . . .	9
What Is the ISPF Conversion Utility? . . . . .	9

<b>Chapter 2. How to Use the Dialog Tag Language (DTL)</b> . . . . .	<b>11</b>
--	-----------

Syntax Conventions. . . . .	11
Attributes and Values . . . . .	11

Tag Text . . . . .	12
Text Formatting . . . . .	13
Nesting tags . . . . .	15
Markup Declarations . . . . .	16
Declaring the Document Type . . . . .	16
Including Comments in Your Markup . . . . .	16
Defining Entities and Parameter Entities. . . . .	18
Embedding Source Files . . . . .	23
Run-Time Substitution Variables . . . . .	24
Predefined Entities . . . . .	25

<b>Chapter 3. Getting Started: Designing Application Panels</b> . . . . .	<b>27</b>
---	-----------

Defining Application Panels: The PANEL Tag . . . . .	27
The Panel Title . . . . .	29
Panel Size (Width and Depth) . . . . .	29
Key Mapping Lists . . . . .	29
Associated Help Panels . . . . .	30
Panel Defaults . . . . .	30
Cursor Placement . . . . .	30
Other Panel Attributes. . . . .	32
Defining Action Bars and Pull-Downs . . . . .	34
Coding an Action Bar Definition . . . . .	35
Pull-Down Choice Actions . . . . .	36
Action Bar Help . . . . .	36
Preselected Pull-Down Choices . . . . .	37
Mnemonic Choice Selection . . . . .	38
Pull-Down Choice Accelerator Support . . . . .	39
Defining the Panel Body . . . . .	39
Panel Instructions . . . . .	39
The AREA Tag . . . . .	40
Scrollable Areas . . . . .	41
Multiple AREA Tags . . . . .	44
The DYNAMIC AREA Tag . . . . .	45
The GRAPHIC AREA Tag . . . . .	46
The DIVIDER Tag . . . . .	46
The REGION Tag . . . . .	48
Defining a Command Area . . . . .	51
Defining Panel Defaults . . . . .	53

<b>Chapter 4. Variables and Variable Classes</b> . . . . .	<b>57</b>
--	-----------

Declaring Variables . . . . .	57
Defining Variable Classes. . . . .	58
Variable Class Types . . . . .	59
Character Variables. . . . .	59
Numeric Variables . . . . .	60
Variable Validation . . . . .	61
Translate Lists . . . . .	61
Validity Checks . . . . .	66
Overriding Variable Classes . . . . .	77

<b>Chapter 5. Application Panel Fields</b> . . . . .	<b>79</b>
--	-----------

Field Prompts . . . . .	79
Defining Data Fields . . . . .	82

Data Field Width . . . . .	84
Data Field Descriptions . . . . .	84
Data Field Help . . . . .	85
Other Data Field Attributes . . . . .	86
Defining Selection Fields . . . . .	89
Single-Choice Fields . . . . .	90
Multiple-Choice Fields. . . . .	91
Menu-Choice Fields . . . . .	93
Model-Choice Fields . . . . .	94
Tutor-Choice Fields. . . . .	95
Selection Field Help . . . . .	95
Selection Width . . . . .	95
Other Selection Field Attributes. . . . .	97
Data Columns . . . . .	99
Defining List Fields . . . . .	101
List Group Headings . . . . .	103
List Column Width . . . . .	105
Other List Column Attributes . . . . .	105
Defining Group Headings . . . . .	107
Defining Point-and-Shoot Fields . . . . .	108
Defining Scrollable Fields . . . . .	108

**Chapter 6. Information Regions and Help Panels . . . . . 113**

Defining an Information Region . . . . .	113
Defining Basic Text . . . . .	114
Paragraphs . . . . .	114
Headings . . . . .	116
Lines . . . . .	117
Examples . . . . .	118
Figures . . . . .	119
Defining Lists . . . . .	121
Note Lists . . . . .	122
Simple Lists . . . . .	122
Unordered Lists . . . . .	124
Ordered Lists . . . . .	126
Definition Lists . . . . .	128
Parameter Lists. . . . .	132
Nesting Tags within Lists . . . . .	133
Nesting Lists within Lists . . . . .	135
Alerting Users: Notes, Warnings, Cautions, and Attention . . . . .	136
Notes . . . . .	136
Attention and Warning . . . . .	139
Caution . . . . .	140
Emphasizing Panel Text . . . . .	141
Using Information Regions with Other Panel Elements . . . . .	145
Help Panels . . . . .	146

**Chapter 7. Messages . . . . . 155**

Defining Messages . . . . .	155
Specifying Message Severity . . . . .	156
Short Messages. . . . .	157
Assigning Messages . . . . .	157
Displaying Messages . . . . .	159
Variable Substitution . . . . .	160

**Chapter 8. The Application Command Table . . . . . 161**

Defining the Application Command Table . . . . .	161
Specifying Command Actions . . . . .	163
Truncating Commands . . . . .	164

**Chapter 9. Defining Key Mapping Lists 167**

Assigning Keys and Actions . . . . .	167
ISPF Default Key List. . . . .	168
Displaying Keys . . . . .	168
Defining Help for Key List . . . . .	169

**Chapter 10. Using the Conversion Utility . . . . . 171**

Using the ISPF-Supplied Invocation Panels . . . . .	171
Invocation Panel . . . . .	171
Panel Input Fields . . . . .	172
Panel Options . . . . .	173
Converting Multiple DTL Source Files . . . . .	176
Calling Help . . . . .	176
Using CUA Panel Attributes . . . . .	176
Conversion Utility Syntax . . . . .	177
Conversion Utility General Information . . . . .	183
ISPF Conversion Utility Messages . . . . .	186
Return Codes . . . . .	187
Conversion Results . . . . .	187
Conversion Utility File Names. . . . .	187

**Part 2. Dialog Tag Language (DTL) Reference . . . . . 191**

**Chapter 11. How to Read the Syntax Diagrams . . . . . 193**

**Chapter 12. Markup Declarations and DTL Macro Reference . . . . . 195**

Document-Type Declaration . . . . .	195
Description . . . . .	195
Example . . . . .	195
Entity Declarations . . . . .	196
Description . . . . .	197
Conditions . . . . .	197
Example . . . . .	198
Sample Entity Definitions . . . . .	199
DTL Macros. . . . .	202

**Chapter 13. Tag Reference. . . . . 205**

Rules for Variable Names . . . . .	205
Rules for “%variable” Names . . . . .	205
AB (Action Bar) . . . . .	206
Description . . . . .	206
Conditions . . . . .	207
Nested Tags . . . . .	207
Example . . . . .	207
ABC (Action Bar Choice) . . . . .	208
Description . . . . .	209
Conditions . . . . .	209
Nested Tags . . . . .	209
Example . . . . .	209
ACTION (Action) . . . . .	211

Description . . . . .	215	Conditions . . . . .	260
Conditions . . . . .	216	Nested Tags . . . . .	261
Nested Tags . . . . .	216	Example . . . . .	261
Example . . . . .	216	CMD (Command Definition) . . . . .	262
AREA (Area) . . . . .	217	Description . . . . .	263
Description . . . . .	219	Conditions . . . . .	263
Conditions . . . . .	220	Nested Tags . . . . .	263
Nested Tags . . . . .	220	Example . . . . .	263
Example . . . . .	221	CMDACT (Command Action) . . . . .	264
ASSIGNI (Assignment List Item) . . . . .	223	Description . . . . .	266
Description . . . . .	224	Conditions . . . . .	266
Conditions . . . . .	224	Nested Tags . . . . .	266
Nested Tags . . . . .	224	Example . . . . .	266
Example . . . . .	224	CMDAREA (Command Area) . . . . .	267
ASSIGNL (Assignment List) . . . . .	225	Description . . . . .	271
Description . . . . .	225	Conditions . . . . .	272
Conditions . . . . .	225	Nested Tags . . . . .	272
Nested Tags . . . . .	225	Example . . . . .	272
Example . . . . .	225	CMDTBL (Command Table) . . . . .	273
ATTENTION (Attention) . . . . .	226	Description . . . . .	274
Description . . . . .	226	Conditions . . . . .	274
Conditions . . . . .	226	Nested Tags . . . . .	274
Nested Tags . . . . .	227	Example . . . . .	275
Example . . . . .	227	COMMENT (Comment) . . . . .	275
ATTR (Attribute) . . . . .	228	Description . . . . .	276
Description . . . . .	231	Conditions: . . . . .	276
Conditions . . . . .	231	Nested Tags . . . . .	276
Nested Tags . . . . .	231	Example . . . . .	276
Example . . . . .	232	COMPOPT (Compiler Options) . . . . .	277
BOTINST (Bottom Instruction) . . . . .	232	Description . . . . .	278
Description . . . . .	232	Conditions: . . . . .	278
Conditions . . . . .	232	Nested Tags . . . . .	278
Nested Tags . . . . .	233	Example . . . . .	278
Example . . . . .	233	COPYR (Copyright) . . . . .	279
CAUTION (Caution) . . . . .	234	Description . . . . .	279
Description . . . . .	234	Conditions . . . . .	279
Conditions . . . . .	234	Nested Tags . . . . .	279
Nested Tags . . . . .	235	Example . . . . .	280
Example . . . . .	235	DA (Dynamic Area) . . . . .	280
CHDIV (Choice Divider) . . . . .	236	Description . . . . .	284
Description . . . . .	237	Conditions . . . . .	284
Conditions . . . . .	237	Nested Tags . . . . .	285
Nested Tags . . . . .	237	Example . . . . .	285
Example . . . . .	237	DD (Definition Description) . . . . .	285
CHECKI (Validity Check Item) . . . . .	238	Description . . . . .	285
Description . . . . .	246	Conditions . . . . .	286
Conditions . . . . .	246	Nested Tags . . . . .	286
Nested Tags . . . . .	246	Example . . . . .	286
Example . . . . .	246	DDHD (Definition Description Header) . . . . .	287
CHECKL (Validity Check List) . . . . .	247	Description . . . . .	288
Description . . . . .	247	Conditions . . . . .	288
Conditions . . . . .	247	Nested Tags . . . . .	288
Nested Tags . . . . .	248	Example . . . . .	288
Example . . . . .	248	DIVIDER (Area Divider) . . . . .	289
CHOFLD (Choice Data Field) . . . . .	248	Description . . . . .	290
Description . . . . .	253	Conditions . . . . .	290
Conditions . . . . .	253	Nested Tags . . . . .	291
Nested Tags . . . . .	253	Example . . . . .	291
Example . . . . .	254	DL (Definition List) . . . . .	292
CHOICE (Selection Choice) . . . . .	255	Description . . . . .	293
Description . . . . .	259	Conditions . . . . .	293

Nested Tags . . . . .	294	Example . . . . .	330
Example . . . . .	294	GENERATE (Generate) . . . . .	330
DLDIV (Definition List Divider) . . . . .	296	Description . . . . .	330
Description . . . . .	297	Conditions . . . . .	330
Conditions . . . . .	297	Nested Tags . . . . .	331
Nested Tags . . . . .	297	Example . . . . .	331
Example . . . . .	297	GRPHDR (Group Header) . . . . .	332
DT (Definition Term) . . . . .	298	Description . . . . .	333
Description . . . . .	299	Conditions . . . . .	334
Conditions . . . . .	299	Nested Tags . . . . .	334
Nested Tags . . . . .	299	Example . . . . .	334
Example . . . . .	299	HELP (Help Panel) . . . . .	335
DTACOL (Data Column) . . . . .	300	Description . . . . .	339
Description . . . . .	304	Conditions . . . . .	341
Conditions . . . . .	304	Nested Tags . . . . .	341
Nested Tags . . . . .	305	Example . . . . .	341
Example . . . . .	305	HELPDEF (Help default) . . . . .	343
DTAFLD (Data Field) . . . . .	306	Description . . . . .	345
Description . . . . .	314	Conditions . . . . .	346
Conditions . . . . .	314	Nested Tags . . . . .	346
Nested Tags . . . . .	314	Example . . . . .	346
Example . . . . .	315	Hn (Heading) . . . . .	346
DTAFLDD (Data Field Description) . . . . .	316	Description . . . . .	347
Description . . . . .	316	Conditions . . . . .	347
Conditions . . . . .	316	Nested Tags . . . . .	347
Nested Tags . . . . .	316	Example . . . . .	347
Example . . . . .	317	HP (Highlighted Phrase) . . . . .	348
DTDIV (Definition Term Divider) . . . . .	318	Description . . . . .	349
Description . . . . .	318	Conditions . . . . .	349
Conditions . . . . .	318	Nested Tags . . . . .	349
Nested Tags . . . . .	318	Example . . . . .	349
Example . . . . .	318	INFO (Information Region) . . . . .	350
DTHD (Definition Term Header) . . . . .	319	Description . . . . .	351
Description . . . . .	319	Conditions . . . . .	351
Conditions . . . . .	319	Nested Tags . . . . .	351
Nested Tags . . . . .	320	Example . . . . .	351
Example . . . . .	320	KEYI (Key Item) . . . . .	352
DTHDIV (Definition Term Header Divider) . . . . .	321	Description . . . . .	354
Description . . . . .	321	Conditions . . . . .	354
Conditions . . . . .	321	Nested Tags . . . . .	354
Nested Tags . . . . .	321	Example . . . . .	354
Example . . . . .	321	KEYL (Key List) . . . . .	355
DTSEG (Definition Term Segment) . . . . .	322	Description . . . . .	356
Description . . . . .	322	Conditions . . . . .	357
Conditions . . . . .	322	Nested Tags . . . . .	357
Nested Tags . . . . .	323	Example . . . . .	357
Example . . . . .	323	LI (List Item) . . . . .	358
FIG (Figure) . . . . .	324	Description . . . . .	358
Description . . . . .	324	Conditions . . . . .	359
Conditions . . . . .	325	Nested Tags . . . . .	359
Nested Tags . . . . .	325	Example . . . . .	360
Example . . . . .	325	LINES (Lines) . . . . .	360
FIGCAP (Figure Caption) . . . . .	326	Description . . . . .	361
Description . . . . .	326	Conditions . . . . .	361
Conditions . . . . .	326	Nested Tags . . . . .	361
Nested Tags . . . . .	326	Example . . . . .	361
Example . . . . .	327	LIT (Literal) . . . . .	362
GA (Graphic Area) . . . . .	327	Description . . . . .	363
Description . . . . .	329	Conditions . . . . .	363
Conditions . . . . .	329	Nested Tags . . . . .	363
Nested Tags . . . . .	329	Example . . . . .	363

LP (List Part) . . . . .	364	Description . . . . .	407
Description . . . . .	365	Conditions . . . . .	407
Conditions . . . . .	365	Nested Tags . . . . .	407
Nested Tags . . . . .	365	Example . . . . .	408
Example . . . . .	365	PANDEF (Panel Default) . . . . .	409
LSTCOL (List Column) . . . . .	366	Description . . . . .	411
Description . . . . .	372	Conditions . . . . .	412
Conditions . . . . .	373	Nested Tags . . . . .	412
Nested Tags . . . . .	373	Example . . . . .	412
Examples . . . . .	373	PANEL (Panel) . . . . .	413
LSTFLD (List Field) . . . . .	377	Description . . . . .	421
Description . . . . .	379	Conditions . . . . .	421
Conditions . . . . .	379	Nested Tags . . . . .	422
Nested Tags . . . . .	380	Example . . . . .	422
Example . . . . .	380	PARML (Parameter List) . . . . .	424
LSTGRP (List Group) . . . . .	382	Description . . . . .	425
Description . . . . .	383	Conditions . . . . .	425
Conditions . . . . .	383	Nested Tags . . . . .	425
Nested Tags . . . . .	383	Example . . . . .	426
Example . . . . .	384	PD (Parameter Description) . . . . .	427
LSTVAR (List Variable) . . . . .	385	Description . . . . .	427
Description . . . . .	385	Conditions . . . . .	427
Conditions . . . . .	386	Nested Tags . . . . .	427
Nested Tags . . . . .	386	Example . . . . .	427
Example . . . . .	386	PDC (Pull-Down Choice) . . . . .	428
M (Mnemonic) . . . . .	388	Description . . . . .	430
Description . . . . .	389	Conditions . . . . .	430
Conditions . . . . .	389	Nested Tags . . . . .	431
Nested Tags . . . . .	389	Example . . . . .	431
Example . . . . .	389	PDSEP (Pull-Down Separator) . . . . .	432
MSG (Message) . . . . .	390	Description . . . . .	432
Description . . . . .	393	Conditions . . . . .	432
Conditions . . . . .	393	Nested Tags . . . . .	432
Nested Tags . . . . .	393	Example . . . . .	432
Example . . . . .	393	PLDIV (Parameter List Divider) . . . . .	434
MSGMBR (Message Member) . . . . .	394	Description . . . . .	434
Description . . . . .	395	Conditions . . . . .	435
Conditions . . . . .	395	Nested Tags . . . . .	435
Nested Tags . . . . .	395	Example . . . . .	435
Example . . . . .	395	PNLINST (Panel Instruction) . . . . .	436
NOTE (Note) . . . . .	396	Description . . . . .	436
Description . . . . .	398	Conditions . . . . .	436
Conditions . . . . .	398	Nested Tags . . . . .	436
Nested Tags . . . . .	398	Example . . . . .	437
Example . . . . .	398	PS (Point-and-Shoot) . . . . .	438
NOTEL (Note List) . . . . .	399	Description . . . . .	439
Description . . . . .	400	Conditions . . . . .	440
Conditions . . . . .	400	Nested tags . . . . .	440
Nested Tags . . . . .	401	Example . . . . .	440
Example . . . . .	401	PT (Parameter Term) . . . . .	441
NT (Note) . . . . .	402	Description . . . . .	442
Description . . . . .	403	Conditions . . . . .	442
Conditions . . . . .	403	Nested Tags . . . . .	442
Nested Tags . . . . .	403	Example . . . . .	442
Example . . . . .	403	PTDIV (Parameter Term Divider) . . . . .	443
OL (Ordered List) . . . . .	404	Description . . . . .	443
Description . . . . .	405	Conditions . . . . .	443
Conditions . . . . .	405	Nested Tags . . . . .	443
Nested Tags . . . . .	405	Example . . . . .	443
Example . . . . .	406	PTSEG (Parameter Term Segment) . . . . .	445
P (Paragraph) . . . . .	406	Description . . . . .	445



---

## Figures

1. Panel with an Action Bar Pull-Down Menu	xxi	54. Compact Simple List	123
2. Pop-Up Selected from an Action Bar Pull-Down	xxii	55. Unordered List	124
3. Panel with an Action Bar and Point-and-Shoot Fields	xxii	56. Nested Unordered Lists	126
4. An Unavailable Choice on a Pull-Down	xxiv	57. Ordered List	126
5. Application Panel	6	58. Nested Ordered Lists	128
6. Help Panel	7	59. Definition List	129
7. Message Displayed in Message Area	8	60. Definition List (BREAK=ALL)	131
8. Text Formatting Rules	14	61. Definition List (BREAK=FIT)	132
9. Entity Reference for Text Substitution	19	62. Parameter List	133
10. Entity Reference for Text Substitution	20	63. Nested Paragraph within a List	134
11. Entity Reference for Text Substitution and File Embedding	21	64. List Part	135
12. Parameter Entities	23	65. Nested Unordered List in a Definition List	135
13. Cursor Placement	31	66. Note (NOTE tag)	137
14. Action Bar and Pull-Down	35	67. Notel (NOTEL tag)	138
15. Preselected Pull-Down Choice	39	68. Note (NT tag)	139
16. Top and Bottom Instructions	40	69. Warning	140
17. AREA MARGINW=10	41	70. Caution	141
18. Scrollable Panel Area	43	71. Highlighted Phrase Example	143
19. Application Panel Area	43	72. Reference Phrase Example	144
20. Scrollable Panel Area	44	73. Reference Phrase Example of Help Attribute	145
21. Multiple Horizontal Areas	45	74. Information Region	146
22. Area Dividers	47	75. Help Panel	148
23. Vertical Region	49	76. Help Panel (Example 1 of 4)	150
24. Horizontal Region	50	77. Help Panel (Example 2 of 4)	150
25. Horizontal Region	51	78. Help Panel (Example 3 of 4)	150
26. Command Area	52	79. Help Panel (Example 4 of 4)	151
27. Command Area	53	80. Help Panel (Example 1 of 3)	152
28. Variable Translation Results	62	81. Help Panel (Example 2 of 3)	152
29. Variable Translation	63	82. Help Panel (Example 3 of 3)	153
30. Variable Translation	64	83. Data Field and Message	159
31. Variable Translation	65	84. Displayed Function Key Area	169
32. Variable Translation	66	85. Conversion Utility Invocation Panel (ISPCP01)	171
33. Prompt Locations	80	86. Panel ISPCP04	176
34. Prompt Widths	81	87. ISPF Dialog Tag Language Conversion Utility - Confirm Cancel	185
35. Data Fields	83	88. ISPF Dialog Tag Language Conversion Utility - Recursive invoke	186
36. Data Field Description	85	89. Entities and Parameter Entities	199
37. Single-Choice Selection Field	91	90. Action Bar	208
38. Multiple-Choice Selection Field	93	91. Action Bar Choices	210
39. Sample Option Menu	94	92. Application Panel Area	222
40. Selection Field SELWIDTH Attribute	97	93. Application Panel Area	222
41. Data Column	101	94. Application Panel Area	223
42. List Field	103	95. Attention Statement	228
43. List Group	104	96. Bottom Instructions	234
44. Scrollable Field	110	97. Caution Statement	236
45. Scrollable Field Within a List Column	111	98. Choice Divider	238
46. Paragraph	115	99. Choice Data Fields	255
47. Multiple Paragraphs	116	100. Selection Field Choices	262
48. Headings (H1-H2)	117	101. Command Area	273
49. LINES	118	102. Comment text added to a panel	277
50. XMP	119	103. Copyright statement added to a panel	280
51. Figure with Rules	120	104. Definition Descriptions	287
52. Figure Caption	121	105. Definition Description Header	289
53. Simple List	122	106. Area Dividers	292

107. Definition List (BREAK=NONE) . . . . .	295	139. List Variable . . . . .	388
108. Definition List (BREAK=FIT) . . . . .	295	140. Messages . . . . .	394
109. Definition List (BREAK=ALL) . . . . .	296	141. Message Member . . . . .	396
110. Definition List Dividers . . . . .	298	142. Note . . . . .	399
111. Definition Terms . . . . .	300	143. NOTEL . . . . .	401
112. PMTWIDTH, ENTWIDTH, FLDSpace, and DESWIDTH attributes . . . . .	304	144. NT . . . . .	404
113. Data Column . . . . .	306	145. Ordered Lists . . . . .	406
114. Data Fields . . . . .	316	146. Paragraphs . . . . .	408
115. Data Field Descriptions . . . . .	317	147. Application Panel . . . . .	424
116. Definition Term Divider . . . . .	319	148. Parameter List . . . . .	426
117. Definition Term Header . . . . .	320	149. Parameter Descriptions . . . . .	428
118. Definition Term Header Divider . . . . .	322	150. Pull-Down Choices . . . . .	432
119. Definition Term Segment. . . . .	324	151. Pull-Down Separator . . . . .	433
120. Figure . . . . .	326	152. Parameter List Divider . . . . .	436
121. Figure Caption . . . . .	327	153. Panel Instructions . . . . .	438
122. Generated Panel . . . . .	332	154. Point-and-Shoot Fields . . . . .	441
123. Group Heading . . . . .	335	155. Parameter Terms . . . . .	443
124. Help Panel (Example 1 of 3) . . . . .	342	156. Parameter Term Divider . . . . .	444
125. Help Panel (Example 2 of 3) . . . . .	343	157. Parameter Term Segment . . . . .	446
126. Help Panel (Example 3 of 3) . . . . .	343	158. Regions . . . . .	452
127. Headings . . . . .	348	159. Using WIDTH and DEPTH Attributes . . . . .	454
128. HP (Highlighted Phrase). . . . .	350	160. Reference Phrase Example . . . . .	456
129. Information Region . . . . .	352	161. Reference Phrase Example . . . . .	456
130. Key Items. . . . .	355	162. List Field . . . . .	463
131. Function Keys . . . . .	358	163. List Variable . . . . .	464
132. List Items . . . . .	360	164. Selection Fields . . . . .	478
133. LINES . . . . .	362	165. Selection Menu . . . . .	479
134. List Part . . . . .	366	166. Simple List . . . . .	481
135. List Columns . . . . .	375	167. Top Instructions. . . . .	491
136. List Columns . . . . .	377	168. Unordered List . . . . .	493
137. List Field . . . . .	382	169. Variable Substitution . . . . .	502
138. List Group . . . . .	385	170. Warning Statement. . . . .	504
		171. Example . . . . .	510

---

## Preface

This document describes how to use the Dialog Tag Language (DTL), the tag-based markup language you use to create the following ISPF dialog elements:

- Application panels
- Help panels
- Application command tables
- Messages
- Key lists.

It also explains how to use the ISPF conversion utility to convert the source files that contain DTL markup into ISPF panel language source or execution time format.

---

## About This Document

This document is organized into two sections:

- Part 1 guides you through the steps involved in using the Dialog Tag Language for designing, defining, and converting dialog elements for ISPF applications.
- Part 2 provides an alphabetical reference of the Dialog Tag Language tags and markup declarations.

---

## Who Should Use This Document

This document is for ISPF application developers who want to use the Dialog Tag Language (DTL) to create dialog elements for ISPF applications.

---

## Using LookAt to look up message explanations

LookAt is an online facility that lets you look up explanations for most of the IBM® messages you encounter, as well as for some system abends and codes. Using LookAt to find information is faster than a conventional search because in most cases LookAt goes directly to the message explanation.

You can use LookAt from the following locations to find IBM message explanations for z/OS® elements and features, z/VM®, VSE/ESA™, and Clusters for AIX® and Linux:

- The Internet. You can access IBM message explanations directly from the LookAt Web site at <http://www.ibm.com/eserver/zseries/zos/bkserv/lookat/>.
- Your z/OS TSO/E host system. You can install code on your z/OS or z/OS.e systems to access IBM message explanations, using LookAt from a TSO/E command line (for example, TSO/E prompt, ISPF, or z/OS UNIX® System Services running OMVS).
- Your Microsoft® Windows® workstation. You can install code to access IBM message explanations on the *z/OS Collection* (SK3T-4269), using LookAt from a Microsoft Windows command prompt (also known as the DOS command line).
- Your wireless handheld device. You can use the LookAt Mobile Edition with a handheld device that has wireless access and an Internet browser (for example, Internet Explorer for Pocket PCs, Blazer, or Eudora for Palm OS, or Opera for Linux handheld devices). Link to the LookAt Mobile Edition from the LookAt Web site.

You can obtain code to install LookAt on your host system or Microsoft Windows workstation from a disk on your *z/OS Collection* (SK3T-4269), or from the LookAt Web site (click **Download**, and select the platform, release, collection, and location that suit your needs). More information is available in the LOOKAT.ME files available during the download process.

---

## Summary of Changes

z/OS V1R6.0 ISPF contains the following changes and enhancements:

- ISPF Product and Library changes
- ISPF Dialog Manager component changes (including DTL changes)
- ISPF PDF Component changes
- ISPF SCLM Component changes
- ISPF Client/Server Component changes

---

### ISPF Product and Library changes

Changes to the ZENVIR variable. Characters 1 through 8 contain the product name and sequence number, in the format ISPF *x.y*, where *x.y* indicates the version number and release. Note that the *x.y* value is not necessarily the same as the operating system version. For example, a value of "ISPF 5.6" represents ISPF for z/OS Version 1 Release 6.0.

The ZOS390RL variable contains the level of the z/OS release running on your system.

The ZISPFOS system variable contains the level of ISPF that is running as part of the operating system release on your system. This might or might not match ZOS390RL. For this release of ISPF, the variable contains **ISPF for z/OS 01.06.00**.

---

### ISPF Dialog Manager component changes

The DM component of ISPF includes the following new functions and enhancements:

- The new \*REXX panel definition statement allows the inclusion of REXX code within a panel's )INIT, )REINIT, or )PROC sections to perform arithmetic, verification, transformation, translation, and formatting of dialog variables.
- Enhancements to ISPF File Tailoring:
  - Added support for continuation of control statements.
  - Increased maximum imbed levels from 3 to 15.
  - Increased maximum select levels from 8 to 32.
  - Increased the maximum number of parameters on a control statement from 31 to 63.
  - Eliminated exclusive SPFEDIT enqueue on a skeleton member when processing a skeleton.
  - Improved skeleton processing by reading skeleton records into storage.
  - Added support for the )DO ... )ENDDO control statements.
  - Added support for the )IF ... THEN ... )ELSE control statements.
  - Added )ITERATE and )LEAVE control words for use within )DO ... )ENDDO loops.
  - Added the )NOP control word, which can be used with a null )IF or )ELSE statement.
  - Added TBSCAN support to the )DOT control word.
- The restriction that Language Environment-enabled programming languages can not be used for ISPF exits has been partially removed. Exits can now be written

in languages that use the LE run-time environment, as long as all the dialogs and service routines are LE-conforming. A mixture of LE-conforming main dialog code and service routine code is not supported.

ISPF Configuration Utility changes:

- Added support for zero block size for dynamic allocation of the ISPLIST, ISPLOG, ISPCTL $x$ , ISPLST $x$ , and ISPWRK $x$  data sets.
- Added support for specifying primary and secondary space for the ISPCTL0 and ISPLST $x$  data sets.
- New keywords control what happens when an explicit member list request is made for an empty PDS/E:

```
DISPLAY_EMPTY_MEMBER_LIST  
DISPLAY_EMPTY_MEMBER_LIST_PATTERN  
DISPLAY_EMPTY_MEMBER_LIST_FUNCTION  
RESET_EMPTY_MEMBER_LIST_OPTIONS
```

## Dialog Tag Language (DTL) changes

There are no changes to Dialog Tag Language (DTL) for this release.

---

## ISPF PDF Component changes

The ISPF PDF component contains the following new functions and enhancements:

- The TBQUERY service has been enhanced to return information about TBSORT and the last TBSARG issued against a table.
- The new QTABOPEN service allows an ISPF dialog to obtain a list of currently open ISPF tables. The TBSTATS or TBQUERY service can then be used to obtain more detailed information about each table.
- A new Edit primary command, COLS, displays a non-scrolling columns line in Edit or View.
- A new Edit primary command and edit macro command, HIDE, removes the excluded lines messages from the display. RESET HIDE restores the excluded lines messages.
- The CUT Edit primary command and edit macro commands now support two new flags: X specifies to cut only excluded lines to the clipboard. NX specifies to cut only nonexcluded lines.
- The MODEL edit macro command now issues RC=4 if the model exceeds the right hand margin of the data being edited.
- The VOLUME edit macro command is changed to permit return of the volume serial where the original data set is stored.
- The CURSOR edit assignment statement has been changed as follows: if the cursor is in the command area, the cursor value is column 0 of the first data line on the panel.
- When saving a member list to a dataset using the SAVE primary command, the new keyword LONG formats all dates in yyyy/mm/dd format for the member.
- Documentation has been added for the OVOLUME parameter on the LMQUERY service.

---

## ISPF SCLM Component changes

The ISPF SCLM component contains the following new functions and enhancements:

- For each of the FLMCMD services a new panel has been added, providing the ability to select a service from a menu and then enter the service parameters in an ISPF interface panel. These panels can also be called directly, by entering the FLMCMD service command without parameters.
- The new Unit of Work utility allows you to use an ARCHDEF member as a member list from which you can use the standard SCLM functions such as select, edit, build, view build map, and promote. You can add your own customized line commands to work with the Unit of Work member List.
- The new SCLM Explorer utility provides the ability to select any architecture definition or part member and then navigate up or down the hierarchy of related ARCHDEFs or parts.

---

## ISPF Client/Server Component changes

The ISPF Client/Server Component enables a panel to be displayed unchanged (except for panels with graphic areas) at a workstation using the native display function of the operating system of the workstation. ISPF documents call this "running in GUI mode."

There are no changes to the ISPF Client/Server for this release.

---

## ISPF Migration Considerations

If you are migrating to z/OS V1R6.0 from an earlier release of z/OS or from OS/390 V2R10.0, no migration actions are needed. If you are migrating to z/OS V1R6.0 from an earlier release of OS/390, follow the migration actions for OS/390 V2R10.0.

When migrating from one version of ISPF to another, you must reassemble and relink the SCLM project definition.

### Note

This book contains terminology, maintenance, and editorial changes. Technical changes or additions to the text and illustrations are indicated by a vertical line to the left of the change.

Starting with z/OS V1R2, you may notice changes in the style and structure of some content in this book—for example, headings that use uppercase for the first letter of initial words only, and procedures that have a different look and format. The changes are ongoing improvements to the consistency and retrievability of information in our books.



---

## What's in the z/OS V1R6.0 ISPF library?

You can order the ISPF books using the numbers provided below.

---

### z/OS V1R6.0 ISPF

<b>Title</b>	<b>Order Number</b>
<i>z/OS V1R6.0 ISPF Dialog Tag Language Guide and Reference</i>	SC34-4824-03
<i>z/OS V1R6.0 ISPF Planning and Customizing</i>	GC34-4814-03
<i>z/OS V1R6.0 ISPF User's Guide Volume I</i>	SC34-4822-03
<i>z/OS V1R6.0 ISPF User's Guide Volume II</i>	SC34-4823-03
<i>z/OS V1R6.0 ISPF Services Guide</i>	SC34-4819-03
<i>z/OS V1R6.0 ISPF Dialog Developer's Guide and Reference</i>	SC34-4821-03
<i>z/OS V1R6.0 ISPF Reference Summary</i>	SC34-4816-03
<i>z/OS V1R6.0 ISPF Edit and Edit Macros</i>	SC34-4820-03
<i>z/OS V1R6.0 ISPF Messages and Codes</i>	SC34-4815-03
<i>z/OS V1R6.0 ISPF Software Configuration and Library Manager Project Manager's and Developer's Guide</i>	SC34-4817-03
<i>z/OS V1R6.0 ISPF Software Configuration and Library Manager Reference</i>	SC34-4818-03



---

## The ISPF User Interface

ISPF provides an action bar-driven interface that exploits many of the usability features of Common User Access<sup>®</sup> (CUA<sup>®</sup>) interfaces. Refer to *Object-Oriented Interface Design: IBM Common User Access Guidelines* for additional information.

These action bars give you another way to move around in ISPF, as well as the ability to nest commands. Command nesting allows you to *suspend* an activity while you perform a new one rather than having to end a function to perform another function.

This chapter primarily explains the action bar-driven interface and the use of ISPF's graphical user interface (GUI).

---

## Some Terms You Should Know

The following terms are used in this document:

### **action bar**

The area at the top of an ISPF panel that contains choices that give you access to actions available on that panel. When you select an action bar choice, ISPF displays a *pull-down menu*.

### **function key**

In previous releases of ISPF, a programmed function (PF) key. *This is a change in terminology only.*

### **mnemonics**

Action bar choices can be defined with a underscored letter in the action bar choice text. In host mode you can access the action bar choice with the ACTIONS command and parameter *x*, where *x* is the underscored letter in the action bar choice text. In GUI mode you can use a *hot key* to access a choice on the action bar; that is, you can press the ALT key in combination with the letter that is underscored in the action bar choice text.

### **modal pop-up window**

A type of window that requires you to interact with the panel in the pop-up before continuing. This includes canceling the window or supplying information requested.

### **modeless pop-up window**

A type of window that allows you to interact with the dialog that produced the pop-up before interacting with the pop-up itself.

### **point-and-shoot text**

Text on a screen that is cursor-sensitive. See "Point-and-Shoot Text Fields" on page xxiv for more information.

### **pop-up window**

A bordered temporary window that displays over another panel.

### **pull-down menu**

A list of numbered choices extending from the selection you made on the action bar. The action bar selection is highlighted; for example, Utilities in Figure 1 on page xxi appears highlighted on your screen. You can select an action either by typing in its number and pressing Enter or by selecting the action with your cursor. ISPF displays the requested panel. If your choice

## The ISPF User Interface

contains an ellipsis (...), ISPF displays a *pop-up window*. When you exit this panel or pop-up, ISPF closes the pull-down and returns you to the panel from which you made the initial action bar selection.

### push button

A rectangle with text inside. Push buttons are used in windows for actions that occur immediately when the push button is selected (available only when you are running ISPF in GUI mode).

**select** In conjunction with point-and-shoot text fields and action bar choices, this means moving the cursor to a field and simulating Enter.

---

## How to Navigate in ISPF Using the Action Bar Interface

Most ISPF panels have action bars at the top; the choices appear on the screen in white by default. Many panels also have point-and-shoot text fields, which appear in turquoise by default. The panel shown in Figure 3 on page xxii has both.

### Action Bars

Action bars give you another way to move through ISPF. If the cursor is located somewhere on the panel, there are several ways to move it to the action bar:

- Use the cursor movement keys to manually place the cursor on an action bar choice.
- Type ACTIONS on the command line and press Enter to move the cursor to the first action bar choice.
- Press F10 (Actions) or the Home key to move the cursor to the first action bar choice.

If mnemonics are defined for action bar choices, you can:


- In 3270 mode, on the command line, type ACTIONS and the mnemonic letter that corresponds to an underscored letter in the action bar choice text. This results in the display of the pull-down menu for that action bar choice.
- In 3270 mode, on the command line enter the mnemonic letter that corresponds to an underscored letter in the action bar choice text, and press the function key assigned to the ACTIONS command. This results in the display of the pull-down menu for that action bar choice.
- In GUI mode, you can use a *hot key* to access a choice on an action bar or on a pull-down menu; that is, you can press the ALT key in combination with the mnemonic letter that is underscored in the choice text to activate the text.

Use the tab key to move the cursor among the action bar choices. If you are running in GUI mode, use the right and left cursor keys.

### Notes:

1. ISPF does not provide a mouse emulator program. This document uses *select* in conjunction with point-and-shoot text fields and action bar choices to mean moving the cursor to a field and simulating Enter.
2. Some users program their mouse emulators as follows:
  - Mouse button 1 – position the cursor to the pointer and simulate Enter
  - Mouse button 2 – simulate F12 (Cancel).
3. If you want the Home key to position the cursor at the first input field on an ISPF panel, type SETTINGS on any command line and press Enter to display the ISPF Settings panel. Deselect the **Tab to action bar choices** option.
4. If you are running in GUI mode, the Home key takes you to the beginning of the current field.

When you select one of the choices on the action bar, ISPF displays a pull-down menu. Figure 1 shows the pull-down menu displayed when you select Options on the ISPF Primary Option Menu action bar.



**1** The selected action bar choice is highlighted.

Figure 1. Panel with an Action Bar Pull-Down Menu

To select a choice from the Options pull-down menu, type its number in the entry field (underlined) and press Enter or select the choice. To cancel a pull-down menu without making a selection, press F12 (Cancel). For example, if you select choice 6, ISPF displays the Dialog Test Application ID pop-up, as shown in Figure 2 on page xxii.

**Note:** If you entered a command on the command line prior to selecting an action bar choice, the command is processed, and the pull-down menu is never displayed. The CANCEL, END, and RETURN commands are exceptions. These three commands are not processed and the cursor is repositioned to the first input field in the panel body. If there is no input field, the cursor is repositioned under the action bar area. If you are running in GUI mode and select an action bar choice, any existing command on the command line is ignored.

## The ISPF User Interface





Figure 2. Pop-Up Selected from an Action Bar Pull-Down



- 1** Action bar. You can select any of the action bar choices and display a pull-down.
- 2** Options. The fields in this column are point-and-shoot text fields.
- 3** Dynamic status area. You can specify what you want to be displayed in this area.

Figure 3. Panel with an Action Bar and Point-and-Shoot Fields

## Command Nesting

You can use the action bars to *suspend* an activity while you perform a new one.

For example, if you are editing a data set and want to allocate another data set, select the Data set choice from the Utilities pull-down on the Edit panel action bar.

ISPF suspends your edit session and displays the Data Set Utility panel. When you have allocated the new data set and ended the function, ISPF returns you directly to your edit session.

By contrast, if you used the jump function (=3.2), ISPF would end your edit session before displaying the Data Set Utility.

### Action Bar Choices

The action bar choices available vary from panel to panel, as do the choices available from their pull-downs. However, Menu and Utilities are basic action bar choices, and the choices on their pull-down menus are always the same.

#### Menu Action Bar Choice

The following choices are available from the Menu pull-down:

<b>Settings</b>	Displays the ISPF Settings panel
<b>View</b>	Displays the View Entry panel
<b>Edit</b>	Displays the Edit Entry panel
<b>ISPF Command Shell</b>	Displays the ISPF Command Shell panel
<b>Dialog Test...</b>	Displays the Dialog Test Primary Option panel
<b>Other IBM Products...</b>	Displays the Additional IBM Program Development Products panel
<b>SCLM</b>	Displays the SCLM Main Menu
<b>ISPF Workplace</b>	Displays the Workplace entry panel
<b>Status Area...</b>	Displays the ISPF Status panel
<b>Exit</b>	Exits ISPF.

**Note:** If a choice displays in blue (the default) with an asterisk as the first digit of the selection number (if you are running in GUI mode, the choice will be *grayed*), the choice is unavailable for one of the following reasons:

- Recursive entry is not permitted here
- The choice is the current state; for example, RefMode is currently set to Retrieve in Figure 4 on page xxiv.

## The ISPF User Interface

```

Menu  RefList  RefMode  Utilities  Workstation  Help
      1  1. List Execute  ry Panel
      *  *. List Retrieve  More:  +

ISPF Library:
Project . . . . PDFTDEV
Group . . . . STG
Type . . . . GML
Member . . . . (Blank or pattern for member selection list)

Other Partitioned, Sequential or VSAM Data Set:
Data Set Name . . . .
Volume Serial . . . . (If not cataloged)

Workstation File:
File Name . . . .

Initial Macro . . . . Options
Profile Name . . . . / Confirm Cancel/Move/Replace
Format Name . . . . Browse Mode
Data Set Password . . . . View on Workstation
Command ==> / Warn on First Data Change
F1=Help F2=Split F3=Exit F7=Backward F8=Forward F9=Swap
F10=Actions F12=Cancel

```

Figure 4. An Unavailable Choice on a Pull-Down

### Utilities Action Bar Choice

The following choices are available from the Utilities pull-down:

<b>Library</b>	Displays the Library Utility panel
<b>Data Set</b>	Displays the Data Set Utility panel
<b>Move/Copy</b>	Displays the Move/Copy Utility panel
<b>Data Set List</b>	Displays the Data Set List Options panel
<b>Reset Statistics</b>	Displays the Reset ISPF Statistics panel
<b>Hardcopy</b>	Displays the Hardcopy Utility panel
<b>Download...</b>	Displays the panel that enables you to download workstation clients and other files from the host.
<b>Outlist</b>	Displays the Outlist Utility panel
<b>Commands...</b>	Displays the Command Table Utility panel
<b>Reserved</b>	Reserved for future use by ISPF; an unavailable choice
<b>Format</b>	Displays the Format Specification panel
<b>SuperC</b>	Displays the SuperC Utility panel
<b>SuperCE</b>	Displays the SuperCE Utility panel
<b>Search-for</b>	Displays the Search-For Utility panel.
<b>Search-forE</b>	Displays the Search-ForE Utility panel.

### Point-and-Shoot Text Fields

*Point-and-shoot* text fields are cursor-sensitive; if you select a field, the action described in that field is performed. For example, if you select Option 0, Settings, in Figure 3 on page xxii, ISPF displays the ISPF Settings panel.

**Note:** If you have entered a command on the command line, this command is processed before any point-and-shoot command unless you are running in GUI mode.

The cursor-sensitive portion of a field often extends past the field name. Until you are familiar with this new feature of ISPF, you might want to display these fields in reverse video (use the PSCOLOR command to set Highlight to REVERSE).

**Note:** You can use the Tab key to position the cursor to point-and-shoot fields by selecting the **Tab to point-and-shoot fields** option on the ISPF Settings panel (Option 0).

### Function Keys

ISPF uses CUA-compliant definitions for function keys F1–F12 (except inside the Edit function). F13–F24 are the same as in ISPF Version 3. By default you see the CUA definitions because your **Primary range** field is set to 1 (Lower - 1 to 12).

To use non-CUA-compliant keys, select the **Tailor function key display** choice from the Function keys pull-down on the ISPF Settings (option 0) panel action bar. On the Tailor Function Key Definition Display panel, specify 2 (Upper - 13 to 24) in the **Primary range** field.

The following function keys help you navigate in ISPF:

- F1**     **Help.** Displays Help information. If you press F1 (and it is set to Help) after ISPF displays a short message, a long message displays in a pop-up window.
- F2**     **Split.** Divides the screen into two logical screens separated by a horizontal line or changes the location of the horizontal line.  
  
           **Note:** If you are running in GUI mode, each logical screen displays in a separate window.
- F3**     **Exit** (from a pull-down). Exits the panel underneath a pull-down.
- F3**     **End.** Ends the current function.
- F7**     **Backward.** Moves the screen up the scroll amount.
- F8**     **Forward.** Moves the screen down the scroll amount.
- F9**     **Swap.** Moves the cursor to where it was previously positioned on the other logical screen of a split-screen pair.
- F10**    **Actions.** Moves the cursor to the action bar. If you press F10 a second time, the cursor moves to the command line.
- F12**    **Cancel.** Issues the Cancel command. Use this command to remove a pull-down menu if you do not want to make a selection. F12 also moves the cursor from the action bar to the Option ==> field on the ISPF Primary Option Menu. See *ISPF Dialog Developer's Guide and Reference* for cursor-positioning rules.
- F16**    **Return.** Returns you to the ISPF Primary Option Menu or to the display from which you entered a nested dialog. RETURN is an ISPF system command.

### Selection Fields

z/OS V1R6.0 ISPF uses the following CUA-compliant conventions for selection fields:

#### A single period (.)

Member lists that use a single period in the selection field recognize only a single selection. For example, within the Edit function you see this on your screen:

```
EDIT      USER1.PRIVATE.TEST          ROW 00001 of 00002
Name      VV MM Created   Changed  Size Init Mod  ID
. MEM1    01.00 94/05/12 94/07/22 40  0  0  USER1
. MEM2    01.00 94/05/12 94/07/22 30  0  0  KEENE
```

You can select only one member to edit.

#### A single underscore (\_)

Selection fields marked by a single underscore prompt you to use a slash (/) to select the choice. You may use any nonblank character. For example, the **Panel display CUA mode** field on the ISPF Settings panel has a single underscore for the selection field:

```
Options
Enter "/" to select option
_ Command line at bottom
_ Panel display CUA mode
_ Long message in pop-up
```

**Note:** In GUI mode, this type of selection field displays as a check box; that is, a square box with associated text that represents a choice. When you select a choice, the check box is filled to indicate that the choice is in effect. You can clear the check box by selecting the choice again.

#### An underscored field (\_\_\_)

Member lists or text fields that use underscores in the selection field recognize multiple selections. For example, from the Display Data Set List Option panel, you may select multiple members for print, rename, delete, edit, browse, or view processing.

---

## How to Navigate in ISPF without Using Action Bars

If you use a non-programmable terminal to access z/OS V1R6.0 ISPF and you do not want to take advantage of the command nesting function, you can make selections the same way you always have: by typing in a selection number and pressing Enter.

---

## Part 1. Guide to the Dialog Tag Language (DTL)

This section contains the following chapters:

**Chapter 1, “Introduction to the Dialog Tag Language (DTL)”** contains an introduction to the Dialog Tag Language (DTL) and descriptions of the dialog elements you define with the Dialog Tag Language. A brief description of the ISPF Conversion Utility is also included.

**Chapter 2, “How to Use the Dialog Tag Language (DTL)”** explains the syntax conventions of the Dialog Tag Language.

**Chapter 3, “Getting Started: Designing Application Panels”** tells you how to design application panels.

**Chapter 4, “Variables and Variable Classes”** tells you how to declare variables, define variable classes, and validate variables.

**Chapter 5, “Application Panel Fields”** tells you how to define interactive fields for application panels.

**Chapter 6, “Information Regions and Help Panels”** tells you how to define information regions and help panels.

**Chapter 7, “Messages”** tells you how to define messages.

**Chapter 8, “The Application Command Table”** tells you how to define application commands and the application command table.

**Chapter 9, “Defining Key Mapping Lists”** tells you how to define key mapping lists.

**Chapter 10, “Using the Conversion Utility”** describes the steps involved in converting your DTL source files into ISPF panel language source format or executable pre-processed ISPF format.



---

## Chapter 1. Introduction to the Dialog Tag Language (DTL)

This document introduces you to the Dialog Tag Language (DTL), a tag-based language used to define many of the elements that make up the type of application known as a *dialog*, the communication between a person and a computer. We tell you how to define these elements using DTL and how to prepare them for use in your ISPF applications.

The elements you produce with DTL are used by ISPF as the user interface for your ISPF applications. The programs you write using ISPF services and a programming language use the dialog elements you create for an application.

This chapter provides an overview of DTL, and the dialog elements you create with DTL. We introduce you to DTL by discussing the following main topics:

- **Why the Dialog Tag Language?**

This section talks about why you would want to use DTL to create elements for ISPF applications.

- **What is the Dialog Tag Language?**

This section explains what the Dialog Tag Language is and how it works.

- **Dialog elements**

This section provides descriptions and examples of the dialog elements. These elements are:

- Application panels
- Help panels
- Messages
- An application command table
- Key mapping lists.

- **Variables and variable classes**

This section discusses the definition of variables you include in dialog element definitions.

- **What is the ISPF Conversion Utility?**

This section provides a description of the conversion utility, the compiler you use to convert your DTL source files for use by ISPF.

---

### Why the Dialog Tag Language (DTL)?

If you are already familiar with a tag-based markup language, such as IBM BookMaster<sup>®</sup> or HTML (Hypertext Markup Language), you will find that DTL is very similar. We created DTL for many of the same reasons that we created BookMaster:

- Markup tags are easy to use. Because tag names are short and relate directly to the structure of the dialog elements, they are also easy to remember.
- DTL lends flexibility to application development. Panels can be quickly changed without your having to tediously line up text and fields. This gives you greater control over application development and updates.
- DTL provides consistency when many programmers are working on the same application, or when programmers who are new to your company must update existing applications. Since each programmer is using the same tags, only minor adjustments may be needed to achieve complete uniformity.

- DTL techniques improve the way in which interactive programs, like ISPF applications, are developed. The language concentrates on the role of the various elements and their interrelationships, and ISPF takes care of their form and appearance at run time.
- DTL also enforces some formatting rules defined by the Systems Application Architecture<sup>®</sup> Common User Access (CUA), so you do not have to be familiar with all of the CUA formatting rules. Therefore, the CUA skills required by programmers who are developing CUA-conforming applications are significantly reduced.
- DTL enables National Language Support (NLS) and the conversion utility provides NLS translations for certain key words.

In other words, if you are looking for an application development and maintenance system that is sophisticated, flexible, and easy to use, that's DTL.

Examples of DTL usage by ISPF have been shipped in data set 'ISP.SISPGxxx', where xxx is a standard ISPF language identifier. Consult your ISPF system administrator for the actual location of these examples.

---

## What Is the Dialog Tag Language?

In Why the Dialog Tag Language (DTL)? we referred to DTL as a tag-based markup language that is similar to IBM BookMaster. The two have much in common. For example, *markup* is a term that is usually associated with documentation. It is an old typesetter's term that formerly meant the instructions with which a document was "marked up" to show how the document should be set in type.

Today, this definition has been expanded to include information that is added to a document to enable a person or system to process it. Just as markup information can describe a document's characteristics or the processing to be performed, it can also describe the characteristics or processing related to dialog elements. This is where the tags come in.

We call DTL a *tag-based* markup language simply because the markup consists of tags that determine not only what each element is, but also how it is processed. To convert the dialog elements into a format that is usable by ISPF, you must convert them to ISPF elements with ISPDTLC, the ISPF conversion utility. (See "What Is the ISPF Conversion Utility?" on page 9 for more information.)

Another thing that DTL and BookMaster have in common, of course, is the tags themselves, which have the following similarities:

- They are very short and easy to remember.
- They are often accompanied by text.
- Many DTL tags are almost identical to corresponding BookMaster tags.

These are all reasons that familiarity with BookMaster will make it easy to learn DTL. For example, we could have created the preceding bulleted, or *unordered* list in BookMaster by editing a file using an editor and typing the following:

```
:ul compact.
  :li.They are very short and easy to remember.
  :li.They are often accompanied by text.
  :li.Many DTL tags are almost identical to corresponding BookMaster tags.
:eul.
```

You could create a similar list for an information panel by using the following DTL tags with the same text:

```
<ul compact>
  <li>They are very short and easy to remember.
  <li>They are often accompanied by text.
  <li>Many DTL tags are almost identical to corresponding BookMaster tags.
</ul>
```

Here, the `<ul >` and `</ul >` tags, respectively, begin and end the unordered list. This type of list is called an unordered list because the list items are not numbered. The individual list items are defined by the `<li >` tags and consist of the accompanying text.

As you can see from the preceding example, DTL tags act as control words that specify how the text of source files is interpreted by the conversion utility. This concept is based on the Standard Generalized Markup Language (SGML), which is a standard of the International Standards Organization (ISO). The conventions of the Dialog Tag Language are based on the SGML standard.

After you are finished marking up a source file, you use the conversion utility to convert the file into a format usable by your ISPF application. In addition to processing the file, the conversion utility also checks and verifies the syntax of your markup, and notifies you of any errors. After conversion, the elements you defined in your source file are stored within ISPF libraries.

You can use ISPF dialog test facilities to display application panels and messages after they have been converted. Displaying your panels is a good idea to make sure they format properly.

You should now have a basic understanding of DTL and how it works. The next section builds on this understanding by describing the types of elements that you can define with DTL.

---

## Dialog Elements

This section provides a descriptive overview of the dialog elements you can create for an ISPF application. These elements include:

- Application panels
- Help panels
- Messages
- An application command table
- Key mapping lists.

### Application Panels

Application panels are the primary element of the user interface for an application. They allow users to interact with your application through the use of data fields, selection fields, and other interactive fields. Application panels appear in primary and pop-up windows.

Figure 5 on page 6 shows a full-screen application panel. Following that is a list of the elements that make up an application panel.




Figure 5. Application Panel

## Application Panel Elements

### Action bar

The action bar appears in the top portion of the panel. It contains keyword choices that provide users access to available actions for the current panel. When the user selects an action bar choice, a pull-down containing choices appears directly below the action bar choice.

### Panel title

The panel title appears below the action bar.

### Panel body

The panel body serves as the main work area of the panel. The panel body contains the input and output fields, selection fields, and other text.

Additionally, the panel body can contain optional top and bottom instructions, which provide instructional text to the user. Top instructions appear below the panel title and above the interactive fields on the panel. Top instructions tell the user how to interact with the panel. Bottom instructions appear below the interactive fields on the panel. Bottom instructions tell the user how to interact with the panel, or how to continue with the application.

### Message area

The message area appears below the panel body.<sup>1</sup> ISPF uses the message area (or message pop-ups) to display messages to users while they are working in the panel.

### Command area

The optional command area (or command line), which appears at the bottom of the panel, consists of two components: the command field

1. The message area and the command area for panels defined with DTL appear at the bottom of the panel if the user has selected the Command line at bottom option on the ISPF Settings panel, or the application has set ZPLACE to BOTTOM. For additional information on placement options, refer to the discussion of the ISPF Settings panel in the *ISPF User's Guide*.

prompt and the command entry field. <sup>1</sup> Application users can use the command entry field to enter commands or requests to the ISPF application.

### Function key area

The optional function key area, which appears at the bottom of the panel immediately below the command area (if one is defined), contains the key assignments for dialog actions valid for the application panel. The user can request that function keys not be displayed.

Chapter 3, “Getting Started: Designing Application Panels,” on page 27 tells you how to define application panels and panel elements.

## Help Panels

Help panels appear in pop-up windows in response to user requests for assistance during ISPF application sessions. ISPF processes these help requests and displays the help panels.

Using DTL, you can create help panels that provide help for:

- An entire application panel (extended help or panel help)
- A specific field on an application panel (contextual help or field help)
- Messages (message help)
- The function key area (keys help).

Figure 6 illustrates a help panel. Following that is a list that defines each of the elements that make up a help panel.




Figure 6. Help Panel

## Help Panel Elements

### Help panel title

The help panel title appears at the topmost portion of the panel, followed by a blank line separating the panel title from the panel body. If the help panel text exceeds the defined depth of the help panel, a scrolling indicator appears in the right margin of the blank line following the panel title.

### Help panel body

The help panel body contains the text of the help panel.

Text within the help panel is protected, which means that the user cannot interact with the text. You define this static text within an *information region* in the panel definition.

### Function key area

If you are creating a help panel that does not end with a scrollable area, note that ISPF reserves 4 lines at the bottom of the panel for function keys. The display of keys in the function key area is controlled by the user through the ISPF FKA command.

Chapter 6, “Information Regions and Help Panels,” on page 113 tells you how to define help panels and information regions.

## Messages

You can use DTL to define messages that display in response to a user request or action, or that provide additional information. Messages can confirm a user-requested action, report an error in user input, or notify the user of an error or exception condition. Figure 7 illustrates a message displayed in the message area of an application panel (highlighting added).

```
File Search Help
-----
Library Card Registration

Type in patron's name and card number if applicable.

Then, select an action bar choice.

Date . . . : 12/29/90
Card No. . . _____ (A 7-digit number)
Name . . . . _____ (Last, First, M.I.)
Address . . _____

Choose one of the following          Check valid branches
— 1. New                            _ North Branch
  2. Renewal                         _ South Branch
  3. Replacement                     _ East Branch
                                      _ West Branch

You must type your name in the Name field.
Enter a command ==> _____
F1=Help      F2=Split      F3=Exit      F6=KEYSHELP  F9=Swap
F12=Cancel
```

Figure 7. Message Displayed in Message Area

The messages you define for an application are stored within *message members*. You use DTL to define the messages and message members.

Chapter 7, “Messages,” on page 155 provides a complete description of defining messages and message members.

## Application Command Table

You can use DTL to define commands that perform actions requested by the user. The valid commands for an application are defined and stored within an internal application command table. You can define only one command table for an application.

Valid commands include those assigned to pull-down choices, function keys, and commands entered in command entry fields.

Chapter 8, “The Application Command Table,” on page 161 tells you how to define commands and application command tables.

## Key Mapping Lists

The key assignments that are active for an application are defined and stored within key mapping lists. These key assignments allow the user to request commands and other actions through the use of function keys. Key assignments for your application are displayed in the function key area of application panels.

Chapter 9, “Defining Key Mapping Lists,” on page 167 tells you how to define key assignments and key mapping lists.

---

## Variables and Variable Classes

Variables are used to communicate information between an application and the user. Each variable you define for a DTL-defined dialog element can be *declared*, or identified, within a variable list. In addition, each variable can be associated with a variable class that defines its type and length characteristics. The variable class can also be used to define translations and validity checks that are used when a value is displayed on a panel or entered by a user.

Chapter 4, “Variables and Variable Classes,” on page 57 tells you how to declare variables and define variable classes.

---

## What Is the ISPF Conversion Utility?

ISPD TLC is the ISPF conversion tool that converts Dialog Tag Language (DTL) source files to ISPF panel language source format or executable preprocessed ISPF format. ISPF provides you with an invocation panel that allows you to specify a number of options for the conversion, or you can use conversion utility command syntax from the command line of your terminal. Chapter 10, “Using the Conversion Utility,” on page 171 provides a complete description of both methods.



---

## Chapter 2. How to Use the Dialog Tag Language (DTL)

This chapter describes the tag syntax conventions and mark-up declarations of the Dialog Tag Language (DTL). It also explains how to use the DTL to create dialog element source files for your ISPF applications.

The markup style of DTL is based on the International Standards Organization (ISO) Standard Generalized Markup Language (SGML). Markup languages allow you to specify, through the use of tags, how the text of a file is to be formatted for use by an application. Because DTL is a markup language, you must follow special rules and conventions when using it to define dialog elements.

---

### Syntax Conventions

The DTL tags act as control words that determine how the text in the source files is used. Each tag is enclosed within a set of delimiter symbols that distinguish the tag as a control word (as opposed to general text). *Start* tags, which initiate text interpretation, are preceded by the start tag open delimiter (<) and followed by the close delimiter (>). *End* tags, which explicitly end text interpretation, are preceded by the end tag open delimiter (</) and followed by the close delimiter (>).

For example, the DTL tags used for defining the beginning and end of an application panel are the PANEL tag and its matching end tag, which look like this:<sup>2</sup>

```
<panel>  
</panel>
```

DTL tags are free-form. Indentation of nested tags can be helpful for DTL source file readability.

All of the text that you define between a start and end tag is the tag *definition*. The DTL tag data extends to the right boundary of the source file. Therefore, DTL source files cannot contain line sequence numbers. The characteristics of the tag determine how the text or other tags coded within the tag definition will be formatted.

### Attributes and Values

Many DTL start tags contain *attributes* and *values* that define various physical and operating characteristics of the dialog elements. While most attributes and values are optional, or contain default settings, some are required.

For example, the PANEL tag has a required NAME attribute that must be specified to identify the panel. The value you assign to the NAME attribute must be unique for each panel in a source file. This PANEL tag has the NAME value "panel1":

```
<panel name=panel1>  
</panel >
```

---

2. End tags are not required for all of the DTL tags. In many cases, the tag is implicitly ended by other start tags. For this reason, we don't use optional end tags in the markup examples in this document. Chapter 13, "Tag Reference," on page 205 contains a detailed description of each of the DTL tags, including which tags require an end tag.

The PANEL tag also has two optional attributes, DEPTH and WIDTH, whose values specify the dimensions of the panel. For these types of attributes, you specify a numeric value.

```
<panel name=panel1 depth=20 width=40>  
</panel >
```

Values for some of the tag attributes are predetermined; that is, you can choose from one of a number of keyword values for the tag. For example, the FIG (figure) tag has a FRAME attribute that specifies the top and bottom borders of the figure. The value you assign to the FRAME attribute can be either RULE, which produces a visible border above and below the figure, or NONE, which results in a figure without a border. No other value is acceptable for the FRAME attribute.

RULE is the default value, which means that the figure formats with visible borders if you do not specify the FRAME attribute.

The markup for a figure without ruled borders looks like this:

```
<fig frame=none>  
</fi g>
```

When coding values for attributes, you must use single or double quotes to enclose values that contain characters other than A–Z, a–z, 0–9, a hyphen (–), or a period (.).

For example, the value assigned to the TYPE attribute of this VARCLASS tag contains a blank, so the value must be enclosed in quotes:

```
<varclass name=boolean type='char 1'>
```

Some attributes can be assigned either a specific value, such as a number or a character string, or a variable name. To distinguish a variable name from a specific value, precede the variable name with a percent (%) sign. This convention is called *% notation*. The percent sign distinguishes the variable name from a specific value. To specify a string that begins with a %, you must code an additional % before the string to distinguish it from a variable name. (For example, to specify the string %"abc", code "%%abc").

The ACTION attribute in the following example uses % notation to specify a variable named "varname":

```
<cmdact action='%varname'>
```

The length of any attribute value is limited to 253 characters, unless stated otherwise. This includes the lengths of any entity references that are a part of the value.

Generally, you can code tags, attributes, and values in uppercase, lowercase, or mixed case; the results are always the same regardless of case. The conventions you must follow for case-sensitive processing for each tag are described in Chapter 13, "Tag Reference," on page 205.

## Tag Text

The content or text of a tag is coded immediately following the start tag. This is the actual text that is subject to formatting and translation. The text is processed according to the type of tag it follows.

For example, the text following this P (paragraph) tag is the actual text that appears in the panel after formatting:

```
<p>The copy command allows you to copy  
single or multiple forms.
```

Because the tag text is processed according to the tag characteristics, not the way it is written in the source file, the paragraph could also be marked up using more than one line, like this:

```
<p>  
The copy command allows you to  
copy single or multiple forms.
```

The formatted result is the same in either case.

In most cases, there is no limit to the amount of text you can code. However, keep in mind that the text of some tags, such as the title of a PANEL tag, should be limited because of size constraints of the panel they are coded within. Chapter 13, “Tag Reference,” on page 205 describes text length restrictions (if they exist) for each of the tags.

In most cases, multiple lines of text are concatenated. Concatenation, leading blanks, and trailing blanks are processed as follows:

- Leading and trailing blanks between lines of text are not preserved. Instead, they are compressed to a single blank when the lines are concatenated.
- The first line of tag text may start on the same line as the start tag, or on the next line. The formatted result is the same.

The text of some tags, such as the FIG, LINES, and XMP tag, allow you to control where lines break. That is, within the range of the tag, each output line is ended at the same point that you ended the input line. With these tags, multiple lines are not concatenated, and all blanks are preserved.

## Text Formatting

ISPF determines if the text is to be formatted according to English rules or Asian rules, based on the language specified on the conversion utility invocation. If the language is JAPANESE, CHINESE, CHINESE, or KOREAN, ISPF will use the Japanese, Traditional Chinese, Simplified Chinese, or Korean text formatting rules, respectively. If JAPANESE language is specified and the KANA option is also specified, ISPF uses the Japanese Katakana formatting rules. Otherwise, the English formatting rules are used.

### English Rules for Text Formatting

Text exceeding the width of the available panel space is wrapped to the next line. The text is split at blanks. However, if any word exceeds the panel space, then the word splits and continues on the next line.

### Asian Rules for Text Formatting

Some characters should not be placed at the beginning of a line, and some should not be placed at the end of a line. These beginning-and-ending inhibited characters are different among the languages but the required process is the same. Thus, ISPF uses the same text formatting process for these Asian languages, but uses a different beginning-and-ending inhibitor character table for each of the languages.

The text is first split into *words*. An SBCS *word* is delimited by blanks, or SO/SI characters. Then any beginning inhibitors are stripped from the beginning of the

word and treated as separate words, and any ending inhibitors are stripped from the end of the word and treated as separate words.

Adjoining DBCS alphanumeric characters (that is, Ward 42 characters) are treated as one DBCS *word*. Then any beginning inhibitors are stripped from the beginning of the word and treated as separate words, and any ending inhibitors are stripped from the end of the word and treated as separate words. All other non-Ward 42 double-byte characters are treated as separate DBCS *words*.

If a word exceeds the available panel space, then the word splits and continues on the next line. If the text consists of mixed data and does not fit in one line within the specified width, the first position will always be reserved for a SO character (if first word is double-byte) or for a blank (if the first word is single-byte). This allows the text to be aligned properly.

Words that exceed the width of the available panel space are wrapped to the next line according to following rules:

... CE-1 CE				
CB CB+1 ...				

CE-1	CE	CB	CB+1	Process
any	B,X	B	X,E	Backward
E	E	X,B	X,E	Backward
X,B	E	any	any	Forward
X,B	X	B	B	Forward
_____	any other	_____		No process

Figure 8. Text Formatting Rules

Where:

- CE-1 and CE** Last two words that fit on line
- CB and CB+1** First two words on next line
- E** Ending inhibitor
- B** Beginning inhibitor
- X** Neither
- Forward** Move CE to next line
- Backward** Move CB to previous line
- No process** Split as is

**Note:** If words CE or CB are single-byte words and are more than 1 character, or if CE or CB are double-byte words and are more than 1 double-byte character, then no special processing is used; the line is split as is.

When your panel contains several successive lines of mixed data from different tags, the alignment of a short text string can appear to be shifted 1 byte further left than the surrounding text. This occurs because a text string that fits on one line does not have the leading position reserved for the SO character to use as many positions on the screen as possible.

You can control the alignment of successive lines of mixed data by adding a string of DBCS blanks to the end of a short text string. This forces the SO character position to be reserved during formatting.

SBCS and DBCS blanks that end or begin a line will be deleted.

## Nesting tags

It is often necessary to code certain tags (and their text) within the definition of other tags (between the start and end tags). This is called *nesting*.

A good example of nesting is the relationship between the DL (definition list) tag, the DT (definition term) tag, and the DD (definition description) tag. The DL tag specifies a definition list and the DT and DD tags specify the terms and descriptions of the items within the definition list. Consequently, the DT and DD tags must be nested within a DL tag and its matching end tag if the list is to format properly.

Here is an example:<sup>3</sup>

```
<dl >
  <dt>This is a definition term.
  <dd>This is a definition description.
  <dt>Another term.
  <dd>Another description.
</dl >
```

There are several tags that must be nested within the actual text of another start tag. These tags serve to identify a condition for the text. In this example, the nested CMD tag follows the CMDTBL start tag and precedes the CMDTBL end tag. The T (truncation) tag nested within the text of the CMD tag provides truncation of the command text.

```
<CMDTBL APPLID=conv>
  <CMD NAME=delete>Del <T>ete
  <CMDACT ACTION=setverb>
</CMDTBL>
```

Nesting tags can take on many different forms and can be complex. For example, some tags allow multiple tags or multiple occurrences of the same tag to be nested, while other tags do not allow nesting of any tags. You can also nest levels of certain tags, that is, nested tags within other nested tags. Additionally, in many instances, you must nest certain tags within other tags. The tag descriptions in Chapter 13, "Tag Reference," on page 205 describe the allowed and required conditions for nesting each of the DTL tags.

### Including Comments in the Generated Panel or Message Member

You can use the COMMENT tag to add comments to the generated panel or message member file. The TYPE attribute specifies the panel section for the comment. TYPE = END is automatically used for message member processing. You provide the comment text in a manner similar to the paragraph tag. ISPD TLC flows the text to a width of 66 bytes and adds "/\* " before and " \*/" after each resulting comment line.

### Including Copyright Statements in the Generated Panel or Message Member

You can use the COPYR tag to add a copyright statement to the generated panel or message member. The copyright statement is placed in the panel immediately following the )END panel section line, or immediately following the last message in the message member. The text of the COPYR tag is limited to 66 bytes. ISPD TLC adds "/\* " before and " \*/" after the copyright text. Each COPYR tag adds one line to the generated panel.

---

3. Although it isn't required, we indented the nested tags in this example to illustrate nesting levels. You can also do this in your own source files.

---

## Markup Declarations

In addition to tag markup, you can also include *markup declarations* in your source files to define other, related information. Markup declarations are control statements that specify how other markup (such as tags) within a source file is to be interpreted.

For example, in order for the compiler to recognize your source files as being intended for DTL conversion to ISPF elements, you must include a *document type* declaration at the beginning of each source file.

Like tags, markup declarations must be enclosed within a set of delimiter symbols so the compiler can distinguish the declaration as a control statement. All markup declarations are preceded by the <! symbol and followed by the > symbol.

**Note:** For NLS users of DTL the <! symbol can be replaced with the <: symbol.

DTL supports three types of markup declarations:

- Document type declarations
- Comments
- Entity declarations.

### Declaring the Document Type

Before you can convert a source file that contains the tag markup for dialog elements, you must declare the *document type*. Do this by coding the DOCTYPE declaration at the beginning of the source file. The DOCTYPE declaration looks like this:

```
<!doctype dm system>
```

Where:

<!	Begins the markup declaration
DOCTYPE	Identifies the declaration as a document type declaration
DM	Specifies that the source file contains tags used to define dialog elements for a Dialog Manager application
SYSTEM	Indicates that the syntax rules for defining elements are contained in an external file
>	Closes the markup declaration.

External files that are embedded (through the use of entity declarations) within the source file intended for conversion cannot contain a DOCTYPE declaration. They are converted using the DOCTYPE declaration of the source file they are embedded within. For more information about entity declarations and embedding external files within source files, see “Defining Entities and Parameter Entities” on page 18.

### Including Comments in Your Markup

If you want to include notes, reminders, or other text that you don’t want processed in your source files, you can insert them as comments, and the conversion utility ignores them.

**Note:** You cannot place comments within any of the DTL tags. A comment placed within a start or end tag causes the tag to end, and the text following the comment is treated as part of the tag content.

Like document type declarations, comments must be enclosed within markup declaration delimiters (<! >). However, you must also delimit comments within markup declarations by preceding and following a comment with two dashes (--), like this:

```
<!-- This is the text of the comment -->
```

Because the dashes act as comment delimiters, you can use them in any markup declaration. For example, you can include a comment within a DOCTYPE declaration:

```
<!doctype dm system -- DECLARE DOCUMENT TYPE -->
```

The following comment will generate a warning message because the second set of dashes is interpreted as the end of a comment and the text "Provides help for ordering" is treated as an additional markup declaration:

```
<!-- Panel DMH022 -- Provides help for ordering -->
```

If you delete one of the dashes in the second set of dashes, or use another symbol, no error will occur.

```
<!-- Panel DMH022 - Provides help for ordering -->
```

This block comment will produce a warning message because of the odd number of dashes in the first and last lines of the block:

```
<!------->
<!--This source file contains all of the -->
<!-- help panels for the application -->
<!------->
```

We could avoid this problem by using a different symbol between the comment dashes, like this:

```
<!--*****-->
<!--This source file contains all of the -->
<!-- help panels for the application -->
<!--*****-->
```

ISPD TLC accepts comments which start with the 4 characters "<!--" and end with the 3 characters "-->". The minimum valid comment is 7 characters ("<!-->").

You cannot nest comments within other comments. You can, however, code multiple comments within a markup declaration, like this:

```
<!-- Here a comment --
-- THERE A COMMENT --
-- Everywhere a comment, COMMENT-->
```

As you can see, each of the comments begin and end correctly with the comment delimiters.

You can use comment delimiters to temporarily ignore multiple lines (or a block) of DTL source text. The block of text might include one or more DTL tags. To *comment out* a block of text, place an *open comment* delimiter before the first line of the text, and a *close comment* delimiter after the last line of text. For example:

```
<!--
<p> This is a multiple line of text block
<p> It is commented out for compile purposes
-->
```

When commenting out multiple lines of DTL source, use the **MCOMMENT** compiler option when coding the **ISPDTLC** invocation syntax, or select the *Process multiple line comment blocks* option on the ISPDTLC invocation panel.

## Defining Entities and Parameter Entities

You can define, or *declare* frequently used words, phrases, and longer character strings in your source file as *entities* or *parameter entities* that represent text in the source file. You declare them within the DOCTYPE statement of your source file. After you declare them, you refer to the names of the entities in place of the word or phrase in the text. This saves you time when marking up your text, and allows you to globally change the defined words or phrases in one place in the source file.

You can use entities and parameter entities for the following purposes:

- To replace single characters in text that are considered special characters. This can include characters not available on a particular keyboard, or characters that have special meaning to the compiler, such as the tag start delimiter (<), that you want to treat as normal text.

DTL provides you with a set of predefined single-character entities. See “Predefined Entities” on page 25 for a list of these entities.

- To replace strings of text, such as words, phrases, and longer text strings used frequently in the source file text.
- To embed entire files in a source file. This is useful for breaking up a source file into smaller, more manageable files, and for declaring entities that are shared by different source files.

When you refer to an entity in the text of a source file, you must precede the entity reference with an ampersand (&) and follow it with a semicolon (;) or a blank space. The text defined by the entity replaces the entity reference in the formatted text.

### Entities

Entities are symbolic statements that represent text strings in a source file. Like other markup declarations, entity declarations must be enclosed within markup declaration delimiters (<! >). In addition, you must place entity declarations within the *declaration subset* of the DOCTYPE statement.

The declaration subset is delimited by left and right brackets ([ ]) or parentheses ( ) and is coded within the DOCTYPE statement. If left and right brackets are coded, they must have the hex values of ‘AD’ and ‘BD’ respectively.

Within the markup declaration delimiters, you declare the entity with the term “entity”, the name you are assigning to the entity, and the text string the name represents. The text string of the entity must be enclosed in single or double quotes.

```
<!doctype dm system (  
<!entity name "text string"  
)>
```

Entity names must have the following characteristics:

- 1–17 characters
- The first character must be alphabetic (A–Z, a–z, @, #, or \$)
- Remaining characters, if any, can be A–Z, a–z, @, #, \$, 0–9, or \_
- Entity names are case-sensitive.
- Entity names of more than 8 bytes must contain at least 1 underscore character.

This example declares an entity named "guar" for the phrase "full, unconditional, money-back guarantee":

```
<!doctype dm system [  
<!entity guar "full, unconditional, money-back guarantee">  
]>
```

Now that we've declared the entity, we can use the entity name in our source file text instead of the entire text string. To specify an entity name in text, you must precede the name with an ampersand (&) and follow it with a semicolon (;) or a blank, as we did in this panel text:

```
<!doctype dm system [  
<!entity guar "full, unconditional, money-back guarantee">  
]>  
<panel name=widget21 width=40>Widgets  
  <area>  
    <info width=38>  
      <p>You'll love the wide selection of merchandise  
        in our Widgets department.  
      <p>And, like all of our merchandise, Widgets come  
        with our &guar;.  
    </info>  
  </area>  
</panel>
```

As long as we declared the entity properly, the compiler recognizes the entity reference in the source file and replaces it with the text of the entity declaration. Figure 9 shows the result.



Figure 9. Entity Reference for Text Substitution

We can refer to the same entity in the text of the source file as many times as we like. And, if we should ever want to change the text of the entity, we only have to do it in one place—where we declared it in the declaration subset.

We'll change the entity we declared earlier to show you what we mean.

```
<!doctype dm system [  
<!entity guar "partial, conditional, non-refundable guarantee">
```

```

]>
<panel name=widget22 width=40>Widgets
  <area>
    <info width=38>
      <p>You'll love the wide selection of merchandise
        in our Widgets department.
      <p>And, like all of our merchandise, Widgets come
        with our &guar;.
    </info>
  </area>
</panel>

```

The only change we made was to the text of the entity declaration, not the entity name. Following reformatting, the text of the entity reference now looks like this:




Figure 10. Entity Reference for Text Substitution

If, for any reason you need to change the name of an entity, be sure to update all of the references to the entity name in your text.

You can also define the text of an entity in an external file and refer to that file in an entity declaration. If you do this, you must include the SYSTEM parameter in the entity declaration, to indicate to the conversion utility that the file is external.

**Note:** You must include the external file in the concatenation of DTL source files defined to the conversion utility.

For example, we'll define a text string we want to use as an entity in our source file in a file called WIDGETS. Here are the contents of the WIDGETS file:

doohickeys, whatnots, and gizmos

To declare this file in the entity declaration in our source file, we code it like this, with the SYSTEM parameter:

```

<!doctype dm system [
<!entity guar "full, unconditional, money-back guarantee">
<!entity widgets system>
]>

```

And, if we want to use the text string in our source file, we refer to the entity “widgets” (in this case, the file name also serves as the entity name).

```
<!doctype dm system [  
<!entity guar "full, unconditional, money-back guarantee">  
<!entity widgets system>  
>  
<panel name=widget23 width=42>More Widgets  
  <area>  
    <info width=40>  
      <p>The fine selection of items in our Widgets department  
        includes &widgets;  
      <p>And, like all of our merchandise, Widgets come with  
        our &guar; .  
    </info>  
  </area>  
</panel>
```

Figure 11 shows the formatted result.




Figure 11. Entity Reference for Text Substitution and File Embedding

Anytime we want to update or change the text of the entity, we only need to change the text in the WIDGETS file.

In the previous example, the name “widgets” serves as the external file name and as the entity name.

The SYSTEM parameter may optionally be followed by the file name for the included file. When the SYSTEM parameter is used but no file name is provided, the entity name is used as the file name.

For instance, if you want to declare a different entity name for the WIDGETS file, “things” for example, code it like this in the entity declaration:

```
<!doctype dm system [  
<!entity guar "full, unconditional, money-back guarantee"  
><!entity things system "widgets">  
>
```

And refer to the entity name, *things*, like this:

```
<!doctype dm system [  
<!entity guar &"full, unconditional, money-back guarantee&">  
<!entity things system "widgets">  
>]  
<panel name=widget24 width=42>More Widgets  
  <area>  
    <info width=40>  
      <p>The fine selection of items in our Widgets department  
        includes &things;.  
      <p>And, like all of our merchandise, Widgets come with  
        our &guar;.  
    </info>  
  </area>  
</panel>
```

The formatted result of this markup is the same as that shown in Figure 11 on page 21, assuming no changes were made to the text of the WIDGETS file.

## Parameter Entities

*Parameter* entities allow you to place multiple entity declarations within an external file and refer to them within a source file. To embed the entities into the source file, you must declare the external file as a parameter entity. A parameter entity is identified by a percent symbol (%) following the term "entity" and followed by a space and the entity name. See "Entity Declarations" on page 196 for the syntax description. You refer to a parameter entity within the DOCTYPE statement by preceding the entity name with a percent symbol (%) and following it with a semicolon (;). This embeds the parameter entity file and allows its entities to be referred to in the source file.

For example, we've declared all of our entities within an external file called SYMBOLS. Here are the contents of the SYMBOLS file:

```
<!ENTITY sb "ShelfBrowse">  
<!ENTITY cotime "ten days">  
<!ENTITY xcotime "five days">  
<!ENTITY ntime "three days">  
<!ENTITY nittem "red checkout card">  
<!ENTITY lfine "ten cents">  
<!ENTITY cophone "555-1234">
```

The conversion utility locates the parameter entity using the rules defined above for entity external files.

We can embed the above file into the declaration subset of the source file with a parameter entity declaration within the DOCTYPE statement. As long as we declare the parameter entity and refer to it properly, we can use any of the declared entities in the external file in the text of the source file.

```
<!doctype dm system  
  [<!entity % SYMBOLS system> %SYMBOLS;]  
<panel name=chkout width=40 depth=22>Library Checkout Periods  
  <area>  
    <info width=38>  
      <p>&sb; allows you to check out an inventory  
        item for a maximum of &cotime;.  
        However, you can renew the item for an additional  
        &xcotime; by calling in your card number to our  
        checkout phone line (&cophone;) any time of day.  
      <p>If an inventory item is a new shelf item  
        (indicated by the &nittem;), you may only reserve it for  
        a maximum of &nttime;.  
        You may not renew a new shelf item.
```

```

        <p>There is a fine of &lfine; per day for all
        items returned late.
    </info>
</area>
</panel>

```

Figure 12 shows the formatted result.




Figure 12. Parameter Entities

Parameter entity names must have the following characteristics:

- 1–8 characters
- The first character must be alphabetic (A–Z, a–z, @, #, or \$)
- Remaining characters, if any, must be A–Z, a–z, @, #, \$, or 0–9
- Parameter entity names are case-sensitive.

## Embedding Source Files

You can also use entities to embed entire files within your source file. For example, you could define common variables for several panels in your source file in a separate file. These separate files are stored as members of any input library specified to ISPDTLC. The following markup shows the contents of a file called VARDEFS.

```

<varclass name=titlcls type=' char 50' >
<varclass name=bookcls type=' char 20' >
<varclass name=pagecls type=' char 5' >
<varclass name=datecls type=' char 8' >

<varlist>
  <vardcl name=title    varclass=titlcls>
  <vardcl name=author   varclass=bookcls>
  <vardcl name=publish  varclass=bookcls>
  <vardcl name=pages    varclass=pagecls>
  <vardcl name=curdate  varclass=datecls>
</varlist>

```

Another common markup file could be defined for an action bar. The following markup shows a portion of the contents of a file called ACTNBAR.

```

<ab>
  <abc>File
    <pdca>Add Entry
      <action run=add>
    <pdca>Delete Entry
      <action run=delete>
    <pdca>Update Entry
      <action run=update>
    <pdca>Exit
      <action run=exit>
  <abc>View
  :
  :
  <abc>Options
  :
  :
  <abc>Help
  :
  :
</ab>

```

We can embed these files in a source file by coding entity references to the files in the source file DOCTYPE statement.

```

<!doctype dm system [
<!entity actnbar system>
<!entity vardefs system]>

```

#### **&vardefs;**

```

<panel name=dfdxmp21>Library Inventory

```

#### **&actnbar;**

```

  <topinst>To add a book to the inventory, complete the fields below,
    and then press Enter.
  <area>
    <dtafld datavar=title usage=in pmtwidth=14>Title
    <dtafld datavar=author usage=in pmtwidth=14>Author
    <dtafld datavar=publish pmtwidth=14>Publisher
    <dtafld datavar=pages usage=in pmtwidth=14>Number of pages
    <divider type=solid gutter=3>
    <dtafld datavar=curdate usage=out pmtwidth=20>Today's date is
  </area>
</panel>

```

The variable definitions in VARDEFS are referred to by the data fields in the panel because the file was embedded into the source file through the entity declaration. In the previous example, the entry width information for each field is obtained from the variable definitions.

File embed entity names must have the following characteristics:

- 1–8 characters
- The first character must be alphabetic (A–Z, a–z, @, #, or \$)
- Remaining characters, if any, must be A–Z, a–z, @, #, \$, or 0–9
- Entity names are case-sensitive.

## Run-Time Substitution Variables

If you need to include a dialog variable within your panel source that will be substituted at run time, the output panel must be created to contain an “&variable” string. An example would be a reference to an ISPF variable such as &ZDATE.

The conversion utility always tries to substitute each “&variable” found at conversion time with the available entity definitions. If the conversion utility can’t find an entity definition, it issues a warning message, and then passes the original “&variable” into the output panel.

To avoid the warning message, you can use the predefined entity “&amp”. You can code the variable in the tag source as “&amp;variable” to make “&variable” appear in the panel. Alternatively, you could provide an entity definition for the variable, such as `<!ENTITY variable “&variable”>`.

You should use caution when designing panels that contain run-time substitution variables. The regular panel formatting process might not leave sufficient space in the panel text line for the variable value to be inserted. For example, a variable name of “&date” that requires 10 positions (YYYY/MM/DD) should be coded as “&date(10);”.

## Predefined Entities

The Dialog Tag Language provides you with a set of predefined entities that you can use in your source files. You can use them when the symbol you want is not present on your keyboard, or conflicts with a conversion utility delimiter symbol.

You do not need to declare a predefined entity to use it. If you use the entity in your source file as you would an entity that you declare within your document subset, the conversion utility performs the substitution for you. You should always use the pre-defined entities for all symbols that are used as part of the tag language syntax.

The Dialog Tag Language predefined entities include:

<b>&amp;gtsym;</b>	greater than (>)
<b>&amp;ltsym;</b>	less than (<)
<b>&amp;colon;</b>	colon (:)
<b>&amp;amp;</b>	ampersand (&)
<b>&amp;semi;</b>	semicolon (;)
<b>&amp;period;</b>	period (.)
<b>&amp;quote;</b>	single quote (')
<b>&amp;dquote;</b>	double quote (")
<b>&amp;ndash;</b>	short dash (–)
<b>&amp;not;</b>	not symbol (¬)
<b>&amp;us;</b>	underscore (_)
<b>&amp;or;</b>	logical or ( )
<b>&amp;sll;</b>	back slash (\)
<b>&amp;lbrk;</b>	left bracket ([)
<b>&amp;rbrk;</b>	right bracket (])
<b>&amp;lbrc;</b>	left brace ({)
<b>&amp;rbrc;</b>	right brace (})
<b>&amp;minus;</b>	minus sign (–)
<b>&amp;plus;</b>	plus sign (+)
<b>&amp;rbl;</b>	required blank ( )
<b>&amp;tpl;</b>	text placeholder ( )
<b>&amp;eqsym;</b>	equal sign (=)
<b>&amp;rdb;</b>	required SBCS blank in DBCS mode ( )
<b>&amp;percent;</b>	percent sign (%)
<b>&amp;dot;</b>	dot (.)
<b>&amp;cmdpmt</b>	command prompt (= = = >)
<b>&amp;rptr</b>	right pointer (-->)

Any of the predefined entities listed above can be coded with a replication factor. For example, `&gtsym(5);` will create the string '>>>>>' in the substituted text.

National Language text strings are also accessible as entities:

<code>&amp;more</code>	More
<code>&amp;caution</code>	CAUTION
<code>&amp;note</code>	Note
<code>&amp;warning</code>	Warning
<code>&amp;command</code>	Command
<code>&amp;alpha</code>	abcdefghijklmnopqrstuvwxy
<code>&amp;scroll</code>	Scroll
<code>&amp;option</code>	Option
<code>&amp;horizdiv</code>	
<code>&amp;multihst</code>	Enter "/" to select option
<code>&amp;multigui</code>	Check box to select option
<code>&amp;release</code>	Release
<code>&amp;maintlvl</code>	Level:
<code>&amp;created</code>	Created -
<code>&amp;datetext</code>	Date:
<code>&amp;timetext</code>	Time:
<code>&amp;notes</code>	Notes
<code>&amp;attentn</code>	Attention
<code>&amp;tutorial</code>	Tutorial

#### Points to Remember:

1. Some of the symbols defined in the preceding list will not display on some non-programmable terminals.
2. The `&rbld;` predefined entity creates one blank in the resulting panel text. To place three required blanks in a text string, for example, you should code `&rbld;&rbld;&rbld;` in your tag source file.
3. The `&tpl;` predefined entity uses a hex FF code to reserve a space in DTL formatted text. After formatting is completed, the hex FF character is replaced by a blank. As with any predefined entity, you can change this default to another value. The current value of `&tpl;` is used for post-formatting text replacement. Thus, if you prefer to use an @ as the reserved space character, define the entity as follows:

```
<! ENTITY TPL '@' >
```

If multiple reserved spaces are required, you could use the following entity definitions to reserve 10 characters. To use your own entity name, first define TPL to override the system default character for text replacement. Second, add your entity definition, using the specified override character.

```
<! ENTITY TPL '@' >  
<! ENTITY MYTPL '#####' >
```

When the `&tpl;` is changed, be careful to select a character that will not otherwise be used in your panel.

4. The `&rdb;` predefined entity generates an SBCS blank when ISPD TLC is processing in DBCS mode, or a null character when processing in SBCS mode.
5. The `&dot;` predefined entity generates a dot (or period) character in the text. The number of spaces following the `&dot;` in the DTL source is maintained in the formatted panel.

---

## Chapter 3. Getting Started: Designing Application Panels

Each application panel you create will serve a specific purpose, with unique fields, messages, and help information defined for each one. In this chapter, we tell you how to define elements that are common among application panels. This includes defining the application panels, and the interactive elements of panels, including action bars, instruction text, and command areas. We also tell you how to arrange the contents of your application panels using panel regions and dividers.

At the end of this chapter, we tell you about the PANDEF tag, which allows you to define common attributes and values for the panels in your application in a single place.

---

### Defining Application Panels: The PANEL Tag

You use the PANEL tag, its associated attributes, and the required PANEL end tag to define an application panel and the specific characteristics of the panel.

The PANEL start and end tags define the beginning and ending of an application panel. The PANEL start tag defines:

- Panel name
- Name of the help panel for the application panel
- Name of the panel default
- Dimensions of the panel
- Associated key mapping list
- KEYLTYPE value
- APPLID value
- Cursor placement
- CCSID number
- MENU keyword
- PRIME keyword
- TUTOR keyword
- WINDOW value
- WINTITLE value
- APPTITLE value
- PAD value
- PADC value
- OUTLINE value
- EXPAND value.
- MSGLINE value
- TITLINE value
- CMDLINE value
- ATTRUSE value
- ENDATTR value
- TYPE value
- MSG value
- LMSG value
- ASIS keyword
- ACTBAR keyword
- MERGESAREA value
- PANELSTMT value
- ENTKEYTEXT value
- IMAPNAME value

- IMAPROW value
- IMAPCOL value
- TMARGIN value
- BMARGIN value
- ERRORCHECK value
- ZUP value
- ZCONT value
- AUTONRET value
- AUTOTCMD value
- Panel title text

With the exception of the required NAME attribute used to identify the name of the application panel, all of the attributes for the PANEL tag are optional. Many attributes have default values that the conversion utility assumes if you do not specify the attribute. This section describes these attributes, and how to use them.

The PANEL start and end tags look like this, respectively:

```
<panel name=mainpan>
.
.</panel>
```

In the preceding example, we included the required NAME attribute and its value *mainpan* on the PANEL start tag. ISPF requires that each panel definition contain this attribute and an associated value to identify the panel. The panel name is also used as the panel ID when the panel ID is displayed. The "NAME=\*" notation will set the panel name to be the same as the member name of the input DTL source file. If multiple panel definitions have been combined within a single source file, then this notation should be used for only one panel definition within the file.

The *panel name* must follow the standard naming convention described in "Rules for Variable Names" on page 205.

**Note:** During conversion when the PREP option is active, the conversion utility uses a temporary PDS to store ISPF source format panels. The file name for interactive use is:

```
'tsoprefix.TEMPDTLW.DTLPANnn', where nn is the screen number.
```

Or, if the TSO NOPREFIX profile option is in effect, the file name is:

```
'tsouserid.TEMPDTLW.DTLPANnn', where nn is the screen number.
```

For batch, the file name is:

```
'tsoprefix.TEMPDTLW.DTLBATCH.Tttttt.Rnnnnn'
```

Or, if the TSO NOPREFIX profile option is in effect, the file name is:

```
'tsouserid.TEMPDTLW.DTLBATCH.Tttttt.Rnnnnn'
```

The batch file name is uniquely created for each ISPD TLC invocation by including the system time and a random number as the last two qualifiers of the name.

The ISPPREP utility is called to convert all of the generated panels from ISPF source format to pre-processed format at one time to improve performance.

## The Panel Title

The text that appears as the title of the panel is called the title text. You define the title text by coding it as tag text for the PANEL start tag.

This example uses the text “Catalog Ordering System” as title text:

```
<panel name=mainpan>Catalog Ordering System
:
</panel >
```

## Panel Size (Width and Depth)

Use the DEPTH and WIDTH attributes of the PANEL tag to define the size of an application panel. The PANEL tag has a default WIDTH value of 76 characters and a default DEPTH value of 22 lines. If you specify WINDOW=NO, the default WIDTH is 80 and the default DEPTH is 24. These are the values the conversion utility assumes if you do not specify dimensions for WIDTH and DEPTH.

The following example defines the panel size as 60 characters wide and 15 lines deep:

```
<panel name=mainpan width=60 depth=15>Catalog Ordering System
:
</panel >
```

If we want the width of the panel to be 76 characters wide (the default width), we only need to specify a value for DEPTH, as in this markup:

```
<panel name=mainpan depth=15>Catalog Ordering System
:
</panel >
```

This results in a panel with a default width of 76 characters and a specified depth of 15 lines.

Because you can display application panels in pop-ups, you should allow for pop-up borders (added by ISPF at run time) when you define the WIDTH and DEPTH values for application panels. When the panel is displayed in a pop-up, ISPF adds two lines to the depth specified and 4 characters to the width specified for pop-up borders. Remember that ISPF cannot display a panel whose size exceeds the device size and will issue an error message at run time if this situation is encountered.

## Key Mapping Lists

To specify the function keys that are active for an application panel, use the KEYLIST attribute of the PANEL tag. This attribute specifies the name of the key mapping list you define for use with the panel. A key mapping list contains the keys that are active while the panel is displayed. The key mapping list also specifies what command is run when each key is pressed.

This PANEL definition refers to a key mapping list named *key01*:

```
<panel name=mainpan keylist=key01>Catalog Ordering System
:
</panel >
```

For more information about defining key mapping lists, see Chapter 9, “Defining Key Mapping Lists,” on page 167.

## Associated Help Panels

To provide help for an application panel (also called *extended help*), specify the name of the associated help panel with the `HELP` attribute of the `PANEL` tag. The help panel you specify appears when the user requests extended help while in the application panel or when contextual help is requested for an item on the panel, but no contextual help is available for the item. The help panel you specify is also displayed when the user requests extended help while in a contextual help panel associated with an item on the panel.

This panel definition refers to a help panel named *ordhelp*:

```
<panel name=mainpan help=ordhelp>Catalog Ordering System  
.  
.</panel >
```

“Help Panels” on page 146 tells you how to create help panels for your application.

## Panel Defaults

The `PANEL` tag attribute `PANDEF` provides the name of a panel default definition. Attribute values defined on the named `PANDEF` tag are used for the current panel unless the attribute has also been specified on the `PANEL` tag.

## Cursor Placement

The `PANEL` tag attributes, `CURSOR`, `CSRINDEX`, and `CSRPOS`, allow you to specify where the cursor is placed when the panel is initially displayed. If you do not specify a specific cursor position, ISPF places the cursor in the first field in the `PANEL` definition that can contain the cursor.

Use the `CURSOR` attribute to specify the field that is to contain the cursor. Use the `CSRINDEX` and `CSRPOS` attributes to identify positions within the field you specify with the `CURSOR` attribute. `CSRINDEX` and `CSRPOS` can only be used when the `CURSOR` attribute is used.

### The `CURSOR` Attribute

Use the `CURSOR` attribute to specify the value of the `NAME` attribute of a `CHOICE` or `SELFLD` tag, or the value of the `DATAVAR` attribute of a `CHOFLD`, `DTAFLD` or `LSTCOL` tag. The characteristics of cursor placement are described in the following list:

- |               |   |
|---------------|---|
| <b>CHOFLD</b> | The cursor appears in the first character position of the choice field. Cursor positioning is valid only when the <code>USAGE</code> attribute of the <code>CHOFLD</code> tag specifies <code>INPUT</code> or <code>BOTH</code> . |
| <b>CHOICE</b> | The cursor appears in the entry field of the specified choice in a multiple-choice selection field.   |
| <b>DTAFLD</b> | The cursor appears in the first character position of the data field. Cursor positioning is valid only when the <code>USAGE</code> attribute of the <code>DTAFLD</code> tag specifies <code>INPUT</code> or <code>BOTH</code> .   |
| <b>LSTCOL</b> | The cursor appears in the first row in the list column. Cursor positioning is valid only when the <code>USAGE</code> attribute of the <code>LSTCOL</code> tag specifies <code>INPUT</code> or <code>BOTH</code> .                 |
| <b>SELFLD</b> | The cursor appears in the entry field of the specified single-choice selection field.   |

Chapter 5, “Application Panel Fields,” on page 79 provides a complete description of the types of interactive fields you can define for your application panels.

You can also place the cursor in the command area of the panel by specifying *cmdarea* as the **CURSOR** value.

“Defining a Command Area” on page 51 provides a complete description of the **CMDAREA** tag.

In the following example<sup>4</sup>, the **CURSOR** attribute specifies the data field **DATAVAR** value *place*. When the panel is initially displayed, the cursor appears in the first character position of that field. Figure 13 shows the formatted result.

```
<!doctype dm system>
<panel name=mainpan1 cursor=place>Travel Agency
  <sel fld name=dest sel width=50 pmtwidth=15>Destinations:
    <choice>London
    <choice>Madrid
    <choice>Paris
    <choice>Zurich
  </sel fld>
  <divider>
  <datafld datavar=place entwidth=9 pmtwidth=5>Other
<cmdarea>
</panel>
```

The screenshot shows a panel titled "Travel Agency". Inside the panel, there is a section labeled "Destinations:" followed by a list of four items: "1. London", "2. Madrid", "3. Paris", and "4. Zurich". Below this list is an "Other" field with a horizontal line for input. At the bottom of the panel, there is a "Command" field with a prompt "===>" and a horizontal line for input. The cursor is positioned at the beginning of the "Other" field.

Figure 13. Cursor Placement

If no cursor placement was specified in the **PANEL** tag for the preceding example, the cursor would appear in the entry field of the **Destinations** single-choice selection field when the panel is initially displayed.

4. In this example, and in other examples in this chapter, we show tag markup for elements such as fields and variables that have not yet been discussed so that we can illustrate the formatting characteristics of some tags. The syntax of these elements are not important for the purposes of these examples. We discuss the syntax conventions of these elements in later chapters of this book.

## The CSRINDEX Attribute

To place the cursor in a table row within a list field, use the CURSOR attribute to specify the data variable name for a list column within the list field, and the CSRINDEX attribute to specify the table row number where the cursor should be placed. The value you assign to CSRINDEX must be numeric.

## The CSRPOS Attribute

If you use the CURSOR attribute to place the cursor within an input-only, or input/output data field or list column, or the command area, you can also define a specific character position for the cursor using the CSRPOS attribute.

The value you assign to the CSRPOS attribute must be numeric. This numeric value indicates the number of character positions from the left margin of the field where the cursor is placed, where a 1 specifies that the cursor should be in the first character position.

## Other Panel Attributes

See "PANEL (Panel)" on page 413 for more information.

<b>KEYLTYPE</b>	This attribute is used to add the SHARED keyword to the KEYLIST parameter of the )PANEL statement.
<b>APPLID</b>	This attribute is used to add the application ID to the KEYLIST parameter of the )PANEL statement.
<b>CCSID</b>	This attribute specifies the coded-character-set identifier as defined by the Character Data Representation Architecture.
<b>MENU</b>	This attribute specifies that the panel will be an ISPF menu selection panel.
<b>PRIME</b>	This attribute is used with the MENU attribute to specify an ISPF primary option menu.
<b>TUTOR</b>	This attribute specifies that the panel is to be an ISPF tutorial panel.
<b>WINDOW</b>	This attribute is used to control the generation of the WINDOW keyword on the panel )BODY statement.
<b>WINTITLE</b>	This attribute is used to add a title on a pop-up window border.
<b>APPTITLE</b>	This attribute is used to add a title on the GUI window border.
<b>PAD</b>	This attribute specifies the pad character for initializing the field. You can define this attribute as a variable name preceded by a "%".
<b>PADC</b>	This attribute specifies the conditional padding character to be used for initializing the field. You can define this attribute as a variable name preceded by a "%".
<b>OUTLINE</b>	This attribute provides for displaying lines around the field on a DBCS terminal. You can define this attribute as a variable name preceded by a "%".
<b>EXPAND</b>	This attribute causes the ISPF EXPAND keyword to be added to the panel )BODY statement.
<b>MSGLINE</b>	This attribute controls the provision for a long message line in the generated panel. When MSGLINE=NO, the blank line for the long message is not added to the panel )BODY section.

<b>TITLINE</b>	This attribute controls the provision for a panel title line in the generated panel. When <b>TITLINE=NO</b> , the title line is not added to the panel )BODY section. This attribute allows a panel formatted as a dynamic area to provide the panel title as part of the dynamic area data.
<b>CMDLINE</b>	This attribute controls the automatic addition of the command area to a menu selection or table display panel. When <b>CMDLINE=NO</b> , the command area is not automatically generated when the <b>CMDAREA</b> tag is not present in the DTL source file.
<b>ATTRUSE</b>	This attribute controls the use of panel attribute characters in the range of x'01' through x'2F'. When <b>ATTRUSE=YES</b> , dynamic area attributes (specified with the <b>ATTR</b> tag) can be assigned low-order hex values normally reserved for use by the conversion utility.
<b>ENDATTR</b>	This attribute specifies that when the last attribute on any panel body line is 'normal text' (CUA), it will be replaced by the default 'text' (ISPF) attribute.
<b>TYPE</b>	This attribute specifies that the panel will be used for host display, GUI mode display, or both.
<b>SMSG</b>	This attribute provides the name of the field where the short message is to be placed.
<b>LMSG</b>	This attribute provides the name of the field where the long message is to be placed.
<b>ASIS</b>	This attribute specifies that the command and long message fields are to appear on the display as specified in the generated panel definition. When <b>ASIS</b> is specified, any user request specified on the Settings panel, or by setting the system variable <b>ZPLACE</b> is ignored.
<b>ACTBAR</b>	This attribute causes the action bar information for the panel to be generated, overriding the <b>NOACTBAR</b> invocation option.
<b>MERGESAREA</b>	This attribute specifies that a panel with a single scrollable area be reformatted to combine the scrollable area into the panel body.
<b>PANELSTMT</b>	This attribute controls the creation of the ) <b>PANEL</b> statement.
<b>ENTKEYTEXT</b>	This attribute provides the text for the Enter key push button provided on panels displayed in GUI mode.
<b>IMAPNAME</b>	This attribute provides the name of the image placed on panels displayed in GUI mode.
<b>IMAPROW</b>	This attribute provides the row number for positioning the image.
<b>IMAPCOL</b>	This attribute provides the column number for positioning the image.
<b>TMARGIN</b>	This attribute provides the number of blank lines to format at the top of the panel as a top margin.
<b>BMARGIN</b>	This attribute provides the number of blank lines to format at the bottom of the panel as a bottom margin.

**ERRORCHECK**

This attribute specifies that error checking code is added to the )PROC panel section.

**ZUP**

This attribute provides the name of the tutorial panel to be assigned to the ZUP variable.

**ZCONT**

This attribute provides the name of the tutorial panel to be assigned to the ZCONT variable.

---

## Defining Action Bars and Pull-Downs

To create a consistent user interface, you should design your applications according to the object-action process sequence defined by the SAA<sup>®</sup> Common User Access. The action bar is a major user interface component that helps you achieve consistency in your applications.

The action bar is the panel element located at the top of an application panel that contains action bar choices for the panel. Each action bar choice represents a group of related choices that appear in the pull-down associated with the action bar choice. When the user selects an action bar choice, the associated pull-down appears directly below the action bar choice. Pull-downs contain choices that, when selected by the user, perform actions that apply to the contents of the panel.

**Panel Design Note**

ISPF and DTL provide the tools to help you create the object-action process sequence in your application, but it is your responsibility as an application designer to ensure that the contents of your action bar are actions that can be applied to the objects contained within your panel.

Typically, application panels intended for display within primary windows contain action bars that present the user with all of the available actions that apply to that panel. Application panels that are displayed as pop-ups should not include the action bar. Instead, actions for a pop-up panel are presented in the function key area.

Figure 14 on page 35 shows an action bar with the **File** pull-down menu displayed.




Figure 14. Action Bar and Pull-Down

The tags you use to create the action bar and its pull-down menus are:

<b>AB</b>	To start an action bar definition. The required AB end tag ends an action bar definition.
<b>ABC</b>	To define each of the action bar choices.
<b>PDC</b>	To define the choices on the pull-down associated with an action bar choice.
<b>ACTION</b>	To specify an action to be taken when the pull-down choice is selected. The ACTION tag is coded within the PDC tag.
<b>M</b>	To specify a mnemonic character for action bar choice or pull-down choice selection.

## Coding an Action Bar Definition

The following list describes how to code an action bar definition:

- Code the AB start tag immediately after the PANEL start tag and before any other tags in the panel.
- Following the AB start tag, code an ABC tag for each action bar choice in the action bar. The text you specify on the ABC tag is the text that appears in the action bar as the action bar choice.
- Code the associated PDC tags within the ABC tags. The text you specify on the PDC tag is the text that appears as the pull-down choice.
- Following each PDC tag, code one or more ACTION tags to specify what type of action occurs when that pull-down choice is selected by the user.

The ACTION tag RUN attribute (and its *internal-command-name*) define a command action for the pull-down choice. If you define multiple ACTION tags for a pull-down choice, one of which contains a RUN value, code the RUN action last, because any actions specified after a RUN action are ignored.

- End the action bar definition with the required AB end tag.

The following example shows the markup for the action bar shown in Figure 14. The detailed markup for the **File** pull-down is included.

```

<panel name=mainpan2 depth=15>Sample Application
  <abc>
    <abc>File
      <pdca>Add Entry
        <action run=add>
      <pdca>Delete Entry
        <action run=delete>
      <pdca>Update Entry
        <action run=update>
      <pdca>Exit
        <action run=Exit>
    <abc>View
    .
    .
  <abc>Options
  .
  .
  <abc>Help
  .
  .
</abc>
</panel>

```

## Pull-Down Choice Actions

A pull-down choice provides an immediate action to the user. To ensure that a pull-down choice performs an immediate action, you should code an ACTION tag that specifies the RUN attribute for each pull-down choice. The value you assign to RUN tells ISPF which command to run when the user selects the choice.

In the preceding markup example, each ACTION definition uses the RUN attribute to specify a command. Each of these commands must be defined within the command table for the application. Chapter 8, “The Application Command Table,” on page 161 tells you how to define commands for an application.

In addition to the RUN action, you can specify other types of actions to occur when a pull-down choice is selected. The SETVAR and TOGVAR attributes on the ACTION tag can be used to set and toggle variables which the application can use to determine the processing to perform.

Remember, any SETVAR or TOGVAR actions for a pull-down choice must be coded before any ACTION definition specifying the RUN action, because actions coded after RUN are ignored.

A pull-down choice may be marked as unavailable. The UNAVAIL attribute is used to provide a variable name that is used by ISPF to determine the availability of the pull-down choice. When the variable value is 1, the pull-down choice is unavailable.

## Action Bar Help

You can provide help for each action bar choice and pull-down choice with the HELP attribute on the ABC and PDC tags, respectively. By specifying the name of a help panel or message for the action bar choice or pull-down choice, ISPF knows which help information to display when the user requests help on that choice. If you do not specify help for a pull-down choice, the help for the action bar choice is displayed, when the user requests help. If there is no help defined for the action bar choice, the extended help panel is displayed.

In the following example, we’ve added the HELP attribute to each of the action bar choices and pull-down choices in the action bar defined on page 36. The values specified with each HELP attribute are the NAME values of defined help panels.

```

<!doctype dm system>
<panel name=mainpan3 width=50 depth=15>Sample Application
  <ab>
    <abc help=hfile>File
      <pdcc help=hnew>Add Entry
        <action run=add>
      <pdcc help=hopen>Delete Entry
        <action run=delete>
      <pdcc help=hsave>Update Entry
        <action run=update>
      <pdcc help=hexit>Exit
        <action run=exit>
    <abc help=hview>View
  :
  :
  <abc help=hoption>Options
  :
  :
  <abc help=hhelp>Help
  :
  </ab>
  :
  </panel>

```

In the preceding example, we defined a help panel named *hhelp* for the **Help** action bar choice.

Common User Access requires that you put the **Help** action bar choice as the last action bar choice in an action bar definition. You should code the **Help** action bar pull-down as follows:

```

<abc help=hhelp>Help
  <pdcc>Extended help
    <action run=exhelp>
  <pdcc>Keys help
    <action run=keyshelp>
</abc>

```

“Help Panels” on page 146 tells you how to define help panels.

## Preselected Pull-Down Choices

You can define a pull-down choice as being *preselected* with the CHECKVAR and MATCH attributes of the PDC tag. The CHECKVAR attribute specifies the name of a variable that you set at run time to indicate if the pull-down choice should be preselected. The MATCH attribute defines a value that causes the choice to be preselected. ISPF compares the value of the variable named for the CHECKVAR attribute to the MATCH value, and if they are equal, the choice appears preselected when the pull-down is displayed.

Continuing with the library application, assume that the user can view the files in the library sorted by name, owner, date, or size. Preselecting a pull-down choice provides a visual cue to the user of the current sort order.

To preselect any of the pull-down choices, the same CHECKVAR value is specified for each choice, and a unique MATCH value is specified for each choice. The application variable specified with CHECKVAR is set to the MATCH value to indicate the sorting option being used. The variable specified with CHECKVAR is changed each time the sorting option is changed. This provides a visual reminder to the user of how the files are sorted.

## Mnemonic Choice Selection

ISPF supports mnemonic selection of action bar choices for both host system and GUI mode display and pull-down choices when running in GUI mode.

Mnemonic selection of action bar choices and pull-down choices is automatically determined by ISPD TLC when a non-DBCS conversion is in process. When DBCS is specified, mnemonics are not automatically generated. The default mnemonic character generation can be overridden by adding the MNEMGEN=NO attribute to the AB tag for non-DBCS conversions. The mnemonic character that will be selected is the first alphabetic or numeric character from the current action bar choice or pull-down choice description text that is not previously used as a mnemonic character within the action bar or current pull-down. If a unique mnemonic character cannot be selected, the conversion utility will issue a message. DBCS characters cannot be specified as mnemonics. See “M (Mnemonic)” on page 388 for a description of how to provide a mnemonic character that is not part of the normal choice description.

Mnemonic selection of action bar choices and pull-down choices may be specified by placing the M tag immediately in front of the character to be used as a mnemonic within the ABC or PDC text.

The automatic mnemonic generation does not replace any valid mnemonic specified by the M tag. (If the mnemonic character specified by the M tag is a duplicate of a mnemonic character previously selected by the generation process, a message is issued and ISPD TLC will attempt to replace the duplicate value that was specified.) This processing allows the combination of specific character selection with the automatic generation feature, as long as the characters automatically generated and the characters specified (by the M tag) are unique.

```
<!doctype dm system (
  <!ENTITY actnfile system>
  <!ENTITY actnoptn system>
  <!ENTITY actnhelp system>
)>

<panel name=pcxmp1>Sample Application
  <ab>
    &actnfile;

    <abc>View
      <pdccheckvar=sorttype match=N><M>Name
        <action run=name>
      <pdccheckvar=sorttype match=O><M>Owner
        <action run=owner>
      <pdccheckvar=sorttype match=D><M>Date
        <action run=date>
      <pdccheckvar=sorttype match=S><M>Size
        <action run=size>

    &actnoptn;
    &actnhelp;
  </ab>

  <topinst>
  <area>
  </area>
  <cmdarea>
</panel>
```

If the application sets the variable *sorttype* to “D” before the panel is displayed, then the **Date** choice will be preselected.

Figure 15 shows how the **View** pull-down would appear in this scenario.

## Pull-Down Choice Accelerator Support

ISPF supports accelerators on pull-down choices when you are operating in GUI mode. Accelerators may include up to three keys. They are supported in DTL by specifying the ACC1, ACC2, and ACC3 attributes on the PDC tag.

See “PDC (Pull-Down Choice)” on page 428 for a description of accelerator attributes.




Figure 15. Preselected Pull-Down Choice

---

## Defining the Panel Body

In this section, we tell you how to use DTL to define elements of the panel body such as instruction text, areas, regions, and dividers.

### Panel Instructions

DTL provides you with the TOPINST, PNLINST, and BOTINST tags to define instructions for your application panels. None of the tags have required end tags associated with them.

Use the instruction tags to provide text that tells the user how to interact with the panel or how to continue with an application.

If the COMPACT attribute is not specified, a blank line is added to the panel after each TOPINST tag and before each PNLINST or BOTINST tag.

You must code the top and bottom instruction tags outside of the portion of the panel defined with the AREA tag and its matching end tag. (The section called “The AREA Tag” on page 40 explains how to use the AREA tag). Code the TOPINST tag immediately after the action bar definition (or the PANEL start tag if the panel does not contain an action bar). Code the BOTINST following the main body of the panel, before the PANEL end tag. You may code PNLINST tags within the AREA tag.

This application panel markup contains both types of instructions. Figure 16 shows the results.

```
<!doctype dm system>
<panel name=mainpan5>Item Selection
  <topinst>Select one of the following items and press Enter.
    <sel fld name=itemtyp selwidth=76>
      <choice>Automotive
      <choice>Hardware
      <choice>Health and beauty
      <choice>Lawn and garden
      <choice>Sporting goods
    </sel fld>
  <botinst>To exit the application, press F3.
</panel>
```




Figure 16. Top and Bottom Instructions

## The AREA Tag

The AREA tag (and its matching end tag) defines the main portions of the panel body. You code all of the interactive fields for the panel within AREA definitions.

Add an AREA definition to the previous application panel markup.

```
<!doctype dm system>
<panel name=mainpan6 depth=18>Item Selection
  <topinst>Select one of the following items and press Enter.
  <area>
    <sel fld name=itemtyp selwidth=76>
      <choice>Automotive
      <choice>Hardware
      <choice>Health and beauty
      <choice>Lawn and garden
      <choice>Sporting goods
    </sel fld>
  </area>
  <botinst>To exit the application, press F3.
</panel>
```

As stated on page 39, you must code the top and bottom instruction tags outside of the AREA definition. In this example, we coded only a selection field within the AREA definition.

The AREA tag has an optional MARGINW attribute that you can use to specify the width of the panel body margins. This is useful for arranging fields on a panel.

The MARGINW attribute has a default value of 1. You can specify a different value to increase the size of the panel body margins. For example, we could specify a margin width for the AREA in the preceding markup example.

```
<!doctype dm system>
<panel name=mainpan7>Item Selection
  <topinst>Select one of the following items and press Enter.
  <area marginw=10>
    <sel fld name=itemptyp selwidth=58>
      <choice>Automotive
      <choice>Hardware
      <choice>Health and beauty
      <choice>Lawn and garden
      <choice>Sporting goods
    </sel fld>
  </area>
  <botinst>To exit the application, press F3.
</panel>
```

We specified a margin width of 10. Here is how the panel looks now:




Figure 17. AREA MARGINW=10

## Scrollable Areas

You specify a scrollable area with the Dialog Tag Language by coding the AREA tag and specifying the DEPTH, EXTEND, and DIV attributes for the area. When the DEPTH attribute is present, the conversion utility generates the )AREA section in the panel definition, along with the corresponding )ATTR and )BODY entries for the scrollable area.

Help panels generated by the Conversion Utility that contain all of the help panel text within an AREA tag (with DEPTH specified) are not split into separate panels.

The conversion utility places the text in an )AREA section, which allows you to define panels up to the display size limit of ISPF.

If you specified DEPTH to signal the creation of a panel with a scrollable area, you can also specify the EXTEND and DIV attributes.

You can specify EXTEND=ON to allow the panel to expand to the logical window size. If you intend to have the panel in a pop-up window, you should not code the EXTEND attribute. Panels that specify EXTEND=ON cannot be preprocessed.

You use the DIV attribute to control the creation of a divider line before and after the scrollable area.

If you specify DIV=BLANK, a blank divider line is added before and after the area. If you specify DIV=SOLID, a visible divider is created. The visible divider formats with an attribute byte on each end of the line of dashes, which causes the line to appear with a 1 character "space" on both ends. Omitting the DIV attribute or specifying DIV=NONE causes the area to be created without divider lines.

The conversion utility uses the DEPTH attribute value to reserve a fixed amount of space in the panel body. This space, together with the divider lines, if specified, is considered as part of the body within the depth limit specified (or defaulted) on the PANEL tag. When EXTEND=OFF, the minimum depth for a scrollable area is two lines, one for the scrolling indicator line and at least one line of displayable text.

The following markup illustrates how you would code a scrollable panel. Figure 18 on page 43, Figure 19 on page 43, and Figure 20 on page 44 show the formatted result.

```
<!DOCTYPE DM SYSTEM(
  <!entity sampvar2 system>
  <!entity sampabc system>)>
&sampvar2;

<PANEL NAME=scrarea3 KEYLIST=keyl xmp>File-A-Case
<AB>
&sampabc;
</AB>
<TOPINST COMPACT>
  Type in client's name and case number (if applicable).
<TOPINST>Then select an action bar choice.
<AREA>
<DTAFLD DATAVAR=caseno PMTWIDTH=12 ENTWIDTH=7 DESWIDTH=25>Case No
  <DTAFLDD>(A 7-digit number)
<DTAFLD DATAVAR=name PMTWIDTH=12 ENTWIDTH=25 DESWIDTH=25>Name
  <DTAFLDD>(Last, First, M.I.)
<DTAFLD DATAVAR=address PMTWIDTH=12 ENTWIDTH=25>Address
<DIVIDER>
<SELFLD NAME=casesel PMTWIDTH=30 PMTLOC=before SELWIDTH=38>Choose
one of the following
  <CHOICE CHECKVAR=case MATCH=civ>Civil
  <CHOICE CHECKVAR=case MATCH=estate>Real Estate
  <CHOICE CHECKVAR=case MATCH=environment>Environmental
</SELFLD>
</AREA>
<AREA DEPTH=6>
<SELFLD TYPE=multi PMTWIDTH=35 SELWIDTH=50>Check type of offense committed
  <CHOICE NAME=patin HELP=patin CHECKVAR=val>Patent Infringement
  <CHOICE NAME=defa HELP=defame CHECKVAR=def>Defamation
  <CHOICE NAME=cont HELP=cont CHECKVAR=con>Breach of Valid Contract
  <CHOICE NAME=priv HELP=priv CHECKVAR=pri>Invasion of Privacy
```

```

<CHOICE NAME=incr HELP=incr CHECKVAR=icr>Interference with Contractual
  Relations
<CHOICE NAME=di sp HELP=di sp CHECKVAR=dis>Improper Disposal of Medical
  By-Products
<CHOICE NAME=fraud HELP=fraud CHECKVAR=fra>Fraud
</SELFLD>
</AREA>
<CMDAREA>Enter a command
</PANEL>

```

File Search Help

---

File-A-Case

Type in client's name and case number (if applicable).  
Then select an action bar choice.

Case No . . . \_\_\_\_\_ (A 7-digit number)  
Name . . . . \_\_\_\_\_ (Last, First, M.I.)  
Address . . \_\_\_\_\_

Choose one of the following   — 1. Civil  
  2. Real Estate  
  3. Environmental

More:    +

Check type of offense committed

Patent Infringement  
 Defamation  
 Breach of Valid Contract

Enter a command ==>> \_\_\_\_\_

F1=Help      F3=Exit      F5=Display      F6=Keyshelp      F10=Actions  
F12=Cancel

*Figure 18. Scrollable Panel Area*

After scrolling, the panel appears as follows:

File Search Help

---

File-A-Case

Type in client's name and case number (if applicable).  
Then select an action bar choice.

Case No . . . \_\_\_\_\_ (A 7-digit number)  
Name . . . . \_\_\_\_\_ (Last, First, M.I.)  
Address . . \_\_\_\_\_

Choose one of the following   — 1. Civil  
  2. Real Estate  
  3. Environmental

More:    - +

Breach of Valid Contract  
 Invasion of Privacy  
 Interference with Contractual Relations  
 Improper Disposal of Medical By-products

Enter a command ==>> \_\_\_\_\_

F1=Help      F3=Exit      F5=Display      F6=Keyshelp      F10=Actions  
F12=Cancel

*Figure 19. Application Panel Area*

After scrolling, the last choice in the list is visible.

```

File Search Help
-----
File-A-Case

Type in client's name and case number (if applicable).
Then select an action bar choice.

Case No . . . _____ (A 7-digit number)
Name . . . . _____ (Last, First, M.I.)
Address . . . _____

Choose one of the following  _ 1. Civil
                               2. Real Estate
                               3. Environmental
                               More: -

_ Invasion of Privacy
_ Interference with Contractual Relations
_ Improper Disposal of Medical By-products
_ Fraud
Enter a command ===> _____
F1=Hel p      F3=Exi t      F5=Di spl ay      F6=Keyshel p      F10=Acti ons
F12=Cancel

```

Figure 20. Scrollable Panel Area

## Multiple AREA Tags

The default AREA tag formatting arranges areas vertically within the panel body.

The WIDTH and DIR attributes of the AREA tag allow areas to be formatted horizontally.

The following markup illustrates the use of horizontal areas. Figure 21 on page 45 shows the formatted result.

```

<!DOCTYPE DM SYSTEM(
  <!entity sampvar2 system>
  <!entity sampabc system>)>
&sampvar2;

<PANEL NAME=scrarea4 KEYLIST=keyl xmp>File-A-Case
<AB>
&sampabc;
</AB>
<CMDAREA>Enter a command
<TOPINST COMPACT>
  Type in client's name and case number (if applicable).
<TOPINST>Then select an action bar choice.
<AREA width=50 dir=horiz>
<DTAFLD DATAVAR=caseno PMTWIDTH=12 ENTWIDTH=7 DESWIDTH=21>Case No
  <DTAFLDD>(A 7-digit number)
<DTAFLD DATAVAR=name PMTWIDTH=12 ENTWIDTH=25 DESWIDTH=8>Name
  <DTAFLDD>(Last, First, M.I.)
<DTAFLD DATAVAR=address PMTWIDTH=12 ENTWIDTH=25>Address
<DIVIDER>
<SELFLD NAME=casesel PMTWIDTH=11 PMTLOC=before SELWIDTH=38>Choose
one of the following
  <CHOICE CHECKVAR=case MATCH=ci v>Civi l
  <CHOICE CHECKVAR=case MATCH=estate>Real Estate
  <CHOICE CHECKVAR=case MATCH=envi ron>Envi ronmental
</SELFLD>
</AREA>
<AREA width=26 dir=horiz>

```

```

<SELFLD TYPE=multi PMTWIDTH=24 SELWIDTH=26 depth=10>
  Check type of offense
  <CHOICE NAME=patin HELP=patin CHECKVAR=val>Patent Infringement
  <CHOICE NAME=defa HELP=defame CHECKVAR=def>Defamation
  <CHOICE NAME=cont HELP=cont CHECKVAR=con>Breach of Valid Contract
  <CHOICE NAME=priv HELP=priv CHECKVAR=pri>Invasion of Privacy
  <CHOICE NAME=incr HELP=incr CHECKVAR=icr>Interference with Contractual
    Relations
  <CHOICE NAME=di sp HELP=di sp CHECKVAR=di s>Improper Disposal of Medical
    By-Products
  <CHOICE NAME=fraud HELP=fraud CHECKVAR=fra>Fraud
</SELFLD>
</AREA>
</PANEL>

```

File Search Help

---

File-A-Case

Type in client's name and case number (if applicable).  
Then select an action bar choice.

		Check type of offense	
Case No . . . _____ (A 7-digit number)		#SAREA37	#
Name . . . . _____ (Last, First, M.I.)		#	#
Address . . _____		#	#
Choose one of the following		#	#
___ 1. Civil		#	#
2. Real Estate			
3. Environmental			
Enter a command ==>> _____			
F1=Help	F3=Exit	F5=Display	F6=Keyshelp
F12=Cancel			F10=Actions

The contents of the scrollable area are as follows:

)AREA SAREA37

- Patent Infringement
- Defamation
- Breach of Valid Contract
- Invasion of Privacy
- Interference with Contractual Relations
- Improper Disposal of Medical By-Products
- Fraud

)AREA SAREA37

Figure 21. Multiple Horizontal Areas

## The DYNAMIC AREA Tag

You specify a dynamic area in the )BODY section by coding the DA and ATTR tags. The DA tag is used to define the dynamic area in the panel )BODY section.

The ATTR tag is used to specify the )ATTR section entries for DATAIN, DATAOUT, and CHAR attribute types used within the dynamic area. A dynamic area allows you to specify an area of the panel to format with your application. Refer to the *ISPF Dialog Developer's Guide and Reference* for more information.

## The GRAPHIC AREA Tag

You specify a graphic area in the panel )BODY section by coding the GA tag. A Graphic area allows you to define a specific portion of the screen for a GDDM display. Refer to the *ISPF Dialog Developer's Guide and Reference* for more information.

## The DIVIDER Tag

You can separate the elements on a panel or the regions you define for a panel with the DIVIDER tag. A DIVIDER definition produces either a blank or visible divider line, depending on the value you assign to the TYPE attribute of the DIVIDER tag. The visible divider line can be a dashed line or a solid line, or it can contain text.

The default value, NONE, produces a blank divider line. The values DASH, SOLID, and TEXT produce a visible divider line.

For horizontally formatted dividers,

- When the GRAPHIC invocation option is specified, SOLID produces a solid line for host display and DASH produces a dashed line.
- When NOGRAPHIC is specified or the panel is displayed in GUI mode, both SOLID and DASH produce a dashed line.

Both SOLID and DASH use the “|” character (obtained from the ISPF literals table) for vertically formatted dividers. The value TEXT (used in combination with the FORMAT attribute) is valid only for dividers within vertical regions and specifies that blank padding is used for the supplied text.

The GAP attribute specifies whether the divider line completely crosses the panel area or region that contains the divider, or if a 1-character gap is to remain at either end of a horizontally formatted divider. The valid values for the GAP attribute are YES (the default), and NO.

The value you assign to GUTTER specifies the size (in characters) of the total width of the divider. For vertical formatting the default is 1, because ISPF allots 1 line of screen space for the divider. For horizontal formatting the default GUTTER size is 3, because an attribute byte is placed both before and after the divider character. Any value above the default is split to either side of the divider. If the GUTTER value is an even number, the conversion utility increases the number by 1 so that the divider is centered within the defined width. The GUTTER attribute is useful for creating blank space on a panel.

The NOENDATTR attribute is valid only when formatting dividers within horizontal regions. When NOENDATTR is specified, the ending attribute is not added to the divider. With NOENDATTR and a GUTTER size of 1, a divider of one blank character can be created. With a GUTTER size of 2, TYPE=SOLID can be used to produce a visible divider.

The FORMAT attribute is valid only when formatting dividers within vertical regions. The FORMAT attribute must be specified to have ISPD TLC process the

text provided with the DIVIDER tag. FORMAT specifies the text placement within the divider line as START, CENTER, or END.

There are two DIVIDER tags defined in the following example. The first DIVIDER does not specify a TYPE attribute, and produces a blank horizontal line. The second DIVIDER specifies TYPE=SOLID, and produces a visible divider.

```
<!doctype dm system>
<panel name=fields1>Selections
  <area>
    <dtacol selwidth=24 pmtwidth=15>
      <sel fld name=item>Pick an item:
        <choice>Widget
        <choice>Doohickey
        <choice>Gizmo
      </sel fld>
      <divider>
      <sel fld name=color>Pick a color:
        <choice>Red
        <choice>Green
      </sel fld>
      <divider type=solid gap=no>
      <sel fld name=size>Pick a size:
        <choice>Minuscule
        <choice>Behemoth
      </sel fld>
    </dtacol>
  </area>
  <botinst>To exit the application, press F3.
</panel>
```

Figure 22 shows the result:




Figure 22. Area Dividers

The dashed line in the second divider in the preceding example extends across the entire AREA definition to both margins because we specified GAP=NO in the DIVIDER definition.

## The REGION Tag

You can further define the areas of your panel, and how you want the information in the areas arranged, with the REGION tag. Using one or more regions within a PANEL definition provides an easy way of arranging the elements on a panel. Like the PANEL and AREA tags, the REGION end tag is required.

The DIR (direction) attribute of the REGION tag specifies how the elements within a region are arranged, either horizontally or vertically. The default value is VERT, which arranges the elements within the region vertically. This means that if you do not specify a horizontal region (DIR=HORIZ), or if you do not define a region at all, the panel elements are arranged vertically by default.

For example, the selection fields in the following example are arranged vertically, because no DIR value is defined for the REGION tag.

```
<!doctype dm system>
<panel name=fields2>Select ions
  <area>
    <region>
      <dtacol sel width=24 pmtwidth=15>
        <sel fld name=item>Pick an item:
          <choi ce>Wi dget
          <choi ce>Doohi ckey
          <choi ce>Gi zmo
        </sel fld>
      <di vi der>
        <sel fld name=color>Pick a color:
          <choi ce>Red
          <choi ce>Green
        </sel fld>
      <di vider type=solid gap=no>
        <sel fld name=size>Pick a size:
          <choi ce>Mi nuscul e
          <choi ce>Behemoth
        </sel fld>
      </dtacol >
    </region>
  </area>
  <botinst>To exit the application, press F3.
</panel >
```




Figure 23. Vertical Region

We'll specify the `HORIZ` value for the region to change the layout of the selection fields to horizontal. Figure 24 on page 50 shows the result.

```
<!doctype dm system>
<panel name=fields3>Selections
  <area>
    <region dir=horiz>
      <dtacol selwidth=20 pmtwidth=15>
        <sel fld name=item>Pick an item:
          <choice>Widget
          <choice>Doohickey
          <choice>Gizmo
        </sel fld>
        <divider type=solid gutter=5>
        <sel fld name=color>Pick a color:
          <choice>Red
          <choice>Green
        </sel fld>
        <divider type=solid gutter=5>
        <sel fld name=size>Pick a size:
          <choice>Minuscule
          <choice>Behemoth
        </sel fld>
      </dtacol>
    </region>
  </area>
  <botinst>To exit the application, press F3.
</panel>
```




Figure 24. Horizontal Region

In the markup for this example, we also changed the format of the DIVIDER tags to provide additional space and a visible line between the selection fields. We did this by specifying TYPE=SOLID and GUTTER=5 on each of the DIVIDER tags. You will notice another characteristic in the preceding example: the divider lines are now vertical. That's because of the manner DTL handles dividers within regions. DTL adheres to the following formatting rules for DIVIDER tags within regions:

- A DIVIDER tag coded within a vertical region formats horizontally.
- A DIVIDER tag coded within a horizontal region formats vertically.

The following markup illustrates how REGION and DIVIDER tags format under different circumstances. This example shows both horizontal and vertical regions, as well as solid and blank dividers.

```
<!doctype dm system>
<panel name=mainpan8>Application
<topinst>Complete the information below and press Enter.
<area>
  <dtafld datavar=name entwidth=25 pmtwidth=9>Name
  <dtafld datavar=addr entwidth=25 pmtwidth=9>Address
  <region dir=horiz>
    <dtafld datavar=city pmtwidth=9 entwidth=25>City
    <dtafld datavar=stat pmtwidth=5 entwidth=2>State
    <dtafld datavar=zip pmtwidth=8 entwidth=5>Zip code
  </region>
  <divider type=solid gutter=3>
  <region dir=horiz>
    <sel fld name=grade pmtwidth=32 selwidth=33>Highest education level
    <choice>Some high school
    <choice>High school graduate
    <choice>Some college
    <choice>College graduate
    <choice>Some post-graduate work
    <choice>Post graduate degree
  </sel fld>
  <divider gutter=5>
  <region>
    <info width=30>
      <p compact>Complete if applicable:
    </info>
    <dtafld datavar=grad pmtwidth=10 entwidth=11>Date of graduation
```

```

        <datafld datavar=field pmtwidth=10 entwidth=11>Field of study
    </region>
</region>
</area>
</panel >

```

Figure 25 shows how the preceding markup formats.

Application

Complete the information below and press Enter.

Name . . \_\_\_\_\_  
 Address \_\_\_\_\_  
 City . . \_\_\_\_\_ State \_\_ Zip code \_\_\_\_\_

-----

<p>Highest education level</p> <p>___ 1. Some high school          2. High school graduate          3. Some college          4. College graduate          5. Some post-graduate work          6. Post graduate degree</p>	<p>Complete if applicable:</p> <p>Date of graduation _____          Field of study . . _____</p>
---	--

Figure 25. Horizontal Region

This is an example of nesting regions. The data fields for entering the graduation date and field of study are arranged in a vertical region that is nested within a horizontal region.

The ALIGN, DEPTH, EXTEND, INDENT, LOCATION, WIDTH, GRPBOX, and GRPWIDTH attributes allow additional formatting control. The DEPTH and EXTEND attributes are used with scrollable regions. ALIGN, INDENT, LOCATION, and WIDTH affect the placement of fields within the region and the placement of the region within the panel. GRPBOX and GRPWIDTH specify that the region should be displayed as a group box in GUI mode. The optional group box title is supplied as text following the REGION tag ending delimiter. When displayed on a host terminal, a panel defined with a group box will contain the group box title, but will not have a group box border.

---

## Defining a Command Area

Many applications are dependent on a command area in their panels. You define a command area and specify the prompt text of the command area with the CMDAREA tag. The conversion utility supplies the prompt symbol (==>) and provides the entry field in the command area for user input.

The conversion utility always formats the command area at the top of the panel. An ISPF run-time option determines the actual display location of the command line.

The command area contains an entry field and command prompt text, and is normally displayed at the bottom of an application panel. Users can enter commands in the command entry field. All commands entered into the command

entry field are validated against the commands you define within the application command table and the ISPF-provided commands. For more information about defining the application command table, see Chapter 8, “The Application Command Table,” on page 161.

```
<!doctype dm system (<!entity actnbar system>)>
<panel name=cmdxmp1>Application Name
  &actnbar;
  <topinst>Sample command area panel
  <area>
  </area>
  <CMDAREA>
</panel >
```

Here is how the command area displays on the panel:




Figure 26. Command Area

In Figure 26 we did not specify the text of the command prompt, so the conversion utility automatically added the text “Command” (or its translated equivalent), which is the default text. If we wanted to specify something other than this text, we could have coded it as tag text, as in this example:

```
<!doctype dm system (<!entity actnbar system>)>
<panel name=cmdxmp2>Application Name
  &actnbar;
  <topinst>Sample command area panel
  <area>
  </area>
  <cmdarea>Enter a command
</panel >
```

You can code up to 59 bytes of prompt text on a standard 76-byte width panel when overriding the default text. Here is how the command prompt looks now:




Figure 27. Command Area

Data entered on the command line can be forced to uppercase either by specifying CAPS = ON or by including a VARCLASS tag to define the command area and an XLATL tag to specify translation to uppercase. (The type attribute defines the space available on a standard 76 character width panel using the default command prompt.)

```
<varclass name=vccmd type=' char 59' >
  <xlatl format=upper>
  </xlatl >
</varclass>

<varlist>
  <varclass name=zcmd varclass=vccmd>
</varclass>
```

The AUTOTAB, CAPS, CMDLEN, CMDLOC, ENTWIDTH, IMAPNAME, IMAPNAMEP, NAME, NOINIT, NOJUMP, OUTLINE, PAD, PADC, PLACE, PMTTEXT, PSBUTTON, PSVAL, PSVAR, SCRCAPS, SCROLLTAB, SCROLLVAR, and SCRHELP are attributes that control formatting, initialization, and presentation of the command area.

---

## Defining Panel Defaults

DTL provides you with a tag that makes it easier for you to define attributes and values that are common for multiple application panels: the PANDEF (panel default) tag. This tag must be coded in the source file before any panels it is providing defaults for.

The default PANEL values you can define with the PANDEF tag are:

- The panel dimensions (DEPTH and WIDTH)
- The help panel
- The key mapping list
- The KEYLTYPE value
- The CCSID number
- The WINDOW value
- The WINTITLE value

- The APPTITLE value
- The PAD value
- The PADC value
- The OUTLINE value
- The EXPAND value.
- The MERGESAREA value
- APPLID value
- ENTKEYTEXT value
- IMAPNAME value
- IMAPROW value
- IMAPCOL value
- TMARGIN value
- BMARGIN value

You can use a PANDEF tag to define all of these values, or some of them. You can also override a specific panel default value for a referencing panel by specifying the attribute on the PANEL tag.

For instance, if you create a series of panels that all have the same dimensions and that all refer to the same help panel and key mapping list, you can define these values in a PANDEF definition, and refer to that definition in each of the application panels that use those values. The DTL compiler does the rest of the work for you, as long as the default definition is available as part of the same source file as the panels that refer to it.

For example, if you are creating a series of panels that all share the same values, you could create a PANDEF definition like this:

```
<!doctype dm system>
```

```
<pandef id=printdef help=prnhlp depth=20 width=70 keylist=printkey>
```

And refer to the panel default like this on all of the panels in that series:

```
<panel name=panel01 pandef=printdef>A Panel
:
</panel >
```

```
<panel name=panel02 pandef=printdef>Another Panel
:
</panel >
```

When you compile this source file, the PANDEF definition provides those values for the panels that refer to the panel default.

You can also use the PANDEF tag to define common values for individual PANEL attributes. For instance, if the only commonality between application panels is the dimensions, you can use a panel default to define the dimensions and refer only to those values in the application panel definitions:

```
<!doctype dm system>
```

```
<pandef id=size depth=20 width=70>
```

```
<panel name=panel01 help=help01
keylist=keylsta pandef=size>A Panel
:
</panel >
```

```

<panel name=panel 02 help=help02
keylist=keylstb pandef=size>Another Panel
:
</panel >

```

Anytime you want to change the dimensions of the application panels that refer to a panel default, you only have to make the change in one place: in the PANDEF definition.

To override a PANDEF value, you must specify that value in the PANEL definition. The following example contains a panel default that defines both dimensions and a help panel. While all three PANEL definitions refer to the panel default, the panel with the NAME value *panel03* specifies a different help panel, and thus overrides the PANDEF HELP value.

```

<!doctype dm system>

<pandef id=pandef01 depth=20 width=70 help=help01>

<panel name=panel 01 pandef=pandef01>
:
</panel >

<panel name=panel 02 pandef=pandef01>
:
</panel >

<panel name=panel 03 pandef=pandef01 help=help02>
:
</panel >

```

You can also define multiple panel defaults within a single source file, like this:

```

<!doctype dm system>
<pandef id=pandef01 depth=20 width=70 help=help01>

<pandef id=pandef02 depth=10 width=50 help=help02 keylist=clist01>

<panel name=panel 01 pandef=pandef01>
:
</panel >

<panel name=panel 02 pandef=pandef02>
:
</panel >

<panel name=panel 03 pandef=pandef01 help=help02>
:
</panel >

```



---

## Chapter 4. Variables and Variable Classes

Much of the information displayed within dialog elements is derived directly from the tags used to define it. Other information is obtained dynamically when the application is running, such as:

- Data that the user supplies
- Data that the application supplies
- Data that ISPF supplies.

In all of these cases, the data is derived from values specified in variables.

DTL provides you with tags to *declare* variables and to define the characteristics of these variables using variable classes. Variables and variable classes are considered global because they can be referred to by more than one element within the same source file. All variables referred to by dialog elements should be declared. Variable names and variable classes should be used consistently throughout dialog elements that are used in the same application.

Variables declared using DTL are accessible to your application through the dialog variable pools and variable services provided by ISPF. Within ISPF display processing, all variable values are in character format. ISPF transforms display variables between their dialog program format and internal display processing character format when retrieving and storing variable values.

### Compatibility Considerations

Although the conversion utility processes all of the variable information provided in your DTL source file and issues suppressible warning messages for missing VARDCL tags during the processing of several other tags, such as DTAFLD and LSTCOL, ISPF does not require any of the tags described in the chapter to generate a valid ISPF panel.

The conversion utility supports the SOURCE tag as an alternative means of placing variable processing and validation statements directly into the ISPF panel.

---

## Declaring Variables

You declare variables for dialog elements by coding variable declarations within a variable list. You also specify the variable class associated with each declared variable.

The variable list (VARLIST) tag and its required end tag define the variable list. You code the variable list after any variable classes and before any other tags.

To declare variables, use VARDCL (variable declaration) tags within the VARLIST definition. The VARDCL tag has two required attributes, NAME and VARCLASS.

**NAME**            The NAME attribute specifies the name of the variable used within the DTL source file.

For example, a data field definition includes a variable name in the DATAVAR attribute to specify the variable that receives data when the user enters data in the field.

**VARCLASS** The VARCLASS attribute specifies the variable class associated with the variable declaration. Variable classes define the format and length of variable data plus translations and checks to perform on the data.

In this example, the variable list contains two variable declarations referred to by the data fields in the application panel.

```
<!doctype dm system>

<varclass name=authorc type=' char 40' >
<varclass name=catnumc type=' char 10' >

<varlist>
  <vardcl name=author varclass=authorc>
  <vardcl name=catnum varclass=catnumc>
</varlist>

<panel name=books1>Book Title Search
  <area>
    <dtacol pmtwidth=20>
      <dtafld entwidth=40 datavar=author>Author
      <dtafld entwidth=10 datavar=catnum>Catalog number
    </dtacol >
  </area>
</panel >
```

**Note:**

The ISPF Dialog Tag Language conversion utility does not require that you code the VARCLASS, VARDCL, or VARLIST tags for a successful generation of a panel, command table, or message member that includes variables. If the conversion utility finds a variable that does not have an associated VARDCL definition, it issues a suppressible warning message.

The use of the VARCLASS, VARDCL, and VARLIST tags is required if you want to use the facilities provided by the CHECKL and XLATL tags.

---

## Defining Variable Classes

To complete the preceding example, we must code the variable classes that are referred to with the VARDCL VARCLASS attributes. The variable class information must be defined if the conversion utility is to generate )INIT and )PROC section statements for variable translations and validations. ("Variable Validation" on page 61 tells you how to define translations and validity checks.)

The VARCLASS (variable class) tag defines a variable class. You include variable classes in the same source file as the dialog elements and variable list that refer to them. Additionally, you must code variable classes in the source file before the variable list and dialog element definitions. You do this by coding variable classes following the DOCTYPE statement or by coding this information in an external file and embedding the file following the DOCTYPE statement.

There are two required attributes associated with the VARCLASS tag: NAME and TYPE.

**NAME**

The NAME attribute is used to identify and refer to the variable class.

**TYPE** The TYPE attribute is used to define the format and entry-field width for variable data.

In addition to the required attributes described above, the VARCLASS tag has an optional MSG attribute. This attribute specifies the message to be displayed if the variable fails any defined validity checks and no message is defined for the XLATL or CHECKL tags. Chapter 7, “Messages,” on page 155 tells you how to define messages.

## Variable Class Types

DTL supports character variables and numeric variables. In addition, the conversion utility uses the length specified in the TYPE attribute value of the VARCLASS tag to determine the entry width of fields associated with the VARCLASS tag if this width is not defined with the tag used to create the field. For more information about defining field entry widths, see Chapter 5, “Application Panel Fields,” on page 79.

### Character Variables

You can specify whether single-byte characters, double-byte characters, or mixed double- and single-byte characters are permitted, as well as the maximum number of bytes the variable can accept. Each type is described below:

Type	Description
'CHAR maximum-length'	Specifies a single-byte character string.
'DBCS maximum-length'	Specifies a double-byte character string. The maximum length must be an even number.
'MIXED maximum-length'	Specifies a character string containing single-byte characters, double-byte characters, or both.  <b>Note:</b> This type is treated as CHAR if the system does not support double-byte characters.
'ANY maximum-length'	Specifies a character string containing single-byte characters, double-byte characters, or both. It is processed by the conversion utility as MIXED.
'EBCDIC maximum-length'	Specifies a single-byte character string.
'%varname maximum-length'	Specifies that a variable name will be used for TYPE in the Panel definition. The application must ensure a valid type is set before the panel is displayed.
'VMASK maximum-length'	A VEDIT statement is added to the generated panel. The 'maximum-length' is the default length for associated variables. The application must use the VMASK service with a user-specified mask value.
'ITIME'	A VEDIT statement is added to the generated panel for associated variables. The default length for the variables is 5. The application must use the VMASK service with a mask of ITIME.

'STDTIME'	A VEDIT statement is added to the generated panel for associated variables. The default length for the variables is 8. The application must use the VMASK service with a mask of STDTIME.
'IDATE'	A VEDIT statement is added to the generated panel for associated variables. The default length for the variables is 8. The application must use the VMASK service with a mask of IDATE.
'STDDATE'	A VEDIT statement is added to the generated panel for associated variables. The default length for the variables is 10. The application must use the VMASK service with a mask of STDDATE.
'JDATE'	A VEDIT statement is added to the generated panel for associated variables. The default length for the variables is 6. The application must use the VMASK service with a mask of JDATE.
'JSTD'	A VEDIT statement is added to the generated panel for associated variables. The default length for the variables is 8. The application must use the VMASK service with a mask of JSTD.

We'll add the variable classes for *authorc* and *catnumc* to the markup example on page 58. We will assume that an author's last name has a maximum of 40 characters and that a catalog number is 10 characters.

```
<!doctype dm system>
<varclass name=authorc type='char 40'>
<varclass name=catnumc type='char 10'>

<varlist>
  <vardcl name=author varclass=authorc>
  <vardcl name=catnum varclass=catnumc>
</varlist>

<panel name=books2>Book Title Search
  <area>
    <dtacol pmtwidth=20>
      <dtafld entwidth=40 datavar=author>Author
      <dtafld entwidth=10 datavar=catnum>Catalog number
    </dtacol>
  </area>
</panel>
```

## Numeric Variables

You can use the NUMERIC type to ensure that a valid number is entered in the associated field. You can specify the total number of digits (up to 16) allowed in the number and the number of fractional digits allowed. The conversion utility will generate a VER(variable ENUM) statement for input validation.

For example, the following variable class specifies that the data entered in the associated field has a maximum number of five digits, two of which are fractional.

```
<varclass name=pricevar
type='numeric 5 2'>
```

If you do not specify an entry width with the tag that defines the associated field, the conversion utility will calculate an entry width for the field based on the NUMERIC value and allow for a sign, thousands separators, and a decimal point.

---

## Variable Validation

DTL allows you to define translate lists and validity checks as part of the variable class definition by using tags nested within the VARCLASS tag. These built-in translations and checks are especially useful because ISPF automatically performs them on variable values, so the dialog application does not need to.

**Note:** Translations and checks are performed only on variable values that are intended for display. For instance, before displaying the data from a variable specified on the DATAVAR attribute of a DTAFD tag, ISPF performs any specified translations on the variable retrieved from the application to construct the correct display value. However, ISPF does not perform translations on a variable specified as the CHECKVAR attribute of a CHOICE tag.

## Translate Lists

Translate lists provide a means of translating a displayed variable value into a different dialog variable pool value, and vice versa. Translation can occur on input (when the user enters a value), on output (the value stored in the variable pool is translated before the user sees it), or both. This is based on the USAGE value of the tag that refers to a variable using a variable class with translate lists.

To associate a translate list with a variable class, code the XLATL (translate list) tag and its required end tag within the VARCLASS definition.

The type of translation is determined by the value assigned to the FORMAT attribute of the XLATL tag. The two types of translations supported are:

- Uppercase translation
- Item translation

There is an optional MSG attribute on the XLATL tag that allows you to specify your own message to display when input translation specified by the XLATL does not result in a match. For information about defining your own messages, see Chapter 7, “Messages,” on page 155.

### Upper

Allows you to translate a value to uppercase. To specify this translation, code FORMAT=UPPER on the XLATL tag. This translation is always successful.

We’ll add a translate list to the *authorc* variable class in the example on page 61. The translate list converts the author’s name to uppercase.

```
<varclass name=authorc type='CHAR 40' msg=liba001>  
  <xlat1 format=upper>  
  </xlat1>
```

The following figure shows the results on input and output translations for the previous example.




Figure 28. Variable Translation Results

## Item Translation

Allows you to translate an internal variable value to a displayed value (or vice-versa) on an item-for-item basis. To specify this translation, either code `FORMAT=NONE` on the `XLATL` tag or omit the `FORMAT` attribute because this is the default. You define the list of possible internal values and the corresponding display values they should be translated to, or from, using the `XLATI` (translate item) tags nested within the `XLATL` tag.

To specify an internal value (the value in the variable pool) for a translate item, use the `VALUE` attribute on the `XLATI` tag. The `XLATI` tag text specifies what the user sees (for output) and enters (for input).

The display value is the `XLATI` tag text. If a display value of all blanks or a display value in which leading, trailing, or embedded blanks are preserved is desired, use the literal (`LIT`) tag and its required end tag to indicate that blanks are significant.

An explicit match is achieved during translation processing as follows:

- On input, an explicit match occurs when the value the user enters matches one of the specified display values in the translate list. An explicit match also occurs when a display value is omitted (indicating any value is acceptable) and the corresponding internal value is specified.
- On output, an explicit match occurs when the value from the variable pool matches one of the specified internal values in the translate list. An explicit match also occurs when an internal value is omitted (indicating any value is acceptable) and the corresponding display value is specified.

Omitting both the internal value and the display value does not produce an explicit match. This case is discussed later in this section.

Translate list processing is case-sensitive. To ensure that a match results when the user enters the correct display value but in a different or mixed case, code an uppercase conversion translate list before the value translate list.

In the following example, we define the variable class `dayc` to use an internal value for days of the week that is different from the display value. We also ensure that comparisons will be on uppercase values by defining a translate list with `FORMAT=UPPER` before the item translation list.

```
<!doctype dm system>
```

```

<varclass name=dayc type=' CHAR 9' >
  <xlat1 format=upper>
  </xlat1>
  <xlat1 msg=liba004>
    <xlati value=1>SUNDAY
    <xlati value=2>MONDAY
    <xlati value=3>TUESDAY
    <xlati value=4>WEDNESDAY
    <xlati value=5>THURSDAY
    <xlati value=6>FRI DAY
    <xlati value=7>SATURDAY
  </xlat1>

```

The following figure shows how variable values of variable class *dayc* are translated on input and output.




Figure 29. Variable Translation

The previous example shows one translate list with a finite number of translation items. This example assumes that the only possible internal values are 1–7 and the only possible display values are the days of the week. For input fields, a match must be found in this list, or the translation fails and message *liba004* is displayed to the user.

To allow a nonmatching value to be passed on for further processing (either to another translate list or to the validity checks that follow), you code an XLATI tag without an *internal-value* or a *display-value* to indicate that any value is acceptable, as in the following example.

```

<!doctype dm system>

<varclass name=dayc type=' CHAR 9' >
  <xlat1 format=upper>
  </xlat1>
  <xlat1>
    <xlati value=1>SUNDAY
    <xlati value=2>MONDAY
    <xlati value=3>TUESDAY
    <xlati value=4>WEDNESDAY
    <xlati value=5>THURSDAY
    <xlati value=6>FRI DAY
    <xlati value=7>SATURDAY
  <xlati>
  </xlat1>

```

Because multiple translate lists are permitted, we can expand this example to accept either the days of the week spelled out or their accepted abbreviations.

Because the last XLATI tag in the first translate list has no internal or displayed value, the input value will be passed on for further translate list or validity checking.

```
<!doctype dm system>

<varclass name=dayc type=' CHAR 9' >
  <xlatl format=upper>
  </xlatl>
  <xlatl>
    <xlati value=1>SUNDAY
    <xlati value=2>MONDAY
    <xlati value=3>TUESDAY
    <xlati value=4>WEDNESDAY
    <xlati value=5>THURSDAY
    <xlati value=6>FRIDAY
    <xlati value=7>SATURDAY
    <xlati >
  </xlatl>
  <xlat1>
    <xlati value=1>SUN
    <xlati value=2>MON
    <xlati value=3>TUES
    <xlati value=4>WED
    <xlati value=5>THUR
    <xlati value=6>FRI
    <xlati value=7>SAT
  </xlat1>
```

It is possible to omit only the internal value to indicate that any internal value is acceptable. This affects input and output translate processing differently. When translating on input, the value is not translated before being stored in the variable pool. When translating on output, any value not already matched is translated to the displayed value.

In the following example, the *branchc* variable class illustrates translate processing when only the internal value is omitted.

```
<!doctype dm system>

<varclass name=branchc type=' CHAR 3' >
  <xlatl format=upper>
  </xlatl>
  <xlatl>
    <xlati value=1>RAL
    <xlati>CRY
  </xlatl>
```





Figure 30. Variable Translation

It is also possible to omit only the display value to indicate that any display value is acceptable. This affects input and output translate processing differently. When translating on input, any value not already matched is translated to the internal value. When translating on output, the internal value is not translated before it is displayed.

We'll change the *branchc* variable class to illustrate translate processing when only the display value is omitted.

```
<!doctype dm system>
<varclass name=branchc type=' CHAR 3' >
  <xlatl format=upper>
</xlatl>
<xlatl>
  <xlati value=1>RAL
  <xlati value=2>
</xlatl>
```

Input:



Output:



Figure 31. Variable Translation

It is possible to specify that less than the full input value be entered by the use of the TRUNC attribute. Output translation is not affected.

We'll change the *branchc* variable class again to illustrate.

```
<!doctype dm system>
<varclass name=branchc type=' CHAR 3' >
  <xlatl format=upper>
</xlatl>
  <xlatl format=none trunc=1>
  <xlati value=1>RAL
  <XLATI VALUE=2>
</xlatl>
```




Figure 32. Variable Translation

## Validity Checks

You use validity checks to automatically verify data input by the user. Validity checks are coded after any translate lists.

To associate a validity check with a variable class, code the CHECKL (check list) tag and its required end tag either following the last translate list, or if no translate list exists, following the VARCLASS start tag. The individual check item that defines the test to perform is coded using the CHECKI (check item) tag nested within the check list. You can code one CHECKI tag in a CHECKL definition. However, you can code multiple CHECKL tags within a variable class definition.

There is an optional MSG attribute on the CHECKL tag that allows you to specify your own message to display when the entered value fails the test. If you do not specify a message, ISPF Dialog Manager supplies a default message for you. For more information about defining your own messages, see Chapter 7, “Messages,” on page 155.

A value entered by the user must pass the check item test for the check list to be considered successful. Furthermore, because there can be multiple check lists defined, all check lists must be successful for the validation to be successful.

The TYPE attribute of the CHECKI tag allows you to specify the various validity tests of the input. You can define the following types of validity checks:

- RANGE
- ALPHA
- VALUES
- VALUESX
- CHARS (limited to characters for HEX, BIT, and NUM tests)
- FILEID
- DSNNAME
- DSNNAMEF
- DSNNAMEFM
- DSNNAMEPQ
- DSNNAMEQ
- NAME
- NAMEF
- DBCS
- EBCDIC
- MIX
- ALPHAB

- PICT
- PICTCN
- LISTV
- LISTVX
- LEN
- ENUM
- BIT
- NUM
- HEX
- INCLUDE
- IDATE
- STDDATE
- JDATE
- JSTD
- ITIME
- STDTIME
- IPADDR4

## RANGE

To perform a range test, specify the check item TYPE attribute as RANGE. A range check allows you to check a value within a numeric range including the end points. The PARM1 attribute specifies the lower bound; PARM2 specifies the upper bound. The range delimiters can include 16 digits, and may contain a preceding sign (- or +).

The following example of a NUMERIC variable class contains a range check that ensures that catalog numbers are in the range 50 to 90000000.

```
<!doctype dm system>

<varclass name=catnumc type='NUMERIC 8' >
  <check1 msg=1iba005>
    <checki type=range parm1=50 parm2=90000000>
  </check1>
```

The conversion utility generates an ISPF range verification statement in the )PROC section.

## ALPHA

To perform an alphabetic test, specify the check item TYPE attribute as ALPHA. An alpha check limits the characters allowed to A-Z, a-z, #, \$, and @.

The following example of an alpha check in the *authorc* variable class ensures that authors' names are alphabetic.

```
<!doctype dm system>

<varclass name=authorc type='CHAR 40' >
  <check1 msg=1iba006>
    <checki type=alpha>
  </check1>
```

The conversion utility generates an ISPF alpha verification statement in the )PROC section.

## VALUES

To perform a values test, specify the check item TYPE attribute as VALUES. A values test allows you to specify a list of values. The value the user enters must

match one of the values in the list. The PARM1 attribute must have the value EQ. The PARM2 attribute specifies the list of values. Because case is respected in a VALUES check, if you want case to be ignored, you must code an UPPER translation and code the values all in uppercase.

The following example of a check in a variable class named *subject* ensures that the value entered is MATH, SCIENCE, ENGLISH, or HISTORY.

```
<!doctype dm system>

<varclass name=subject type=' char 10' >
  <xlatl format=upper>
  </xlatl >
  <check1 msg=1iba008>
    <checki type=values parm1=eq
      parm2='MATH SCIENCE ENGLISH HISTORY'>
  </check1>
```

The conversion utility generates a LIST verification statement in the )PROC section.

## VALUESX

The check item type VALUESX is the opposite of VALUES. This test allows you to specify a list of values that are not valid. The PARM1 attribute must have the value NE. The PARM2 attribute specifies the list of values that are not valid. The value the user enters cannot match any of the values specified in the list. Because case is respected in a VALUESX check, if you want case to be ignored, you must code an UPPER translation and code the values all in uppercase.

The following example of a check in a variable class named *subject* ensures that the value entered is not MATH, SCIENCE, ENGLISH, or HISTORY.

```
<!doctype dm system>

<varclass name=subject type=' char 10' >
  <xlatl format=upper>
  </xlatl >
  <check1 msg=1iba008>
    <checki type=valuesx parm1=ne
      parm2='MATH SCIENCE ENGLISH HISTORY'>
  </check1>
```

The conversion utility generates a LISTX verification statement in the )PROC section.

## CHARS

The conversion utility supports BIT, HEX and NUM validation with TYPE=CHARS. The PARM1 attribute must have the value EQ. The PARM2 attribute value can be either "01" for BIT validation, "0123456789ABCDEFabcdef" for HEX validation, or "0123456789" for NUM validation.

The following example of a check list in the *hexc* variable class validates hexadecimal values.

```
<!doctype dm system>

<varclass name=hexc type=' char 2' >
  <check1 msg=1iba008>
    <checki type=chars parm1=eq parm2='0123456789ABCDEFabcdef'>
  </check1>
```

The conversion utility generates an ISPF hex verification statement in the )PROC section.

## FILEID

To perform a FILEID test, specify the check item TYPE attribute as FILEID.

The following example of a FILEID check in the *infile* variable class ensures that specified variables contain a valid file ID in CMS syntax.

```
<!doctype dm system>
<varclass name=infile type=' CHAR 20' >
  <check1 msg=liba010>
    <checki type=fileid>
  </check1>
```

The conversion utility generates an ISPF FILEID verification statement in the )PROC section.

## DSNAME

To perform a DSNAME test, specify the check item TYPE attribute as DSNAME.

The following example of a DSNAME check in the *namefile* variable class ensures that the specified variables contain a valid TSO file name.

```
<!doctype dm system>
<varclass name=namefile type=' CHAR 44' >
  <check1 msg=liba011>
    <checki type=dsname>
  </check1>
```

The conversion utility generates a DSNAME verification statement in the )PROC section.

## DSNAMEF

To perform a DSNAMEF test, specify the check item TYPE attribute as DSNAMEF.

The following example of a DSNAMEF check in the *namefile* variable class ensures that the specified variables contain a valid TSO file name.

```
<!doctype dm system>
<varclass name=namefile type=' CHAR 44' >
  <check1 msg=liba011>
    <checki type=dsnamef>
  </check1>
```

The conversion utility generates a DSNAMEF verification statement in the )PROC section.

## DSNAMEFM

To perform a DSNAMEFM test, specify the check item TYPE attribute as DSNAMEFM.

The following example of a DSNAMEFM check in the *namefile* variable class ensures that the specified variables contain a valid TSO file name.

```
<!doctype dm system>
```

```
<varclass name=namefile type='CHAR 44' >
  <check1 msg=1iba011>
    <checki type=dsnamefm>
  </check1>
```

The conversion utility generates a DSNAMEFM verification statement in the )PROC section.

### **DSNAMEPQ**

To perform a DSNAMEPQ test, specify the check item TYPE attribute as DSNAMEPQ.

The following example of a DSNAMEPQ check in the *namefile* variable class ensures that the specified variables contain a valid TSO file name.

```
<!doctype dm system>

<varclass name=namefile type='CHAR 44' >
  <check1 msg=1iba011>
    <checki type=dsnamepq>
  </check1>
```

The conversion utility generates a DSNAMEPQ verification statement in the )PROC section.

### **DSNAMEQ**

To perform a DSNAMEQ test, specify the check item TYPE attribute as DSNAMEQ.

The following example of a DSNAMEQ check in the *namefile* variable class ensures that the specified variables contain a valid TSO file name.

```
<!doctype dm system>

<varclass name=namefile type='CHAR 44' >
  <check1 msg=1iba011>
    <checki type=dsnameq>
  </check1>
```

The conversion utility generates a DSNAMEQ verification statement in the )PROC section.

### **NAME**

To perform a NAME test, specify the check item TYPE attribute as NAME.

The following example of a NAME check in the *chapters* variable class ensures that the variable contains a valid name, following the rules of member names.

```
<!doctype dm system>

<varclass name=chapters type='CHAR 8' >
  <check1 msg=1iba012>
    <checki type=name>
  </check1>
```

The conversion utility generates a NAME verification statement in the )PROC section.

## NAMEF

To perform a NAMEF test, specify the check item TYPE attribute as NAMEF.

The following example of a NAMEF check in the *chapters* variable class ensures that the variable contains a valid name, following the rules of member names.

```
<!doctype dm system>
<varclass name=chapters type=' CHAR 8' >
  <check1 msg=liba012>
    <checki type=namef>
  </check1>
```

The conversion utility generates a NAMEF verification statement in the )PROC section.

## DBCS

To perform a DBCS test, specify the check item TYPE attribute as DBCS.

The following example of a DBCS check in the *dbdesc* variable class ensures that specified variables contain valid DBCS characters.

```
<!doctype dm system>
<varclass name=dbdesc type=' DBCS 12' >
  <check1 msg=liba013>
    <checki type=dbcs>
  </check1>
```

The conversion utility generates a DBCS verification statement in the )PROC section.

## EBCDIC

To perform an EBCDIC test, specify the check item TYPE attribute as EBCDIC.

The following example of an EBCDIC check in the *title* variable class ensures that specified variables contain valid EBCDIC characters.

```
<!doctype dm system>
<varclass name=title1 type=' CHAR 40' >
  <check1 msg=liba014>
    <checki type=ebcdic>
  </check1>
```

The conversion utility generates an EBCDIC verification statement in the )PROC section.

## MIX

To perform a MIX test, specify the check item TYPE attribute as MIX.

The following example of a MIX check in the *title2* variable class ensures that specified variables contain valid DBCS and EBCDIC characters.

```
<!doctype dm system>
```

```
<varclass name=title2 type='CHAR 40' >
  <check1 msg=liba015>
    <checki type=mix>
  </check1>
```

The conversion utility generates a MIX verification statement in the )PROC section.

## ALPHAB

To perform an ALPHAB test, specify the check item TYPE attribute as ALPHAB. An ALPHAB check limits the characters allowed to A–Z or a–z. Blanks are not allowed.

The following example of an ALPHAB check in the *chapters* variable class ensures that chapters' names are alphabetic.

```
<!doctype dm system>

<varclass name=chapters type='CHAR 8' >
  <check1 msg=liba016>
    <checki type=alphab>
  </check1>
```

The conversion utility generates an ALPHAB verification statement in the )PROC section.

## PICT

To perform a PICT check, specify the check item TYPE attribute as PICT. A PICT check allows you to specify a pattern used to validate the variable. The PARM1 attribute must have the value EQ. The PARM2 attribute contains the validation character string.

The following example of a PICT check in the *socsec* variable class validates the format of a social security number.

```
<!doctype dm system>

<varclass name=socsec type='CHAR 11' >
  <check1 msg=liba017>
    <checki type=pict parm1=eq parm2='nnn-nn-nnnn'>
  </check1>
```

The conversion utility generates a PICT verification statement in the )PROC section.

## PICTCN

To perform a PICTCN check, specify the check item TYPE attribute as PICTCN. A PICTCN check allows you to specify a pattern containing required characters to validate the variable. The PARM1 attribute contains a mask character. The PARM2 attribute contains the field-mask. The PARM3 attribute contains the validation string.

The following example of a PICTCN check in the *socsec* variable class validates the format of a social security number, including the hyphen (-) character in positions 4 and 7.

```
<!doctype dm system>

<varclass name=socsec type='CHAR 11' >
```

```

<check1 msg=liba017>
  <checki type=pictcn parm1='*' parm2='***-***-***'
    parm3='nnn-nn-nnnn'>
</check1>

```

The conversion utility generates a PICTCN verification statement in the )PROC section.

## LISTV

To perform a LISTV check, specify the check item TYPE attribute as LISTV. A LISTV test allows you to provide a variable name that has been defined by your application to contain a list of valid variable values. The PARM1 attribute must have the value EQ. The PARM2 attribute must be a variable name entered with “%” as the first character.

The following example of a LISTV check in the *majors* variable class validates major subjects, providing the application has previously defined the *listitem* variable to contain the value “MATH SCIENCE ENGLISH HISTORY”.

```

<!doctype dm system>

<varclass name=majors type='CHAR 8' >
  <check1 msg=liba018>
    <checki type=listv parm1=eq parm2=%listitem>
  </check1>

```

The conversion utility generates a LISTV verification statement in the )PROC section.

## LISTVX

The check item type LISTVX is the opposite of LISTV. A LISTVX test allows you to provide a variable name that has been defined by your application to contain a list of variable values that are not valid. PARM1 attribute must have the value NE. The PARM2 attribute must be a variable name entered with “%” as the first character.

The following example of a LISTVX check in the *majors* variable class validates major subjects, providing the application has previously defined the *listitem* variable to contain the value “MATH SCIENCE ENGLISH HISTORY”.

```

<!doctype dm system>

<varclass name=majors type='CHAR 8' >
  <check1 msg=liba018>
    <checki type=listvx parm1=ne parm2=%listitem>
  </check1>

```

The conversion utility generates a LISTVX verification statement in the )PROC section.

## LEN

To perform a LEN check, specify the check item TYPE attribute as LEN. A LEN test allows you to validate the length of the variable. The PARM1 attribute can be a relational operator or a variable name that contains a relational operator. Valid relational operators are EQ, LT, GT, LE, GE, NE, NG, or NL. If a variable name is used, it must be preceded by a “%”. The PARM2 value can be either a number or a variable name that contains the number. If you enter a number, it must be in the range of 1–99999. If you use a variable name, it must be preceded by a “%”.

The following example of a LEN check in the *chapters* variable class validates the length of chapter names.

```
<!doctype dm system>
<varclass name=chapters type=' CHAR 8' >
  <check1 msg=liba019>
    <checki type=len parm1=1e parm2=8>
  </check1>
```

The conversion utility generates a LEN verification statement in the )PROC section.

## ENUM

To perform an ENUM check, specify the check item TYPE attribute as ENUM. An ENUM check allows you to verify a variable as extended numeric. ISPF verifies variable values for correct decimal and comma notation plus correct sign placement.

The following example of an ENUM check in the *quantity* variable class ensures that specified variables are in correct extended numeric format.

```
<!doctype dm system>
<varclass name=quantity type=' CHAR 10' >
  <check1 msg=liba020>
    <checki type=enum>
  </check1>
```

The conversion utility generates an ENUM verification statement in the )PROC section.

## BIT

To perform a BIT check, specify the check item TYPE as BIT. A BIT check allows you to verify that a variable contains only 0's and 1's.

The following example of a BIT check in the *choices* variable class ensures that specified variables are in BIT format.

```
<!doctype dm system>
<varclass name=choices type=' CHAR 1' >
  <check1 msg=liba021>
    <checki type=bit>
  </check1>
```

## NUM

To perform a NUM check, specify the check item TYPE attribute as NUM. A NUM check allows you to verify a variable as a numeric character 0–9.

The following example of a NUM check in the *numbers* variable class ensures that specified variables are numeric.

```
<!doctype dm system>
<varclass name=numbers type=' CHAR 5' >
  <check1 msg=liba022>
    <checki type=num>
  </check1>
```

## HEX

To perform a HEX check, specify the check item TYPE attribute as HEX. A HEX check allows you to specify a variable that contains only hexadecimal characters (0–9, A–F).

The following example of a HEX check in the *hexc* variable class validates hexadecimal values.

```
<!doctype dm system>
<varclass name=hexc type='CHAR 2' >
  <check1 msg=1iba008>
    <checki type=hex>
  </check1>
```

## INCLUDE

To perform an INCLUDE check, specify the TYPE attribute as INCLUDE, and, at a minimum, the PARM2 attribute as ALPHA, ALPHAB, or NUM. The PARM1 and PARM3 attributes are optional.

The following example of an INCLUDE check in the *incl* variable class will allow an embedded blank and validate the values for both the ALPHA and NUM characters as defined earlier.

```
<!doctype dm system>
<varclass name=incl type='CHAR 10' >
  <check1 msg=1iba023>
    <checki type=include parm1=IMBLK parm2=ALPHA parm3=NUM>
  </check1>
```

**Note:** Refer to the *ISPF Dialog Developer's Guide and Reference* for additional information concerning panel variable verification.

## IDATE

To perform an IDATE check, specify the TYPE attribute as IDATE. An IDATE check allows you to validate an 8 character international date, including the national language date delimiter. The format for the United States is YY/MM/DD.

The following example validates an IDATE.

```
<!doctype dm system>
<varclass name=idate type='CHAR 8'>
  <check1 msg=1iba024>
    <checki type=idate>
  </check1>
```

## STDDATE

To perform an STDDATE check, specify the TYPE attribute as STDDATE. An STDDATE check allows you to validate a 10 character standard date, including the national language date delimiter. The format for the United States is YYYY/MM/DD.

The following example validates an STDDATE.

```
<!doctype dm system>
```

```
<varclass name=stddate type='CHAR 10'>
  <check1 msg=liba025>
    <checki type=stddate>
  </check1>
```

## JDATE

To perform a JDATE check, specify the TYPE attribute as JDATE. A JDATE check allows you to validate a 6 character Julian date. The format is YY.DDD.

The following example validates a JDATE.

```
<!doctype dm system>

  <varclass name=jdate type='CHAR 6'>
    <check1 msg=liba026>
      <checki type=jdate>
    </check1>
```

## JSTD

To perform a JSTD check, specify the TYPE attribute as JSTD. A JSTD check allows you to validate an 8 character Julian date. The format is YYYY.DDD.

The following example validates a JSTD.

```
<!doctype dm system>

  <varclass name=jstd type='CHAR 8'>
    <check1 msg=liba026>
      <checki type=jstd>
    </check1>
```

## ITIME

To perform an ITIME check, specify the TYPE attribute as ITIME. An ITIME check allows you to validate a 5 character international time, including the national language time delimiter. The format for the United States is HH:MM.

The following example validates an ITIME.

```
<!doctype dm system>

  <varclass name=itime type='CHAR 5'>
    <check1 msg=liba027>
      <checki type=itime>
    </check1>
```

## STDTIME

To perform a STDTIME check, specify the TYPE attribute as STDTIME. A STDTIME check allows you to validate an 8 character standard time, including the national language time delimiter. The format for the United States is HH:MM:SS.

The following example validates a STDTIME.

```
<!doctype dm system>

  <varclass name=stdtime type='CHAR 8'>
    <check1 msg=liba028>
      <checki type=stdtime>
    </check1>
```

## IPADDR4

To perform a IPADDR4 check, specify the TYPE attribute as IPADDR4. A IPADDR4 check allows you to verify a 15 character IP address of the format xxx.xxx.xxx.xxx.

The following example validates an IPADDR4.

```
<!doctype dm system>
  <varclass name=ipaddr4 type='CHAR 15'>
    <check1 msg=liba029>
      <checki type=ipaddr4>
    </check1>
```

## Overriding Variable Classes

Some tags, such as DTAFLD, allow you to specify a different variable class for a variable other than the default one that was specified when the variable was declared using the VARDCL tag. This is called an overriding variable class and is used to perform different translates and validity checks from those provided by the default variable class.



---

## Chapter 5. Application Panel Fields

Most of the direct interaction that takes place between the user and the application is through the use of interactive fields. They provide a means for the user to communicate data to the application, as well as receive data from the application.

The type of interaction the user has with the application depends on the task. The task, in turn, determines the fields' characteristics. The appearance of the fields, the application's response to user input, and assistance such as messages and help information must all be considered when defining an interactive field.

In this chapter, we tell you how to use the Dialog Tag Language to define the following types of fields and their operating characteristics:

- Data fields
- Selection fields
- List fields.

This chapter begins with a description of field prompts for data fields and selection fields.

---

### Field Prompts

A field prompt is static, descriptive text that explains the field it is associated with. Data fields and selection fields support the use of field prompts. To define a field prompt for a data field or selection field, specify the prompt text as the tag text on the DTAFLD and SELFLD tags.

The PMTLOC attribute defines the location of the prompt using one of the following values:

**PMTLOC = ABOVE**

The prompt appears above and left-aligned with the field. This is the default for selection fields.

**PMTLOC = BEFORE**

The prompt appears directly in front of and on the same line as the field. This is the default for data fields.

You should define the amount of space the prompt uses by specifying the PMTWIDTH attribute on the DTAFLD and SELFLD tags. If the prompt text is longer than the width you specify on PMTWIDTH, the prompt is word-wrapped on multiple lines. Using the PMTWIDTH attribute can ensure that multiple fields with prompts are aligned evenly. If you do not specify PMTWIDTH, the field prompt length is determined by the length of the prompt text.

When PMTLOC=BEFORE, the conversion utility inserts leader dots at the end of the prompt text to fill the specified prompt width. For output-only data fields, a colon is used in place of the last leader dot. For fields with this prompt location, it is a good idea to specify a PMTWIDTH with a value that allows for leader dots after the prompt text. This lends consistency to the panel appearance. The conversion utility issues a warning message when there is insufficient space for leader dots.



```

        <choi ce>50 - 64
        <choi ce>over 65
    </sel fld>
    <di vi der gutter=5>
    <sel fld name=paymeth selwidth=24 pmtwidth=20>Method of payment
        <choi ce>Cash
        <choi ce>Check
        <choi ce>Credi t card
    </sel fld>
    </regi on>
    <di vi der>
    <dtafld datavar=pay entwidth=11 pmtloc=above pmtwidth=7>Payment
    </area>
</panel >

```

Figure 34 shows how the prompt width can affect the appearance of the prompt text.




Figure 34. Prompt Widths

The prompts in the two data fields are formatted differently. The prompt text of the first data field is not wrapped. It formats on one line, using as much space as necessary (up to the maximum available formatting width). The second data field has the same prompt text, with a prompt width that is less than the amount of space needed, so the prompt text is wrapped to as many lines as are needed. Similarly, the two selection fields also demonstrate how the prompt text appears based on the prompt width. The prompt text of data fields and selection fields can be displayed differently by omitting or specifying different values for the PMTWIDTH attribute.

The following is the markup used to demonstrate the field prompts in Figure 34:

```

<!doctype dm system>

<varclass name=sampcls type='char 10'>
<varclass name=char1 type='char 1'>

<varlist>
  <vardcl name=sampl ea varclass=sampcls>
  <vardcl name=sampl eb varclass=sampcls>
  <vardcl name=sampl ec varclass=char1>

```

```

    <vardcl name=sampled varclass=char1>
</varlist>

<panel name=pmt02>Application Name
  <area>
    <dtacol entwidth=10 selwidth=76>
    <dtafld datavar=samplea>This is a very, very long prompt
    <divider>
    <dtafld datavar=sampleb pmtwidth=12>This is a very, very long prompt
    <divider>
    <selfld name=samplec>Here is another long prompt used to show
      word-wrapping of prompts
      <choice>Choice 1
      <choice>Choice 2
    </selfld>
    <divider>
    <selfld name=sampled pmtwidth=14>Here is another long prompt used to show
      word-wrapping of prompts
      <choice>Choice 1
      <choice>Choice 2
    </selfld>
    </dtacol>
  </area>
</panel>

```

---

## Defining Data Fields

Data fields are used to display variable data and to allow the user to enter data. To define a data field, use the DTAFD tag. Every data field must have an associated variable, which is specified on the required DATAVAR attribute. Like all variables used on the panel, the variable named on the DATAVAR attribute can be declared using the VARDCL tag.

The purpose of the data field is defined using one of these values on the USAGE attribute of the DTAFD tag:

- IN** Defines an entry (input-only) data field. An entry data field allows the user to enter data. When an entry field is initially displayed, it is padded with underscore characters, unless the data is right-justified.
- OUT** Defines an output-only data field. An output-only data field is used to display the current value of the variable associated with the data field. The user cannot tab to or interact with an output-only field.
- BOTH** Defines an input/output data field. When an input/output field is initially displayed, the current value of the associated variable is displayed, and the user can enter data into the field as well. If you do not specify the USAGE attribute, BOTH is the default.

Data fields support field prompts, which can be placed in front of or above the data field.

This panel contains examples of all three types of data fields:




Figure 35. Data Fields

Here is the markup for Figure 35:

```
<!doctype dm system>

<varclass name=titlecls type=' char 50' >
<varclass name=bookcls type=' char 20' >
<varclass name=pagecls type=' numeric 5' >
<varclass name=datecls type=' char 8' >

<varlist>
  <vardcl name=title varclass=titlecls>
  <vardcl name=author varclass=bookcls>
  <vardcl name=publish varclass=bookcls>
  <vardcl name=pages varclass=pagecls>
  <vardcl name=curdate varclass=datecls>
</varlist>

<panel name=dfdxdmp1a>Library Inventory
  <topinst>To add a book to the inventory, complete the fields below,
    and then press Enter.
  <area>
    <dtafld datavar=title usage=in pmtwidth=14>Title
    <dtafld datavar=author usage=in entwidth=20 pmtwidth=14>Author
    <dtafld datavar=publish entwidth=20 pmtwidth=14>Publisher
    <dtafld datavar=pages usage=in entwidth=5 pmtwidth=14>Number of pages
    <divider type=solid gutter=3 gap=no>
    <dtafld datavar=curdate usage=out entwidth=8 pmtwidth=20>Today's date is
  </area>
</panel>
```

In the previous example, there are three input-only data fields, an input/output data field, and an output-only data field. The value of the associated variable is not displayed in an input-only data field, so when the panel is initially displayed, the **Title**, **Author**, and **Number of pages** fields are blank. The **Publisher** data field assumes the default, BOTH, so the current value of the associated variable, *publish*, is displayed in the data field when the panel is initially displayed. The output-only data field is used to display the current date. The user cannot interact with this data field, since it is used only to display variable data. The user can enter data into any of the data fields except the output-only field.

## Data Field Width

The width of a data field is determined by the value you specify for the ENTWIDTH attribute of the DTAFLD tag. You should specify ENTWIDTH for all data fields. In the previous example, ENTWIDTH is specified for each DTAFLD tag except for the **Title** field, whose length is determined as discussed next.

If you do not specify a value for ENTWIDTH, the width of the data field is determined by the value specified for the TYPE attribute of the VARCLASS tag associated with the variable named in the DTAFLD DATAVAR attribute. For example, the **Title** field in Figure 35 on page 83 has an entry width of 50 as determined by the variable class *titcls*, which has the TYPE value "char 50". This variable class is associated with the data field through the variable declaration *title*, which is specified as the data field's DATAVAR attribute value. For more information about variables and variable classes, see Chapter 4, "Variables and Variable Classes," on page 57.

The formatted width of the field is 2 positions more than the ENTWIDTH value to provide for an attribute byte both before and after the field. The maximum width for an entry field is the remaining available formatting width in the panel.

**Note:** The conversion utility tracks the remaining width available for use. For data fields, the width of the entry field has first priority, followed by the prompt width, and then the description width.

## Data Field Descriptions

In addition to a field prompt, you can provide additional descriptive text for a data field using the DTAFLDD (data field description) tag. You code the DTAFLDD tag following the definition of the data field being described. The DTAFLDD tag has no attributes or required end tag. Multiple data field descriptions can be coded if necessary, and each description begins a new line.

The data field description appears to the right of the entry field, taking up as much room as is available, unless you have used the DESWIDTH attribute of the DTAFLD tag to specify a width for the description. If the DESWIDTH attribute is defined, the data field description is displayed within the description width specified (or defaulted), and word-wrapped on multiple lines, if necessary.

This panel contains data field descriptions.

Library Inventory

To add a book to the inventory, complete the fields below, then press Enter.

Title . . . . . \_\_\_\_\_

Author . . . . . \_\_\_\_\_ Last name, First name, M.I.

Publisher . . . . . SPOTH AND CRICK

Total number of pages . . . . . \_\_\_\_\_ (1 - 99999)

Figure 36. Data Field Description

Here is the markup used to generate the panel in Figure 36:

```

<!doctype dm system>

<varclass name=titlecls type='char 50'>
<varclass name=bookcls type='char 20'>
<varclass name=pagecls type='numeric 5'>

<varlist>
  <vardcl name=title varclass=titlecls>
  <vardcl name=author varclass=bookcls>
  <vardcl name=publish varclass=bookcls>
  <vardcl name=pages varclass=pagecls>
</varlist>

<panel name=dfdxmp4>Library Inventory
  <topinst>To add a book to the inventory, complete the fields below,
  then press Enter.
  <area>
    <dtacol pmtwidth=15>
      <dtafld datavar=title usage=in entwidth=50>Title
      <dtafld datavar=author usage=in entwidth=20 deswidth=30>Author
        <dtafldd>Last name, First name, M.I.
      <dtafld datavar=publish entwidth=20>Publisher
      <dtafld datavar=pages usage=in entwidth=5 deswidth=15>
        Total number of pages
        <dtafldd>(1 - 99999)
    </dtacol>
  </area>
</panel>

```

## Data Field Help

ISPF allows you to provide help on a data field using the HELP attribute on the DTAFLD tag. If you specify the name of a help panel or message for a data field, ISPF knows which help information to display when the user selects help on the data field. If you do not specify help for a data field, the extended help panel (specified with the HELP attribute of the enclosing PANEL tag) is displayed.

The following example shows how to provide help for data fields.

```
<!doctype dm system>

<varclass name=titlecls type='char 50'>
<varclass name=bookcls type='char 20'>
<varclass name=pagecls type='numeric 5'>

<varlist>
  <vardcl name=title varclass=titlecls>
  <vardcl name=author varclass=bookcls>
  <vardcl name=publish varclass=bookcls>
  <vardcl name=pages varclass=pagecls>
</varlist>

<panel name=dfdcmp5>Library Inventory
  <topinst>To add a book to the inventory, complete the fields below,
  then press Enter.
  <area>
    <dtacol pmtwidth=15>
      <dtafld datavar=title help=h1ptit1 entwidth=50>Title
      <dtafld datavar=author help=h1pauth entwidth=20 deswidth=30>Author
        <dtafldd>Last name, First name, M.I.
      <dtafld datavar=publish help=h1ppubl1 entwidth=20>Publisher
      <dtafld datavar=pages help=h1ppage entwidth=5 deswidth=15>
        Total number of pages
        <dtafldd>(1 - 99999)
    </dtacol>
  </area>
</panel>
```

## Other Data Field Attributes

There are several other attributes you can specify to tailor a data field to meet the requirements of your application. See “DTAFLD (Data Field)” on page 306 for more information. The following list describes each of the remaining DTAFLD attributes and what you can do with them:

- REQUIRED** This attribute allows you to indicate if the data field requires input. When you assign a value of YES to this attribute, the user must enter data into the field before ISPF accepts the panel as valid. The default REQUIRED value is NO. This attribute is only valid for data fields defined as input-only or as input/output.
- MSG** This attribute identifies the message that should be displayed when the user does not enter any data into an input-required data field. If you do not specify this attribute, ISPF displays a default message. This attribute is valid only if REQUIRED=YES.
- Chapter 7, “Messages,” on page 155 tells you how to define application messages.
- ALIGN** This attribute allows you to align the variable data within the data field. The default value for ALIGN is *start*, which aligns the data from the left side of the data field. You can also center the data within the field with the *center* value, or justify the data from the right side of the field with the *end* value.
- AUTOTAB** This attribute provides automatic cursor movement between data fields. If you specify AUTOTAB=YES for a data field, the cursor automatically moves to the next field that is capable of input. If no other field capable of input exists on the panel, the cursor returns to the beginning of the data field.

<b>DISPLAY</b>	The value you assign to this attribute, either <i>yes</i> (the default) or <i>no</i> , determines if the data appears on the screen when the user enters it. One way to use DISPLAY=NO is for defining a password.
<b>VARCLASS</b>	This attribute allows you to override the variable class that is specified on the variable declaration (VARDCL) for the data field's data variable (DATAVAR). See Chapter 4, "Variables and Variable Classes," on page 57 for a description of variables and variable classes.
<b>FLDSPACE</b>	This attribute specifies the space reserved for the data-entry field. When the FLDSPACE value is larger than the entry width plus any attributes, blanks are added following the data-entry field. This provides spacing before DTAFLDD tag descriptions.
<b>NOENDATTR</b>	This attribute specifies that no ending attribute character will be placed after the data field. NOENDATTR is valid only when WINDOW=NO is specified or when data fields are being formatted within a horizontal region.
<b>PAD</b>	This attribute specifies the pad character for initializing the field. You can define this attribute as a variable name preceded by a "%".
<b>PADC</b>	This attribute specifies the conditional padding character to be used for initializing the field. You can define this attribute as a variable name preceded by a "%".
<b>OUTLINE</b>	This attribute provides for displaying lines around the field on a DBCS terminal. You can define this attribute as a variable name preceded by a "%".
<b>PMTFMT</b>	This attribute controls the generation of prompt leader characters. The default is to create CUA leader dots.
<b>PSVAR</b>	This attribute provides the name of a variable that is to be set when a DTAFLD is clicked on for point-and-shoot selection.
<b>PSVAL</b>	This attribute provides the value to be placed in the field specified by the PSVAR attribute.
<b>PAS</b>	This attribute can be used to provide a variable name that will contain the value ON to enable point-and-shoot for this data field, or OFF to disable point-and-shoot. When PSVAR and PSVAL have been specified without the PAS attribute, the point-and-shoot field will be automatically enabled.
<b>CSRGRP</b>	The CSRGRP attribute, in combination with the PAS attribute, is used to specify a cursor group for GUI mode operation.
<b>EXPAND</b>	The EXPAND attribute, used in combination with EXPAND=xy on the PANEL definition, causes the expand characters to be added to the DTAFLD definition, effectively allowing ENTWIDTH to expand.
<b>FLDWIDTH</b>	The FLDWIDTH attribute, used in combination with WINDOW=NO on the PANEL definition, provides the width of a data field that spans multiple lines.
<b>ATTRCHANGE</b>	The ATTRCHANGE attribute specifies that, if required, an

additional )ATTR section entry (which can apply to multiple fields) be created instead of a unique “.ATTR” override entry for the current field.

<b>INIT</b>	The INIT attribute provides an initial value for the data field.
<b>DBALIGN</b>	The DBALIGN attribute is used only for DBCS language conversion when PMTLOC=ABOVE to align the prompt text with the data field.
<b>DEPTH</b>	This attribute defines the depth reserved for the field. When the panel is displayed in GUI mode, a field specified as point-and-shoot results in a push button displayed with the specified DEPTH.
<b>IMAPNAME</b>	This attribute specifies the name of an image to be placed on the point-and-shoot push button when it is displayed in GUI mode.
<b>IMAPNAMEP</b>	This attribute specifies the name of an image to be placed on the point-and-shoot push button after it has been pushed when it is displayed in GUI mode.
<b>PLACE</b>	This attribute specifies the position of the image relative to the text within the point-and-shoot push button.
<b>PMTSKIP</b>	This attribute, used during horizontal field formatting of input fields, specifies that the cursor should move past the prompt text to the input field.
<b>DESSKIP</b>	This attribute, used during horizontal field formatting of input fields, specifies that the cursor should move past the description text to the next input field.
<b>FLDTYPE</b>	This attribute specifies whether CUA or traditional ISPF attribute definitions are used.
<b>COLOR</b>	When FLDTYPE=ISPF, this attribute specifies the color of the field.
<b>INTENS</b>	When FLDTYPE=ISPF, this attribute specifies the intensity of the field.
<b>HILITE</b>	When FLDTYPE=ISPF, this attribute specifies the highlighting for the field.
<b>ATTRCHAR</b>	This attribute provides a user selected panel attribute for the data field.
<b>CAPS</b>	This attribute specifies whether the field is displayed in uppercase characters.
<b>NOJUMP</b>	This attribute specifies that the JUMP function is disabled for the data field.
<b>AUTOTYPE</b>	This attribute specifies whether ISPF panel logic is added to support the AUTOTYPE function.
<b>AUTOVOL</b>	This attribute specifies an associated volume name when AUTOTYPE = DSN.
<b>AUTODMEM</b>	This attribute specifies whether a member name is part of the data set name when AUTOTYPE = DSN.
<b>VARDC</b>	This attribute specifies whether the field name is validated to the panel variables specified with the VARDCL tag.

---

## Defining Selection Fields

Selection fields allow the user to select from a group of choices on an application panel. You can specify if only one choice can be selected from a selection field, or if multiple choices are allowed.

In either case, you use the same DTL tags to define a selection field. The SELFLD (selection field) tag and its required end tag define a selection field. The CHOICE (selection choice) tag defines a choice within a selection field. You code the CHOICE tags between the SELFLD start and end tags, like this:

```
<sel fld>  
  <choice>  
  <choice>  
  <choice>  
</sel fld>
```

Each CHOICE tag defines a choice within the selection field.

Like data fields, selection fields support field prompts, which can be placed in front of or above the selection field. Field prompts are described in “Field Prompts” on page 79.

To define the selection field type use the TYPE attribute of the SELFLD tag. The values you can assign to TYPE are:

- |               |   |
|---------------|---|
| <b>SINGLE</b> | Specifies the selection field as being a single-choice field. Choices in a single-choice selection field appear in a list with an entry field preceding the first choice in the list. The conversion utility prefixes the text of each choice with a number, so the selection field choices are numbered sequentially. Users indicate choice selection by typing the number of the choice they want in the entry field. |
| <b>MULTI</b>  | Specifies the selection field as being a multiple-choice field. Choices in a multiple-choice selection field appear in a list with a single-character entry field preceding each choice. Users indicate choice selection by typing any nonblank character in the entry fields.  |
| <b>MENU</b>   | Specifies the selection field as being a menu-choice field. Choices in a menu-choice selection field are similar to those in a single-choice selection field. TYPE=MENU is valid only when the MENU keyword has been specified on the PANEL tag.  |
| <b>MODEL</b>  | Specifies the selection field as being a model-choice field. Choices in a model-choice selection field are similar to those in a menu-choice selection field. TYPE=MODEL is valid only when the MENU keyword has been specified on the PANEL tag.   |
| <b>TUTOR</b>  | Specifies the selection field as being a tutor-choice field. Choices in a tutor-choice selection field are similar to those in a menu-choice selection field. TYPE=TUTOR is valid only when the MENU keyword has been specified on the PANEL tag.   |

The CHOICE tag has two attributes associated with it that are important when defining a selection field: CHECKVAR and MATCH. The CHECKVAR and MATCH attributes are used to preselect choices in the selection field. The CHECKVAR attribute can also communicate to the application which selections were made by the user.

The value specified on the CHECKVAR attribute is the name of a dialog variable that is defined by the application. Both the application and ISPF can set the check variable. The following sections describe how the CHECKVAR and MATCH attributes are used for each type of selection field.

## Single-Choice Fields

Use a single-choice selection field when you have a fixed set of choices that are mutually exclusive. That is, the user can select only one of the choices by typing the choice number in the entry field. You can specify the preselected choice in a single-choice selection field so that one item is already selected when the panel is displayed. The user can either leave the preselected choice or enter a different choice number.

To preselect choices in a single-choice selection field, and to find out which choice was selected by the user, you should specify the CHECKVAR and MATCH attributes for each CHOICE tag. For a single-choice field, all of the enclosed choices should refer to the same check variable, but they should have unique MATCH values. The following markup shows how this is coded.

```
<!doctype dm system>

<varclass name=daycls type='char 1'>

<varlist>
  <vardcl name=day varclass=daycls>
  <vardcl name=choice varclass=daycls>
</varlist>

<panel name=singssel>Schedule Appointments
  <topinst>Choose the most convenient day for your appointment,
    then press Enter.
  <area>
    <selfld name=choice selwidth=30 pmtwidth=9>Weekdays:
      <choice checkvar=day match=M>Monday
      <choice checkvar=day match=T>Tuesday
      <choice checkvar=day match=W>Wednesday
      <choice checkvar=day match=H>Thursday
      <choice checkvar=day match=F>Friday
    </selfld>
  </area>
</panel>
```

To preselect a certain choice, set the check variable, *day*, to the match value for that choice. Assume that the check variable, *day*, is set to M before the panel is displayed. When the panel is displayed, the choice, **Monday**, is selected as shown in Figure 37 on page 91.



Figure 37. Single-Choice Selection Field

If the user decides that another day is more convenient, another choice might be selected. This causes the check variable to be updated with the match value of the newly selected choice. For example, if the user selects **Friday** (by typing “5” in the entry field), the check variable, *day*, will contain “F” when control is returned to the application.

**Note:** The TYPE attribute does not have to be specified on a single-choice selection field because TYPE=SINGLE is the default. However, you must specify the NAME attribute for single-choice selection fields.

## Multiple-Choice Fields

Use a multiple-choice selection field when you have several choices for the user, but they are not mutually exclusive. Each choice acts independently as a toggle, and selecting one of the choices does not affect any of the other choices in the selection field.

To preselect choices in a multiple-choice selection field, and to find out which choices were selected by the user, specify the CHECKVAR, MATCH, and NOMATCH attributes for each CHOICE tag.

On a multiple-choice selection field, define a unique check variable for each enclosed CHOICE. You can let the MATCH value default to 1, or specify the MATCH attribute with a value of your choice. Also, you can let the NOMATCH value default to 0, or specify the NOMATCH attribute with a value of your choice. Here is how a multiple-choice selection field is coded:

```
<!doctype dm system>

<varclass name=sampcls type =' char 1' >

<varlist>
  <vardcl name=dry varclass=sampcls>
  <vardcl name=cut varclass=sampcls>
  <vardcl name=per varclass=sampcls>
  <vardcl name=fac varclass=sampcls>
  <vardcl name=man varclass=sampcls>
```

```

<vardcl name=ped varclass=sampcl s>
<vardcl name=ch1 varclass=sampcl s>
<vardcl name=ch2 varclass=sampcl s>
<vardcl name=ch3 varclass=sampcl s>
<vardcl name=ch4 varclass=sampcl s>
<vardcl name=ch5 varclass=sampcl s>
<vardcl name=ch6 varclass=sampcl s>
</varlist>

<panel name=multsel>Schedule Appointments
  <area>
    <dtacol pmtwidth=45 selwidth=76>
      <sel fld type=multi>Choose the services needed, then press Enter.
        <choice name=ch1 checkvar=dry>Dry haircut
        <choice name=ch2 checkvar=cut>Shampoo, haircut, and style
        <choice name=ch3 checkvar=per>Permanent or body wave
        <choice name=ch4 checkvar=fac>Facial
        <choice name=ch5 checkvar=man>Manicure
        <choice name=ch6 checkvar=ped>Pedicure
      </sel fld>
    </dtacol>
  </area>
</panel>

```

You specify preselected choices for a multiple-choice selection field just as you would for a single-choice selection field. Set the check variable for the preselected choices to the match values (or the default value of 1) for those choices. When a choice is preselected, a slash (/) is displayed in the entry field preceding the choice.

When the user types a value in an entry field in a multiple-choice selection field, ISPF toggles the choice as follows:

- If the choice is already selected and the user enters a blank in the entry field, ISPF deselects the choice and sets the check variable to the NOMATCH value for the choice, or to 0 if the NOMATCH attribute is not specified.
- If the choice is not selected and the user types a nonblank character in the entry field, ISPF selects the choice and sets the check variable to the MATCH value for the choice, or to 1 if the MATCH attribute is not specified. If the choice is not selected, ISPF sets the check variable to the NOMATCH value for the choice, or to 0 if the NOMATCH attribute is not specified.

In the preceding markup, the MATCH attribute was not specified, so the check variables toggle between 0 and 1 (the default MATCH and NOMATCH values) as the user selects and deselects items.

Because ISPF is setting the check variable, you should not use the SETVAR or the TOGVAR attributes of the ACTION tag to refer to the check variable.

Figure 38 on page 93 shows how the multiple-choice selection field in the preceding markup appears with the choices **Facial** and **Pedicure** preselected.




Figure 38. Multiple-Choice Selection Field

## Menu-Choice Fields

Use a menu-choice selection field to create an ISPF option menu. Menu-choice fields are similar to single-choice fields. That is, the user can select only one of the choices presented. The entry field for this type of selection field is the command line, which is formatted with the word *Option* instead of *Command*. As with single-choice selections, you can specify a preselected choice so that one item is already selected when the panel is displayed.

The CHOICE tag is followed by an ACTION tag which specifies the type of selection (PANEL, PGM, CMD, or EXIT), and other attributes required by the ISPF SELECT service.

When creating an option menu, the MENU keyword is required on the PANEL tag. The optional PRIME keyword causes the creation of a primary option menu. The SELFLD tag must specify TYPE=MENU. Depending on the panel being created, the SELFLD tag attributes ENTWIDTH, FCHOICE, and TRAIL, and the CHOICE tag attribute SELCHAR might be required. See Chapter 13, “Tag Reference,” on page 205 for more information on the PANEL, SELFLD, CHOICE, and ACTION tags.

The following markup creates a sample option menu:

```
<!doctype dm system ()>
<!-- MENU selection panel example -->
<panel name=menuse11 menu>Sample Option Menu
  <topinst>Enter a selection choice

  <region indent=4>
    <sel fld type=menu entwidth=1 selwidth=40>
      <choice checkvar=xtest1 match=a>Select Command
        <action run=tstch1 type=cmd parm=' 1234'
          newappl=aaaa passlib newpool suspend
          lang=crex nocheck mode=fscr>
      <choice checkvar=xtest1 match=b>Select Panel
        <action run=tstch2 type=panel
```

```

        addpop newappl=aaaa passlib newpool suspend>
    <choice checkvar=xtest1 match=c>Select Program
        <action run=tstch3 type=pgm parm=abcd
            newappl=aaaa passlib newpool suspend
            nocheck mode=fscr>
    <choice checkvar=xtest1 match=x>Exit
        <action run=exit type=exit>
    </sel fld>
</region>

<cmdarea>
</panel>

```

The resulting panel is:

```

Sample Option Menu

Enter a selection choice

1 Select Command
2 Select Panel
3 Select Program
4 Exit

Option ===> _____

```

Figure 39. Sample Option Menu

## Model-Choice Fields

Use a model-choice selection field to create an ISPF edit model selection menu. Model-choice fields are similar to single-choice or menu-choice fields. That is, the user can select only one of the choices presented. The entry field for this type of selection field is the command line, which is formatted with the word *Option* instead of *Command*. As with single-choice or menu-choice selections, you can specify a preselected choice so that one item is already selected when the panel is displayed.

The CHOICE tag is followed by an ACTION tag which specifies the type of selection (PANEL, PGM, CMD, or EXIT), and other attributes required by the ISPF SELECT service.

When creating an edit model menu, the MENU keyword is required on the PANEL tag. The SELFLD tag must specify TYPE=MODEL. Depending on the panel being created, the SELFLD tag attributes ENTWIDTH, FCHOICE, and TRAIL, and the CHOICE tag attributes SELCHAR, HINDEX, and TRUNC might be required. See Chapter 13, "Tag Reference," on page 205 for more information about the PANEL, SELFLD, CHOICE, and ACTION tags.

## Tutor-Choice Fields

Use a tutor-choice selection field to create an ISPF tutorial selection menu. Tutor-choice fields are similar to menu-choice fields. That is, the user can select only one of the choices presented. The entry field for this type of selection field is the command line, which is formatted with the word *Option* instead of *Command*. As with menu-choice selections, you can specify a preselected choice so that one item is already selected when the panel is displayed.

The CHOICE tag is followed by an ACTION tag that must specify the type of selection as PANEL, and other attributes required by the ISPF SELECT service.

When creating a tutorial menu, the MENU keyword is required on the PANEL tag. The SELFLD tag must specify TYPE=TUTOR. Depending on the panel being created, the SELFLD tag attributes ENTWIDTH and FCHOICE, and the CHOICE tag attribute SELCHAR might be required. See Chapter 13, "Tag Reference," on page 205 for more information on the PANEL, SELFLD, CHOICE, and ACTION tags.

## Selection Field Help

ISPF enables you to provide help on selection fields. For single-choice selection fields, you specify the name of a help panel or message for the selection field with the HELP attribute of the SELFLD tag. For multiple-choice selection fields, you specify

is used to control the formatting of panels defined with horizontal regions. If you do not specify a SELWIDTH value, the conversion utility reserves the remaining available formatting width for the text.

When specifying an explicit SELWIDTH value, you must take into consideration the components of the selection field, as well as the *choice-description-text*. The conversion utility reserves a number of positions on the lines that selection field choices appear on for the entry fields, 3270 attributes, and, in the case of single-choice, menu-choice, model-choice, and tutor-choice selection fields, the choice prefixes. See page 467 for a discussion of the amount of space reserved for each choice type.

These reserved positions must be added to the length of the *choice-description-text* in the SELWIDTH value you specify. For example, the following markup contains two selection fields, one single-choice and one multiple-choice, within a horizontal region. To format the selection fields properly, ensure that the SELWIDTH values you specify are adequate for the reserved positions and the *choice-description-text*. The largest *choice-description-text* in the first selection field is 9 characters, which, when combined with the 10 reserved positions in the field, means you must specify a SELWIDTH value of at least 19. The largest *choice-description-text* in the second selection field is 27 characters, which, when combined with the 5 reserved positions in the field, means you must specify a SELWIDTH value of at least 32.

See page 467 for more information about SELWIDTH.

```
<!doctype dm system>
<varclass name=char1 type='char 1'>
<varclass name=char2 type='char 2'>

<varlist>
  <vardcl name=person varclass=char2>
  <vardcl name=ch1 varclass=char1>
  <vardcl name=ch2 varclass=char1>
  <vardcl name=ch3 varclass=char1>
  <vardcl name=ch4 varclass=char1>
  <vardcl name=ch5 varclass=char1>
  <vardcl name=ch6 varclass=char1>
</varlist>

<panel name=servsel>Service Selections
  <topinst>Select the stylist and services you want, then press Enter.
  <area>
    <region dir=horiz>
      <sel fld name=person selwidth=19 pmtwidth=15>Stylist
        <choice checkvar=stylst match=1>Cecilia
        <choice checkvar=stylst match=2>Dana
        <choice checkvar=stylst match=3>Laurel
        <choice checkvar=stylst match=4>Pierce
        <choice checkvar=stylst match=5>Stephnie
      </sel fld>
    <divider>
      <sel fld type=multi selwidth=32 pmtwidth=15>Services
        <choice name=ch1 checkvar=dry>Dry haircut
        <choice name=ch2 checkvar=cut>Shampoo, haircut, and style
        <choice name=ch3 checkvar=per>Permanent or body wave
        <choice name=ch4 checkvar=fac>Facial
        <choice name=ch5 checkvar=man>Manicure
        <choice name=ch6 checkvar=ped>Pedicure
      </sel fld>
    </region>
  </area>
</panel>
```

Here is the formatted result:

```
Service Selections

Select the stylist and services you want, then press Enter.

Stylist          Services
— 1. Cecilia    — Dry haircut
  2. Dana       — Shampoo, haircut, and style
  3. Laurel     — Permanent or body wave
  4. Pierce     — Facial
  5. Stephenie — Manicure
                   — Pedicure
```

Figure 40. Selection Field SELWIDTH Attribute

## Other Selection Field Attributes

There are several other attributes you can specify to tailor a selection field to meet the requirements of your application. See “SELFLD (Selection Field)” on page 464 for more information. The following list describes each of the remaining SELFLD attributes and what you can do with them:

- ENTWIDTH** This attribute controls the entry width for single-choice, menu-choice, model-choice, and tutor-choice selections.
- REQUIRED** This attribute allows you to indicate if the single-choice selection field requires input. When you assign a value of YES to this attribute, the user must enter data into the field before ISPF accepts the panel as valid. The default REQUIRED value is NO.
- MSG** This attribute identifies the message that should be displayed when the user does not enter any data into the selection field. If you do not specify this attribute, ISPF displays a default message. This attribute is valid only if REQUIRED=YES.
- Chapter 7, “Messages,” on page 155 tells you how to define application messages.
- FCHOICE** This attribute controls the first choice number for single-choice, menu-choice, model-choice, and tutor-choice selections. The value can be either 0 or 1.
- AUTOTAB** This attribute provides automatic cursor movement between fields. If you specify AUTOTAB=YES for a selection field, the cursor automatically moves to the next field that is capable of input. If no other field capable of input exists on the panel, the cursor returns to the selection field.
- DEPTH** This attribute specifies that the selection list is to be formatted as a scrollable area. A list formatted into multiple columns (see CHOICECOLS below) is formatted as multiple scrollable areas.

<b>EXTEND</b>	This attribute is valid only when DEPTH has been specified and specifies that the scrollable area is to be expanded at run-time to the size of the logical screen.
<b>TRAIL</b>	This attribute is used with menu-choice selections to specify the name of one or more variables that applications use to obtain TRAIL information created by option menu selection processing.
<b>CHOICECOLS</b>	This attribute is used to specify the number of columns to create for the selection list. When multiple columns are requested, the number of choices placed in each column is obtained from the CHOICEDEPTH attribute.
<b>CHOICEDEPTH</b>	This attribute specifies the number of choices to be formatted into each column of choices. If more choice entries are specified than can be formatted in the available number of columns specified by the CHOICECOLS attribute, the remaining choice entries are placed in the rightmost (or only) available column for the current SELFLD tag.
<b>CWIDTHS</b>	This attribute specifies the number of bytes to be allocated for each column of CHOICE entries. The 'w1 w2...wn' notation provides the number of bytes for each column. You may use an asterisk or a number combined with an asterisk to specify a proportional allocation of column space.
<b>PAD</b>	This attribute specifies the pad character for initializing the field. You can define this attribute as a variable name preceded by a "%".
<b>PADC</b>	This attribute specifies the conditional padding character to be used for initializing the field. You can define this attribute as a variable name preceded by a "%".
<b>OUTLINE</b>	This attribute provides for displaying lines around the field on a DBCS terminal. You can define this attribute as a variable name preceded by a "%".
<b>SELMSG</b>	This attribute specifies the message that is displayed when an invalid single-choice entry is selected.
<b>SELMSGU</b>	This attribute specifies the message that is displayed when an unavailable single-choice entry is selected.
<b>INIT</b>	This attribute controls the single-choice and multiple-choice selection field variables initialization in the panel )INIT section.
<b>VERIFY</b>	This attribute controls the single-choice verification and menu-choice, model-choice, or tutor-choice selection logic generation in the panel )PROC section.
<b>REFRESH</b>	This attribute controls the creation of the REFRESH statement in the )REINIT section for multi-choice selection variables.
<b>SELFMT</b>	This attribute controls the placement of the choice selection character(s) within the width specified by ENTWIDTH.
<b>CHKBOX</b>	This attribute controls the display of multiple-choice fields as check boxes when operating in GUI mode.
<b>ZGUI</b>	This attribute controls the creation of the VGET (ZGUI) statement

created as part of the )INIT section for multiple-choice selection definitions using the "&multipmt" built-in ENTITY.

<b>CSRGRP</b>	This attribute, in combination with CHKBOX=YES, provides a cursor group identification for multi-choice selections.
<b>TSIZE</b>	This attribute provides the number of bytes to indent multiple lines of CHOICE text.
<b>LISTTYPE</b>	This attribute controls the display of single-choice selection lists when operating in GUI mode.
<b>LISTREF</b>	This attribute provides the name of the )LIST section for list boxes, drop-down lists, and combination boxes.
<b>LISTDEPTH</b>	This attribute specifies the display depth for list boxes, drop-down lists, and combination boxes.
<b>DBALIGN</b>	This attribute, used for DBCS fields when PMTLOC=ABOVE, specifies alignment of the prompt text with the selection input field.
<b>NOSEL</b>	This attribute provides a value to be placed in the CHECKVAR variable (specified by the CHOICE tag), when no selection is made from a single-choice selection list.
<b>SELDEFAULT</b>	This attribute specifies a default choice selection for a single-choice selection list.
<b>PMTSKIP</b>	This attribute, used during horizontal field formatting, specifies that the cursor should move past the prompt text to the input field.
<b>FLDTYPE</b>	This attribute specifies whether CUA or traditional ISPF attribute definitions are used.
<b>COLOR</b>	When FLDTYPE=ISPF, this attribute specifies the color of the field.
<b>INTENS</b>	When FLDTYPE=ISPF, this attribute specifies the intensity of the field.
<b>HILITE</b>	When FLDTYPE=ISPF, this attribute specifies the highlighting of the field.
<b>SELCHECK</b>	This attribute is used with menu-choice selection to specify that panel logic be included in selection processing to check for selection choices that are not valid.

---

## Data Columns

The DTACOL (data column) tag can be used to define values for data fields and selection fields that are coded within the data column. If you have a group of data fields and selection fields on the same application panel, the DTACOL tag is a convenient short-cut for ensuring alignment of the fields.

The DTACOL tag has the following attributes:

<b>PMTWIDTH</b>	Applies to data fields and selection fields
<b>ENTWIDTH</b>	Applies to data fields only
<b>DESWIDTH</b>	Applies to data fields only
<b>SELWIDTH</b>	Applies to selection fields only

<b>FLDSPACE</b>	Applies to data fields only
<b>PAD</b>	Applies to data fields only
<b>PADC</b>	Applies to data fields only
<b>OUTLINE</b>	Applies to data fields only
<b>PMTFMT</b>	Applies to data fields only
<b>AUTOTAB</b>	Applies to data fields only
<b>ATTRCHANGE</b>	Applies to data fields only
<b>PMTLOC</b>	Applies to data fields only
<b>DBALIGN</b>	Applies to data fields only
<b>VARCLASS</b>	Applies to data fields only
<b>REQUIRED</b>	Applies to data fields only
<b>CAPS</b>	Applies to data fields only

These attributes serve the same purposes in DTACOL definitions as they do in CHOFLD, DTAFLD, and SELFLD definitions. The only difference is that when you use them with a DTACOL tag, they define those values for all of the data fields and selection fields coded between the DTACOL start and end tags.

The following markup uses a data column to define a prompt width, entry width, and description width for the data fields and the selection field coded within the data column. Because we want to limit the entry width of the **State** and **Zip code** fields, we defined ENTWIDTH values in the DTAFLD definitions for these fields that override the DTACOL ENTWIDTH value.

```
<!doctype dm system>

<varclass name=sampcls type =' char 30' >
<varclass name=statcls type =' char 2' >
<varclass name=zipcls type =' char 5' >
<varclass name=char1cls type =' char 1' >

<varlist>
  <vardcl name=name varclass=sampcls>
  <vardcl name=addr varclass=sampcls>
  <vardcl name=city varclass=sampcls>
  <vardcl name=stat varclass=statcls>
  <vardcl name=day varclass=char1cls>
  <vardcl name=zipc varclass=zipcls>
</varlist>

<panel name=dcolxmp>Schedule Appointments
<topinst>Enter your name and address and
choose the most convenient day for your appointment.
<area>
  <dtacol pmtwidth=12 entwidth=30 deswidth=29 selwidth=30>
    <dtafld datavar=name>Name
      <dtafldd>Last, First, M.I.
    <dtafld datavar=addr>Address
      <dtafldd>If it applies, include apartment number
    <dtafld datavar=city>City
    <dtafld datavar=stat entwidth=2>State
      <dtafldd>Use 2-character abbreviation
    <dtafld datavar=zipc entwidth=5>Zip code
    <divider type=solid gutter=3>
    <selfld name=day pmtloc=before>Weekdays
      <choice>Monday
```



underscore-filled when it is initially displayed, unless the data is right-justified, and the user can enter data into any of the rows in the input column.

**OUT** Defines an output-only list column. When the panel is initially displayed, output-only columns display the value of the ISPF table variable associated with the list column. The user cannot interact with an output-only list column.

**BOTH** Defines an input/output list column. Input/output list columns display the value of the ISPF table variable associated with the list column when the panel is initially displayed, as well as allowing the user to enter data into any of the rows in the column. BOTH is the default value for the USAGE attribute.

The data that is associated with each list column is specified on the DATAVAR attribute of the LSTCOL tag. Like all variables used on the panel, the data variable should be declared using the VARDCL tag.

The conversion utility builds a model section into the converted application panel. The model section begins with a )MODEL header statement, which includes the variables named by the DATAVAR attributes of each of the LSTCOL tags defined within the LSTFLD.

Application panels defined using the LSTFLD tag must be displayed using the ISPF TBDISPL service. You can specify the optional ROWS=SCAN attribute on the LSTFLD tag to indicate that only those rows meeting the criteria established by a previous TBSARG service are to be displayed.

You can define a column heading for any of the list columns in the list field by specifying the column heading text as the tag text on the LSTCOL tag. You can specify the optional DIV attribute on the LSTFLD tag to create a divider line between the display of table rows. The column headings do not scroll when the list field is scrolled.

A scroll amount field can be placed at the right end of the command line by specifying the SCROLLVAR attribute on the LSTFLD tag. Field level help for the SCROLLVAR field is specified using the SCRHELP attribute. The scroll amount field is displayed in uppercase characters when the SCRCAPS=ON attribute is specified.

This panel shows a list field with six columns. The first column is output-only, and the remaining columns are input/output.

Scheduling Account Visits					ROW 1 to 9 of 9
Enter the account name in the appropriate time slot.					
	Monday	Tuesday	Wednesday	Thursday	Friday
08:00 - 08:59	_____	_____	_____	_____	_____
09:00 - 09:59	_____	_____	_____	_____	_____
10:00 - 10:59	_____	Simmons	_____	_____	_____
11:00 - 11:59	_____	_____	_____	_____	_____
12:00 - 12:59	_____	_____	Dougl ass	Campbel l	_____
01:00 - 01:59	_____	_____	_____	_____	_____
02:00 - 02:59	_____	_____	_____	_____	_____
03:00 - 03:59	_____	_____	_____	_____	_____
04:00 - 04:59	_____	_____	_____	_____	_____
***** Bottom of data *****					
Command ==>			Scroll ==> CSR		
F1=Hel p	F2=Spl it	F3=Exi t	F9=Swap	F12=Cancel	

Figure 42. List Field

Here is the markup we used to create the panel:

```
<!doctype dm system>

<varclass name=timecls type=' char 13' >
<varclass name=vc1 type =' char 9' >

<varlist>
  <vardcl name=timecol varclass=timecls>
  <vardcl name=moncol varclass=vc1>
  <vardcl name=tuecol varclass=vc1>
  <vardcl name=wedcol varclass=vc1>
  <vardcl name=thrcol varclass=vc1>
  <vardcl name=fri col varclass=vc1>
</varlist>

<panel name=lstfld2>Scheduling Account Visits
  <topinst>Enter the account name in the appropriate time slot.
  <area>
    <lstfld scrollvar=scr1amt scrvhel p=scrhelp>
      <lstcol datavar=timecol usage=out colwidth=13>
      <lstcol datavar=moncol colwidth=9>Monday
      <lstcol datavar=tuecol colwidth=9>Tuesday
      <lstcol datavar=wedcol colwidth=9>Wednesday
      <lstcol datavar=thrcol colwidth=9>Thursday
      <lstcol datavar=fri col colwidth=9>Friday
    </LSTFLD>
  </area>
<cmdarea>
</panel >
```

## List Group Headings

You can define additional headings for the columns in a list field using the LSTGRP (list group) tag and its matching end tag. You can define a list group for a single list column or for multiple list columns. You nest the list columns you want to provide additional heading text for within the LSTGRP definition.

At least one field from the first line of the model set must be included within a LSTGRP definition.

The HEADLINE attribute of the LSTGRP tag allows you to place dashes in the list group heading. This is handy for list groups that span across several list columns. Specify HEADLINE=YES to produce a dashed list group heading.

The ALIGN attribute of the LSTGRP tag allows you to control the format position of the list group heading. The default value is CENTER. The heading can be left- or right-justified by specifying the values START or END, respectively.

For example, we added a LSTGRP definition to the list field shown earlier.

Scheduling Account Visits					ROW 1 to 9 of 9
Enter the account name in the appropriate time slot.					
	----- Appointments -----				
	Monday	Tuesday	Wednesday	Thursday	Friday
08:00 - 08:59	_____	_____	_____	_____	_____
09:00 - 09:59	_____	_____	_____	_____	_____
10:00 - 10:59	_____	Simmons	_____	_____	_____
11:00 - 11:59	_____	_____	_____	_____	_____
12:00 - 12:59	_____	_____	Douglas	Campbell	_____
01:00 - 01:59	_____	_____	_____	_____	_____
02:00 - 02:59	_____	_____	_____	_____	_____
03:00 - 03:59	_____	_____	_____	_____	_____
04:00 - 04:59	_____	_____	_____	_____	_____
***** Bottom of data *****					
Command ==>			Scroll ==> CSR		
F1=Help	F2=Split	F3=Exit	F9=Swap	F12=Cancel	

Figure 43. List Group

The text of the list group, **Appointments** is centered within the dashes. Here is how we coded the list group:

```
<!doctype dm system>

<varclass name=timecls type='char 13'>
<varclass name=vc1 type='char 9'>

<varlist>
  <vardcl name=timecol varclass=timecls>
  <vardcl name=moncol varclass=vc1>
  <vardcl name=tuecol varclass=vc1>
  <vardcl name=wedcol varclass=vc1>
  <vardcl name=thrcol varclass=vc1>
  <vardcl name=fri col varclass=vc1>
</varlist>

<panel name=lstgrp2>Scheduling Account Visits
  <topinst>Enter the account name in the appropriate time slot.
  <area>
    <lstfld scrollvar=scr1amt scrvhel p=scrhel p>
      <lstcol datavar=timecol usage=out colwidth=13>
        <lstgrp headline=yes>Appointments
          <lstcol datavar=moncol colwidth=9>Monday
```

```

        <lstcol datavar=tuecol colwidth=9>Tuesday
        <lstcol datavar=wedcol colwidth=9>Wednesday
        <lstcol datavar=thrcol colwidth=9>Thursday
        <lstcol datavar=fri col colwidth=9>Friday
    </lstgrp>
</lstfld>
</area>
<cmdarea>
</panel>

```

## List Column Width

You can use the COLWIDTH attribute of the LSTCOL tag to determine the data width to be used by the column. If you do not specify this attribute, the data width and column formatting width are determined by the actual length of the *column-heading*. If the width of the *column-heading* text is greater than the COLWIDTH, it is used as the column formatting width.

The minimum width value is 1 and the maximum is the remaining available panel (or region) width. If the *column-heading* and the COLWIDTH attribute are omitted, the data width and column formatting width are determined by the TYPE value of the associated VARCLASS. If a VARCLASS TYPE value is not available, the size of the column variable name (specified by the DATAVAR attribute) determines the width.

You should code the COLWIDTH attribute with a value equal to the length of the table data variable.

## Other List Column Attributes

There are several other attributes that can be used in the LSTCOL tag. Many of these attributes are the same as attributes on the DTAFLD tag. The following list describes these LSTCOL attributes and how they are used:

**ALIGN** This attribute aligns the variable data within the list column. The default value for ALIGN is **start**, which aligns the data from the left side of the column. You can also center the data within the column with the **center** value, or align the data to the right side of the column with the **end** value. The attribute value **end** is useful for right-aligning numbers within an output-only column, because numbers are typically right-aligned.

**ATTRCHANGE** This attribute specifies that, if required, an additional )ATTR section entry (which can apply to multiple fields) be created instead of a unique ".ATTR" override entry for the current field.

**AUTOTAB** This attribute specifies automatic tabbing. If you assign a value of YES to this attribute, the cursor automatically moves to the next field that is capable of user input when the user enters the last character in the current list column. The default value for AUTOTAB is NO. This attribute is only valid for list columns defined as input-only or as input/output.

**CAPS** This attribute specifies whether the data column is displayed in uppercase characters.

**CLEAR** This attribute specifies that the column is a table extension variable, which should be cleared before the row is displayed. Column names with the CLEAR attribute are identified by the CLEAR keyword on the )MODEL statement.

<b>COLOR</b>	When COLTYPE=ISPF, this attribute specifies the color for the column.
<b>COLSPACE</b>	The COLSPACE attribute specifies the total number of bytes for the column width, including the leading and trailing attributes, and the trailing blank for input fields. The use of the COLSPACE attribute causes column heading text longer than the COLSPACE value to be flowed into multiple lines.
<b>COLTYPE</b>	The COLTYPE attribute specifies the attribute type to be used for the column.
<b>CSRGRP</b>	This attribute, in combination with the PAS attribute, specifies a cursor group for GUI mode operation.
<b>DISPLAY</b>	This attribute specifies whether the data column is visible when the panel is displayed.
<b>FORMAT</b>	This attribute specifies how the data column and its column heading are formatted. If you do not specify this attribute, or if you specify the attribute value START, then the column formats as in ISPF Version 3.1 and ISPF Version 3.2.
<b>HELP</b>	This attribute specifies the help panel name to display when the user requests help on the list column.
<b>HILITE</b>	When COLTYPE=ISPF, this attribute specifies the highlighting for the column.
<b>INTENS</b>	When COLTYPE=ISPF, this attribute specifies the intensity for the column.
<b>LINE</b>	This attribute specifies the model line that contains the variable. You can specify lines 1–8.
<b>MSG</b>	This attribute identifies the message that should be displayed when the user does not enter any data into an input-required list column. If you do not specify this attribute, ISPF displays a default message. This attribute is valid only if REQUIRED=YES. Chapter 7, “Messages,” on page 155 tells you how to define application messages.
<b>NOENDATTR</b>	This attribute specifies that no ending attribute character will be placed after the data column. NOENDATTR is ignored for the last data column on each model line. See “LSTCOL (List Column)” on page 366 for more information about the NOENDATTR attribute.
<b>OUTLINE</b>	This attribute provides for displaying lines around the field on a DBCS terminal. You can define this attribute as a variable name preceded by a “%”. See “LSTCOL (List Column)” on page 366 for more information about the OUTLINE attribute.
<b>PAD</b>	This attribute specifies the pad character for initializing the field. You can define this attribute as a variable name preceded by a “%”. See “LSTCOL (List Column)” on page 366 for more information about the PAD attribute.
<b>PADC</b>	This attribute specifies the conditional padding character to be used for initializing the field. You can define this attribute as a variable name preceded by a “%”. See “LSTCOL (List Column)” on page 366 for more information about the PADC attribute.

<b>PAS</b>	This attribute is used to control the generation of the point-and-shoot indicator for table display panels. You can define this attribute as a variable name preceded by a "%".
<b>POSITION</b>	This attribute allows you to specify the starting position of the data column. The POSITION value must be greater than the end of the last formatted data column for that model line and less than the right panel margin. Column formatting for adding the data column and text takes place after the starting position has been established. See "LSTCOL (List Column)" on page 366 for more information.
<b>REQUIRED</b>	This attribute indicates if this column is required to have input for any modified row. For input-required columns (REQUIRED=YES), ISPF will not validate the panel unless the user has entered data into that column. If you do not specify this attribute, input is not required on the list column. This attribute is only valid for list columns defined as input-only or as input/output.
<b>TEXT</b>	This attribute specifies a short description of the data column. Text can be placed before or after the data column. See "LSTCOL (List Column)" on page 366 for more information.
<b>TEXTLOC</b>	This attribute specifies the location of the TEXT relative to the data column. Text can be placed on either side of the data column. See "LSTCOL (List Column)" on page 366 for more information.
<b>TEXTFMT</b>	This attribute specifies the format of the text within the length of the text area. The text can be left-justified, centered, or right-justified. See "LSTCOL (List Column)" on page 366 for more information.
<b>TEXTLEN</b>	This attribute specifies the amount of space to reserve for formatting the descriptive text. This helps you line up text on different model lines, and if the space reserved is longer than the descriptive text, TEXTLEN permits formatting within the reserved space with the TEXTFMT attribute. See "LSTCOL (List Column)" on page 366 for more information.
<b>TEXTSKIP</b>	This attribute specifies the cursor should move past the text to the next input field.
<b>VARCLASS</b>	This attribute allows you to override the variable class that is specified on the variable declaration (VARDCL) for the list column's data variable (DATAVAR). See Chapter 4, "Variables and Variable Classes," on page 57 for a description of variables and variable classes.

## Defining Group Headings

The Group Header (GRPHDR) tag defines a group heading in the panel )BODY section.

The FORMAT attribute is used to control the type of text formatting. You can choose formatting similar to the LINES tag or the P tag. For example, if FORMAT=NONE, the text formats as if you used a LINES tag. However, if FORMAT=START, CENTER, or END, the text flows to multiple lines and is formatted at the right, center or left part of the space reserved for the group heading.

The following list provides a short description of the other available attributes:

<b>WIDTH</b>	This attribute specifies the number of columns reserved for the group heading. The default value is the remaining panel width.
<b>FMTWIDTH</b>	This attribute specifies the number of columns (of the WIDTH value) to use for formatting the group heading. The default is the WIDTH value. By specifying a FMTWIDTH that is less than the WIDTH value, the group heading text can be formatted on multiple lines.
<b>INDENT</b>	This attribute specifies the number of bytes that the group heading is to be indented.
<b>HEADLINE</b>	This attribute specifies whether dashes are added to span the width of the group heading not occupied by text.
<b>DIV</b>	This attribute specifies the type of divider line to be placed before and after the group heading text.
<b>DIVLOC</b>	This attribute specifies whether the divider is to be added before the group heading, after the group heading, or both before and after the group heading.
<b>COMPACT</b>	This attribute causes the group heading to format without a blank line before the group heading.
<b>STRIP</b>	This attribute causes leading and trailing blanks to be removed from the group heading text.

---

## Defining Point-and-Shoot Fields

The Point-and-Shoot (PS) tag is used to identify a portion of panel )BODY section text to be used for point-and-shoot selection. When a point-and-shoot selection is made, a variable is set to a specified value before normal )PROC section processing. The PS tag attributes identify the variable name and the value associated with each point-and-shoot selection.

The PS tag requires a matching end tag to indicate the end of the point-and-shoot text.

Refer to the *ISPF Dialog Developer's Guide and Reference* for more information about point-and-shoot selection.

---

## Defining Scrollable Fields

A scrollable field can be used when the size of the field defined on the panel is smaller than the amount of data to be displayed. With the cursor placed in the field, the LEFT and RIGHT commands can be used to scroll the data displayed. In addition, the EXPAND command can be used to display the data in a popup window.

With DTL, fields that can be made scrollable are defined using the DTAFLD or LSTCOL tags. A field is made scrollable by nesting a SCRFLD tag in the DTAFLD or LSTCOL tag. The SCRFLD tag has the following attributes that allow you to specify dialog variables to contain scroll indicators. The conversion utility will generate output fields on the panel to allow the scroll indicators to be displayed along with the scrollable field:

<b>INDVAR</b>	A 2-byte left and right scroll indicator that shows whether left and right scrolling can be performed.
---------------	--

<b>LINDVAR</b>	A 1-byte left scroll indicator that shows whether left scrolling can be performed.
<b>RINDVAR</b>	A 1-byte right scroll indicator that shows whether right scrolling can be performed.
<b>SINDVAR</b>	A separator scroll indicator that shows the length of the scrollable field and whether left and right scrolling can be performed.
<b>LCOLIND</b>	A left column position indicator that shows the position of the character currently displayed in the leftmost byte of the scrollable field.
<b>RCOLIND</b>	A right column position indicator that shows the position of the character currently displayed in the rightmost byte of the scrollable field.
<b>SCALE</b>	A scale indicator showing the positions of the columns currently displayed in the scrollable field.

The following is the markup used for the Data Columns example (see page 100), modified to display the Name and Address fields as scrollable fields. The Name field is displayed with a separator scroll indicator and the Address field is displayed with a scale indicator. The conversion utility automatically generates the separator scroll indicator below the Name field and the scale indicator below the Address field.

```
<!doctype dm system>
<varclass name=sampcls type =' char 30' >
<varclass name=statcls type =' char 2' >
<varclass name=zipcls type =' char 5' >
<varclass name=char1cls type =' char 1' >

<varlist>
  <vardcl name=name varclass=sampcls>
  <vardcl name=addr varclass=sampcls>
  <vardcl name=city varclass=sampcls>
  <vardcl name=stat varclass=statcls>
  <vardcl name=day varclass=char1cls>
  <vardcl name=zipc varclass=zipcls>
</varlist>

<panel name=scr1xmp depth=24>Schedule Appointments
  <topinst>Enter your name and address and
  choose the most convenient day for your appointment.
  <area>
    <dtacol pmtwidth=12 entwidth=30 deswidth=29 selwidth=30>
      <dtafld datavar=name>Name
        <dtafldd>Last, First, M.I.
          <scrfld displen=50 sindvar=namesi >
      <dtafld datavar=addr>Address
        <scrfld displen=80 scale=addrsi >
      <dtafld datavar=city>City
      <dtafld datavar=stat entwidth=2>State
        <dtafldd>Use 2-character abbreviation
      <dtafld datavar=zipc entwidth=5>Zip code
      <divider type=solid gutter=3>
      <selfld name=day pmtloc=before>Weekdays
        <choice>Monday
        <choice>Tuesday
        <choice>Wednesday
        <choice>Thursday
        <choice>Friday
```

```

        </sel fld>
    </dtacol >
</area>
</panel >

```

This is how the panel displays:

Schedule Appointments

Enter your name and address and choose the most convenient day for your appointment.

Name . . . . Veryveryverylongsurname, Alexa Last, First, M.I.  
 ----->

Address . . Apartment 52b, 446 Verylongstr  
 -----1-----2-----3

City . . . . \_\_\_\_\_

State . . . .    Use 2-character abbreviation

Zip code . . \_\_\_\_\_

-----

Weekdays . .    1. Monday  
 2. Tuesday  
 3. Wednesday  
 4. Thursday  
 5. Friday

Command ==>>> \_\_\_\_\_ Scroll ==>> CSR

F1=Help    F2=Split    F3=Exit    F9=Swap    F12=Cancel

Figure 44. Scrollable Field

When the scrollable field is defined using the LSTCOL tag the conversion utility automatically generates, along with the column heading, output fields for any scroll indicators you specify. The following is the markup used for the List Group Headings example (see page 104), modified to display the Appointment data in scrollable fields. This would allow more information than just the account name to be stored and displayed in the Appointment data. A scale indicator is displayed with the heading for each day's column.

```

<!doctype dm system>

<varclass name=timecls type=' char 13' >
<varclass name=vc1     type =' char 9' >

<varlist>
  <vardcl name=timecol varclass=timecls>
  <vardcl name=moncol  varclass=vc1>
  <vardcl name=tuecol  varclass=vc1>
  <vardcl name=wedcol  varclass=vc1>
  <vardcl name=thrcol  varclass=vc1>
  <vardcl name=fri     col varclass=vc1>
</varlist>

<panel name=scrxmp2>Scheduling Account Visits
  <topinst>Enter the appointment details in the appropriate time slot.
  <area>
    <lstfld scroll var=scr1amt scrvhel p=scrhel p>
      <lstcol datavar=timecol usage=out colwidth=13>
        <lstgrp headl ine=yes>Appointments
          <lstcol datavar=moncol colwidth=9>Monday

```

```

        <scrfl d di spl en=30 scal e=monscl >
        <l stcol datavar=tuecol colwidth=9>Tuesday
        <scrfl d di spl en=30 scal e=tuescl >
        <l stcol datavar=wedcol colwidth=9>Wednesday
        <scrfl d di spl en=30 scal e=wedscl >
        <l stcol datavar=thrcol colwidth=9>Thursday
        <scrfl d di spl en=30 scal e=thrscl >
        <l stcol datavar=fri col colwidth=9>Friday
        <scrfl d di spl en=30 scal e=fri scl >
    </l stgrp>
</l stfld>
</area>
<cmdarea>
</panel >

```

This is how the panel displays:

Scheduling Account Visits ROW 1 to 9 of 9

Enter the account name in the appropriate time slot.

	----- Monday -----	----- Tuesday -----	----- Wednesday -----	----- Thursday -----	----- Friday -----
	-----+-----	-----+-----	-----+-----	-----+-----	-----+-----
08:00 - 08:59	_____	_____	_____	_____	_____
09:00 - 09:59	_____	_____	_____	_____	_____
10:00 - 10:59	_____	Hart - Pl	_____	_____	_____
11:00 - 11:59	_____	_____	_____	_____	_____
12:00 - 12:59	_____	_____	Wi fe - lu	_____	_____
01:00 - 01:59	_____	XYZ - rev	_____	ABC - upd	_____
02:00 - 02:59	_____	_____	_____	_____	_____
03:00 - 03:59	_____	_____	_____	_____	_____
04:00 - 04:59	_____	_____	_____	_____	Rod - ten
***** Bottom of data *****					

Command ==> Scroll ==> CSR

F1=Hel p    F2=Spl it    F3=Exi t    F9=Swap    F12=Cancel

Figure 45. Scrollable Field Within a List Column



---

## Chapter 6. Information Regions and Help Panels

Some of the information displayed on panels is *static*, or fixed text that the user does not interact with directly. This includes text such as top instructions and bottom instructions, prompt text, and data-field description text. DTL provides you with another method of defining static text for application panels using *information regions*.

Defining an information region on a panel allows you more flexibility for defining static text on a panel. The tags you use to define the text of information regions are much more versatile than the tags you use to define other types of static text, which means you can be more creative in the text you define.

In addition to using information regions on application panels, you must use them to define the text on help panels you define for your application. In this chapter, we tell you how to define information regions on application panels, and how to define help panels for your applications.

---

### Defining an Information Region

Use the INFO tag and its required end tag to define an information region on a panel. You can code an information region within an AREA, HELP, PANEL, or REGION definition.

Here is an example of an INFO definition:

```
<panel name=infopan width=42 depth=16>Information  
  
  <area>  
    <info>  
      </info>  
  </area>  
</panel >
```

The INFO tag has an optional WIDTH attribute that defines the width of the information region. If the value you assign the INFO WIDTH attribute is greater than the WIDTH available in the panel, the conversion utility will reset the value to the available width.

**Note:** You should code the WIDTH attribute if the information region is part of an application panel definition that uses horizontal region capability.

The INFO tag only defines an information region. It does not define the text of the information region. DTL provides you with a set of tags that define the text in information regions. These tags are:

- ATTENTION
- CAUTION
- DL (definition list)
- FIG (figure)
- Hn (heading)
- HP (highlighted phrase)
- LINES
- NOTE
- NOTEL (note list)
- NT (note)

- OL (ordered list)
- P (paragraph)
- PARML (parameter list)
- RP (reference phrase)
- PS (point-and-shoot)
- SL (simple list)
- UL (unordered list)
- WARNING
- XMP (example).

With the exception of HP, PS, and RP, these tags can be coded *only* within an INFO definition. The next section explains how to use each of these tags and some other tags that complement these tags within information regions.

---

## Defining Basic Text

### Paragraphs

The tag you use most often in information regions is the P (paragraph) tag. Use the P tag to arrange text as you would arrange a paragraph in your usual writing (to join one or more sentences related by their subject matter into a single block of text).

When the paragraph text formats for display, the text starts at the current margin and the words automatically wrap to fit within the margin. In addition, the conversion utility normally inserts a blank line before each paragraph.

The P tag has an optional attribute, COMPACT, which causes the blank line before the paragraph to be omitted. The P tag does not require a matching end tag.

We'll illustrate the use of the P tag with this example :

```
<!doctype dm system>
<panel name=infopan1 width=42>Information
  <area>
    <info width=40>
      <p>This is a paragraph.
      This sentence is also part of the paragraph.
    </info>
  </area>
</panel>
```

Notice that we coded the second sentence of the paragraph on a different line. It doesn't matter, because the conversion utility treats it as part of the same paragraph and formats it accordingly. That is, two blanks are automatically inserted between the sentences. Here is how the paragraph looks:




Figure 46. Paragraph

As you can see, the text of the paragraph is left-justified on the panel and the words automatically wrap to fit within the defined dimensions of the information region.

We'll add another paragraph to the panel to illustrate how two paragraphs format:

```
<!doctype dm system>
<panel name=infofan2 width=42>Information
  <area>
    <info width=40>
      <p>This is a paragraph.
      This sentence is also part of the paragraph.
      <p>Here is another paragraph.
      Paragraphs are useful for providing
      information on panels.
    </info>
  </area>
</panel>
```

Figure 47 on page 116 shows the result:




Figure 47. Multiple Paragraphs

In addition to the placement and wrapping of the text, the compiler separated the paragraphs with a blank line.

## Headings

The Hn (heading) tag allows you to place headings in an information region. You use these headings to define topics and subtopics of information. You can define four levels of headings:

- H1**                      Centers text in the information region. Use this heading level to identify a main topic of information.
- H2, H3, H4**            Formats text against the left margin of the information region. Use one of these heading levels to identify subtopics of information.

You must code headings sequentially. The conversion utility adds a blank line to the information region before and after the formatted heading text. The heading tags have no attributes associated with them, and they don't require an end tag.

The following markup contains an information region using two heading levels and paragraphs following each one.

```
<!doctype dm system>
<panel name=info pan3 width=42>Information
  <area>
    <info width=40>
      <h1>A Main Topic
      <p>Notice how the heading is in the
        center of the information region?
      <h2>A Subtopic
      <p>This heading is left-justified.
      <h2>Another Subtopic
      <p>Here's another level-two heading.
    </info>
  </area>
</panel>
```

Here is the formatted result:




Figure 48. Headings (H1-H2)

## Lines

Occasionally, you'll want to present text that you don't want formatted by the compiler, or that you want to show "as is". You can use the LINES (lines) tag and its required end tag to do this. All text coded within a LINES definition is treated as unformatted text, and you can position the text however you like on each line. If the text line is too long to fit in the available width, the conversion utility truncates the text and issues a warning message.

The LINES tag requires an end tag.

There are many ways to use a LINES definition. Here we use it for a quotation:

```
<!doctype dm system>
<panel name=specact width=48>Special Activities
  <area>
    <info width=46>
      <lines>
        Between the dark and daylight,
        When the night is beginning to lower,
        Comes a pause in the days' occupations,
        That's known as the children's hour.
                               -Longfellow
      </lines>
      <p>Every Tuesday evening at seven
      o'clock, we present the Children's Hour,
      a one-hour recital of selected children's
      stories in our children's section.
    </info>
  </area>
</panel>
```

And our quotation appears just the way we marked it up:



Figure 49. LINES

## Examples

The XMP (example) tag is similar to the LINES tag, in that it allows you to code unformatted text. However, the text of an XMP definition is indented two spaces from the current margin, as opposed to the text of a LINES definition, which is not indented from the current margin.

Like a LINES definition, you should avoid coding lines of text in an XMP definition that exceed the available formatting width of the information region. If the text exceeds the defined width, it is truncated.

The XMP tag requires a matching end tag.

Here's the formatted result of an example using the XMP tag:




Figure 50. XMP

The markup for the previous panel looks like this:

```
<!doctype dm system>
<panel name=toy1 width=57>Order a Toy
<area>
<info width=55>
<p>Type the catalog number of the toy you want to order
and press Enter.
The number must be a 6-digit number.
<p>For example:
<xmp>
Catalog Number. . . 581678
</xmp>
</info>
</area>
</panel>
```

## Figures

The FIG (figure) tag is yet another way you can code text that isn't formatted. It works just like the LINES tag, except you can add a ruled border above and below the figure to separate it from the rest of the panel. You can also provide a caption for the figure using the FIGCAP tag.

Like the LINES and XMP tags, the FIG tag requires an end tag.

To define the ruled borders for the figure, use the FRAME attribute of the FIG start tag. The FRAME attribute has two values, RULE, which is the default, and NONE. Because RULE is the default value, you don't need to specify this attribute if you want ruled lines above and below the figure. To create a figure without rules, specify NONE as the FRAME value.

The figure in this panel formats with a ruled border:

```
<!doctype dm system>
<panel name=toy2 width=57>Order a Toy
<area>
<info width=55>
<p>Type the catalog number of
the toy you want to order and
```

```

press Enter.
The number must be a 6-digit number.
<p>For example:
<xmp>
Catalog Number. . . 581678
</xmp>
<p>A description of the toy will appear.
<fig>
        ZOOM-A-GO DAREDEVIL SET

        Your kids will have hours of excitement
        playing with this full set of action toys.
        Requires 80 "AA" batteries. Not included.
</fig>
</info>
</area>
</panel>

```

Here is the formatted panel:




Figure 51. Figure with Rules

If we wanted the figure to appear without a ruled border, we would have specified `FRAME=NONE` for the `FIG` tag.

The `FIG` tag also has an optional `WIDTH` attribute that allows you to specify how the figure is aligned in the information region. The valid values for `WIDTH` are `PAGE` and `COL`. `PAGE`, which is the default value, aligns the figure along the left margin of the information region. `COL` indicates that the figure is aligned along the current left margin; that is, the current margin defined by the tag the figure is nested in. This is useful, for example, for aligning figures within list items.

### Figure Captions (`FIGCAP`) Tag

To add a caption to the figure in Figure 51, use a `FIGCAP` tag and caption text within the figure definition, like this:

```

<!doctype dm system>
<panel name=toy3 width=57>Order a Toy
<area>
<info width=55>
<p>Type the catalog number of

```

```

the toy you want to order and
press Enter.
The number must be a 6-digit number.
<p>For example:
<xmp>
Catalog Number. . . 581678
</xmp>
<p>A description of the toy will appear.
<fig>
        ZOOM-A-GO DAREDEVIL SET

        Your kids will have hours of excitement
        playing with this full set of action toys.
        Requires 80 "AA" batteries. Not included.
<figcaption>Zoom-A-Go Daredevil Set
</figcaption>
</info>
</area>
</panel>

```

The figure caption appears just below the bottom figure rule:




Figure 52. Figure Caption

---

## Defining Lists

Sometimes you want to present information to the user that is not appropriate in paragraph form, such as list items, a sequence of items or actions, or definitions. For these situations (and many others), you can use the DTL list tags to format your text appropriately.

You can create these types of lists:

- |                        |  |
|------------------------|--|
| <b>Note lists</b>      | Format as numbered lists of notes under a header called <b>Notes</b> . |
| <b>Simple lists</b>    | Format as indented lists of items without any preceding identifiers.   |
| <b>Unordered lists</b> | Format as indented lists of items with each item                       |

preceded by a bullet (o), a hyphen (-), or dashes (--), depending on the level of nesting.

**Ordered lists**

Format as indented lists of items with each item preceded by a number or letter indicating its sequence in the list.

**Definition lists**

Format in two columns, with terms in one column and their matching descriptions in the other. You can also specify headings for each column in the list. (This list is a definition list.)

**Parameter lists**

Format in two columns. This list is specifically designed to identify and define parameter terms.

The list items in note lists, simple lists, unordered lists, and ordered lists are created with the list item (LI) tag. The LI tag does not require an end tag. It is implicitly ended by another LI tag, an LP tag, or the end tag of the list it is coded within.

## Note Lists

See “Alerting Users: Notes, Warnings, Cautions, and Attention” on page 136 for an example showing the use of note lists.

## Simple Lists

A simple list is the least complex type of list. Use a simple list when the information you are presenting does not follow a sequential pattern or when bullets are not required to discriminate one list item from another.

Figure 53 illustrates a simple list.




Figure 53. Simple List

This is the markup for the panel:

```
<!doctype dm system>  
<panel name=sl i stx1 width=44>Vir tues  
  <area>  
    <i nfo wi dth=42>
```

```

<p>Around the child bend all the
three sweet graces:
<sl>
  <li>Fai th
  <li>Hope
  <li>Chari ty
</sl>
</info>
</area>
</panel>

```

We used the SL tag and its matching end tag to define the simple list. We defined each of the list items by nesting the LI tags within the simple list definition.

As you can see, our simple list formatted with a blank line between each of the list items. For cases where you need to conserve space, you can use the COMPACT attribute to format the list without blank lines between the list items.

Code the COMPACT attribute within the SL start tag (before the tag close delimiter), like this:

```

<!doctype dm system>
<panel name=sl istx2 width=44>Vi rtues
  <area>
    <info width=42>
      <p>Around the child bend all the
      three sweet graces:
      <sl compact>
        <li>Fai th
        <li>Hope
        <li>Chari ty
      </sl>
    </info>
  </area>
</panel>

```

Now the simple list is compacted:




Figure 54. Compact Simple List

You can also nest simple lists within other lists. The list items format at different indentation levels, based on the level of nesting.

The indentation for the list item is based on the SPACE attribute of the LI tag and the enclosing list tag. When SPACE=NO (or the SPACE attribute is not present) the list item indentation is 4 spaces. When SPACE=YES, the indentation is 3 spaces. See Chapter 13, "Tag Reference," on page 205 for additional information about the LI, SL, OL, and UL tags.

## Unordered Lists

Unordered lists are similar to simple lists, except each list item is preceded by symbol that is dependent on the nesting level of the list. You don't have to supply the symbols—the conversion utility does that for you.

Use an unordered list if the list items are long and you don't want to imply any particular sequence in the list.

Here is an unordered list:



Figure 55. Unordered List

And Here is the markup for this unordered list:

```
<!doctype dm system>
<panel name=winshop width=48>Window Shopper
  <area>
    <info width=46>
      <p>With Window Shopper, you can order many wonderful things,
      such as:
      <ul>
        <li>Raindrops on roses
        <li>Whiskers on kittens
        <li>Bright copper kettles
        <li>Warm woolen mittens
        <li>Brown paper packages tied up with string
      </ul>
      <p>And many more of your favorite things!
    </info>
  </area>
</panel>
```

For our unordered list, we used the UL tag and its matching end tag. As you can see, even though we didn't code the bullet symbols (o) in the markup, they appear before each of the list items in the unordered list.

We could make this list compact like our simple list example because the COMPACT attribute is also valid for the UL tag. Likewise, we could use the SPACE attribute to control indentation of the list items for the UL tag.

You can also define levels of unordered lists; that is, you can nest unordered lists within other unordered lists. When you do this, the symbols preceding the list items in each level of the list vary, depending on the level of nesting. Specifically, the list items in the first (or only) level of unordered list are preceded by bullets (o), as shown in Figure 55 on page 124. If you nest another unordered list within an unordered list, the list items in that list are preceded by hyphen symbols (-). A third-level unordered list has dashes (--) preceding the list items. The nested tag text is aligned according to the level of nesting.

To show how this works, we'll create a panel with three levels of unordered lists.

```
<!doctype dm system>
<panel name=ulists width=42>Nested Unordered Lists
  <area>
    <info width=40>
      <ul>
        <li>First level, first item
        <li>First level, second item
          <ul>
            <li>Second level, first item
            <li>Second level, second item
              <ul>
                <li>Third level, only item
              </ul>
            </ul>
          </ul>
        <li>Back to the first level
      </ul>
    </info>
  </area>
</panel>
```

Here is how this panel looks:




Figure 56. *Nested Unordered Lists*

If you nest more than three levels of unordered lists, the sequence of bullets, hyphens, and dashes repeats. For example, a fourth level would be preceded by bullets, a fifth level by hyphens, and so on.

Remember, all lists must be explicitly ended with the appropriate list end tag.

## Ordered Lists

Ordered lists imply an outline sequence to the list items by preceding each of the list items with a number or character depending on the level of nesting.

Here is an ordered list:



Figure 57. *Ordered List*

You don't supply the numbers for the list items in your markup; they are generated automatically. This saves you time when you revise ordered lists, because you can insert, delete, or rearrange list items without renumbering them yourself.

Here is the markup we used for this list:

```
<!doctype dm system>
<panel name=winshop2 width=52>Window Shopper
  <area>
    <info width=50>
      <p>After you have placed your order with Window Shopper, you should...
      <ol>
        <li>Press the Enter key to leave the Order Panel.
        <li>Go to the receiving desk located at the front of the store.
        <li>Give the cashier the pink copy of your receipt.
        <li>Take your purchases home, and enjoy!
      </ol>
    </info>
  </area>
</panel>
```

Like other types of lists, you can nest ordered lists within other lists. And, like unordered lists, the levels of the lists you nest determine the characters that precede the list items.

Specifically, the conversion utility uses the following sequence when processing list items in nested ordered lists:

- First-level list items are preceded by sequential numbers followed by a period and 2 spaces <sup>5</sup>.
- Second-level list items are preceded by sequential lowercase alphabetic characters followed by a period and 2 spaces <sup>5</sup>.
- Third-level list items are preceded by sequential numbers followed by a close parentheses symbol and 2 spaces <sup>5</sup>.
- Fourth-level list items are preceded by sequential lowercase alphabetic characters followed by a close parentheses symbol and 2 spaces <sup>5</sup>.

**Note:** Each level beyond the first level indents 4<sup>5</sup> spaces.

The sequence of nesting is repeated for levels of nesting beyond the fourth level. For example, the list items in a fifth level of nesting are preceded by sequential numbers followed by a period.

To show you what this looks like, we'll nest three levels of ordered lists in this markup. We'll use the COMPACT attribute in the third level to conserve space.

```
<!doctype dm system>
<panel name=olists width=42>Nested Ordered Lists
  <area>
    <info width=40>
      <ol>
        <li>Step one (first level)
        <li>Step two (first level)
          <ol>
            <li>Step one (second level)
            <li>Step two (second level)
          <ol compact>
```

---

5. The default indentation for a list item is 4 spaces. When the SPACE=YES attribute is coded, the indentation is 3 spaces. See the LI and OL tag descriptions in Chapter 13, "Tag Reference," on page 205 for more information.

```

        <li>Step one (thi rd level)
        <li>Step two (thi rd level)
    </ol>
    <li>Step three (second level)
</ol>
<li>Step three (first level)
</ol>
</info>
</area>
</panel>

```

Here is how the DTL compiler formats this panel:




Figure 58. Nested Ordered Lists

## Definition Lists

Definition lists allow you to identify a list of words or phrases and their corresponding definitions. A simple definition list formats as a two-column list: the terms you define appear in the left column, and the definitions for the terms appear in the right column. Definition lists are slightly more complex than the previous lists we've discussed, because of the additional tags required to construct them.

The tags used to create a definition list are:

- DL** Begins a definition list. The required end tag ends the list.
- DT** Identifies the term being defined. The definition term is formatted in the left column of the list. It does not require an end tag.
- DD** Identifies the term description. Each definition description is formatted in the right column of the list, immediately opposite or below its associated term. It does not require an end tag.

You can also create headings for definition list columns. There are two additional tags that you can use to do this. They are:

- DTHD** Defines a header for the definition term column.
- DDHD** Defines a header for the definition description column.

Both of these tags are optional for creating definition lists. We'll show you how you can use them to enhance definition lists later on in this section.

Here is an example of a definition list:




Figure 59. Definition List

Here is the markup:

```
<!doctype dm system>
<panel name=deptcode width=42>Department Codes
  <area>
    <info width=40>
      <p>Use the following codes for each of the
        matching departments:
      <dl>
        <dt>AP
        <dd>Appliances
        <dt>AU
        <dd>Automotive
        <dt>GA
        <dd>Garden shop
        <dt>HB
        <dd>Health and beauty
        <dt>HO
        <dd>Home decor
        <dt>SP
        <dd>Sporting goods
      </dl>
    </info>
  </area>
</panel>
```

A definition list can contain multiple definition terms. The **TSIZE** attribute of the enclosing **DL** tag specifies the number of **DT** tags in a group and their respective widths. For example, **TSIZE='10 5'** specifies 2 definition term columns with sizes of 10 and 5 characters, respectively.

The **DL** tag has optional attributes:

**TSIZE** specifies the space allocated for the term column or columns

<b>BREAK</b>	indicates if the definition formats on the same line as its associated term
<b>COMPACT</b>	determines if there is a space between each set of terms and descriptions
<b>NOSKIP</b>	suppresses the blank line normally placed before the list
<b>INDENT</b>	controls the indentation from the current left margin
<b>FORMAT</b>	controls the location of the definition term within the TSIZE space
<b>DIVEND</b>	determines whether a divider character will be inserted following the DDHD and DD tag text
<b>SPLIT</b>	controls the format of the last DT tag in a multiple DT tag group

Use the TSIZE attribute to specify how much space you want for the definition term column (or columns). The default value is 10 bytes, which also sets the default number of DT tags to **one**. If you want to specify more (or less) space than the default, or multiple DT tags, use the TSIZE attribute to assign the value you want.

Use the BREAK attribute to specify where the definition descriptions are supposed to start (on the same line as the definition terms or on the next line). The BREAK attribute can be specified as NONE, ALL, or FIT.

<b><u>NONE</u></b>	The definition descriptions start on the same lines as the definition terms.
<b>ALL</b>	All of the definition descriptions start on the line after the definition terms.
<b>FIT</b>	The definition descriptions are to start on the next line only when the definition term does not fit in the allocated space and spills over into the description area.

The definition list in Figure 59 on page 129 used the default BREAK=NONE. We'll define another list that uses BREAK=ALL.

```
<!doctype dm system>
<panel name=reverb1 width=52>Reverberations
  <area>
    <info width=50>
      <p>Reverberations is one of the most popular brands of electronic
        components available today.
        We stock the following Reverberations components:
        <dl break=all>
          <dt>CD Player Unit
          <dd>With auto-search, auto-off, power door, and
            a two-year warranty.
          <dt>Receiver
          <dd>Digital, 6-speaker hookup, and built-in
equalizer.
          <dt>Tape deck
          <dd>Supports metal and chrome cassettes, and comes with
            a two-year warranty.
        </dl>
      </info>
    </area>
  </panel>
```

Figure 60 on page 131 shows how this definition list formats.




Figure 60. Definition List (BREAK=ALL)

Because the TSIZE and BREAK attributes lend versatility to definition lists, we can rearrange this list practically any way we want. We'll change the BREAK value to FIT, and increase the TSIZE to 13 to show you what we mean. We'll also add headings to the list to show you how they format.

```
<!doctype dm system>
<panel name=reverb2 width=52>Reverberations
  <area>
    <info width=50>
      <p>Reverberations is one of the most popular brands of electronic
        components available today.
        We stock the following Reverberations components:
        <dl tsize=13 break=fit>
          <dthd>Component
            <ddhd>Features
              <dt>CD Player Unit
                <dd>With auto-search, auto-off, power door, and
                  a two-year warranty.
              <dt>Receiver
                <dd>Digital, 6-speaker hookup, and built-in equalizer.
              <dt>Tape deck
                <dd>Supports metal and chrome cassettes, and comes with
                  a two-year warranty.
            </dl>
          </info>
        </area>
      </panel>
```

Here is how the panel looks now:

Reverberations	
Reverberations is one of the most popular brands of electronic components available today. We stock the following Reverberations components:	
Component	Feature
CD Player Unit	With auto-search, auto-off, power door, and a two-year warranty.
Receiver	Digital, 6-speaker hookup, and built-in equalizer.
Tape deck	Supports metal and chrome cassettes, and comes with a two-year warranty.

Figure 61. Definition List (BREAK=FIT)

## Parameter Lists

Parameter lists are another way of defining terms in a list form. You use a parameter list when the terms you are defining are related to the application in some way (for example, showing codes or parameters).

The tags you use to create parameter lists are the PARML tag and its required end tag, the PT (parameter term) tag, and the PD (parameter description) tag. The parameter list tags work a lot like the definition list tags in defining terms and descriptions, except there are no tags for defining list headings.

The PARML tag also contains the TSIZE, BREAK, COMPACT, INDENT, and SKIP attributes. The TSIZE default value is 10 bytes, as it is for definition lists. However, the BREAK default value for parameter lists is ALL, instead of NONE, as in definition lists. Thus, the parameter descriptions format on the lines following the parameter terms unless you specify otherwise.

A parameter list can contain multiple parameter terms. The TSIZE attribute of the enclosing PARML tag specifies the number of PT tags in a group and their respective widths. For example, TSIZE='10 5' specifies 2 parameter term columns with sizes of 10 and 5 characters, respectively.

Here is the markup for a typical parameter list:

```
<!doctype dm system>
<panel name=ordnum width=52>Order Numbers
  <area>
    <info width=50>
      <p>The order number assigned to each inventory item
        represents specific information about the item.
      <p>Specifically,
        <parml>
          <pt>123
          <pd>The first 3 digits represent the
            department the item is stocked in.
          <pt>456
```

```

        <pd>The fourth, fifth, and sixth digits
        represent the item.
        <pt>78
        <pd>The seventh and eighth digits represent
        the lot number of the item.
    </param1>
</info>
</area>
</panel>

```

And Here is the formatted parameter list:




Figure 62. Parameter List

## Nesting Tags within Lists

The format of your lists isn't confined to only list items. You can also nest other tags within the list items. For example, if a list item requires an additional paragraph, you can nest a P tag following the list item.

This markup contains an ordered list with a paragraph nested within the second list item.

```

<!doctype dm system>
<panel name=winshop3 width=52>Window Shopper
<area>
  <info width=50>
    <p>After you have placed your order with Window Shopper, you should...
    <ol>
      <li>Press the Enter key to leave the Order Panel.
      <li>Go to the receiving desk located at the front of the store.
        <pd>Don't forget to bring your receipt!
      <li>Give the cashier the pink copy of your receipt.
      <li>Take your purchases home, and enjoy!
    </ol>
  </info>
</area>
</panel>

```

The paragraph text follows the indentation of the preceding list item, like this:



Figure 63. Nested Paragraph within a List

## The List Part (LP) Tag

If you want to insert unindented text in a list, use the list part (LP) tag. The LP tag is useful for providing information about the list items that follow it.

We added a list part to the panel shown in Figure 63:

```
<!doctype dm system>

<panel name=winshop4 width=52>Window Shopper
  <area>
    <info width=50>
      <p>After you have placed your order with Window Shopper, you should...
      <ol>
        <li>Press the Enter key to leave the Order Panel.
        <li>Go to the receiving desk located at the front of the store.
          <p>Don't forget to bring your receipt!
        <li>Give the cashier the pink copy of your receipt.
          <lp>Occasionally, the item you ordered won't be in stock.
            If this occurs, the cashier will be happy to delete
            the item from your order.
        <li>Take your purchases home, and enjoy!
      </ol>
    </info>
  </area>
</panel>
```

Here is the formatted result:



Figure 64. List Part

## Nesting Lists within Lists

On pages 125 and 127 we showed you how to define levels of nested unordered and ordered lists. You can also nest different types of lists within other lists.

Here is an example of an unordered list nested within a definition list:




Figure 65. Nested Unordered List in a Definition List

Here is the markup we used to create the nested lists in Figure 65:

```
<!doctype dm system>
<panel name=payment width=52>Payment Procedures
  <area>
    <info width=50>
```

```

<h1>Methods of Payment
<dl size=9 break=all>
  <dt>Cash
  <dd>Of course, we always accept cash!
  <dt>Charge
  <dd>Your charge card is welcome here!
  We accept the following charge cards:
    <ul compact>
      <li>BigCharge
      <li>MoneyCard
      <li>Plastic Express
    </ul>
  <dt>Personal check
  <dd>We gladly welcome your personal check,
  with the proper identification.
</dl>
</info>
</area>
</panel>

```

You can nest any type of list within another list. Remember, whenever you nest lists, be sure that you end each level with its proper end tag.

---

## Alerting Users: Notes, Warnings, Cautions, and Attention

DTL provides you with tags that you can use to alert the user to certain text that warrants special attention. Whether you are noting a minor aspect of the application or alerting the user to the risk of possible damage to programs or data, you can alert the user appropriately.

In this section, we discuss the following tags:

- ATTENTION
- CAUTION
- NOTE
- NOTEL
- NT
- WARNING.

### Notes

The NOTE, NOTEL, and NT tags format as noted text. Use notes to emphasize minor points.

When you use either the NOTE or NT tag, you get the text "Note:" followed by a space before the text you specify. However, the text is formatted differently depending on which tag you use.

The NOTEL tag is formatted with the first line containing the text "Notes:" followed by a numbered list of note information provided by the <LI> tag.

#### The NOTE tag

If the text is a single paragraph, you use the NOTE tag. The text is formatted as an unindented block, like a paragraph. The NOTE tag does not require a matching end tag.

You use the NOTE tag like this:

```

<!doctype dm system>
<panel name=widget61 width=50>Widgets
<area>
  <info width=48>
    <p>Choose the type of Widget you want to order by placing

```

```

the cursor on the field and pressing Enter.
<note>If the Widget you wish to order is not in stock, please
refer to the "Back Order" panel to place an order.
</info>
</area>
</panel>

```

Figure 66 shows how it formats.




Figure 66. Note (NOTE tag)

### The NOTEL tag

If more than one note is used for special attention information, you use the NOTEL tag. Each note is provided by a separate LI tag. The notes are numbered similar to the format described in "Ordered Lists" on page 126. You use either the P or LP tag to add any additional paragraphs in the NOTEL definition. Use the required end tag to end the NOTEL definition.

In this example, 2 notes are used, 1 with more than one paragraph. We use the NOTEL tag and its required end tag along with LI tags to define the notes, and a P tag for the additional paragraph.

```

<!doctype dm system>
<panel name=widget63 width=50>Widgets
<area>
<info width=48>
<p>Choose the type of Widget you want to order by placing
the cursor on the field and pressing Enter.
<notel>
<li>If the Widget you wish to order is not in stock, please
refer to the "Back Order" panel to place an order.
<li>Back-ordered Widgets usually arrive within three days.
<p>Please check again in three days.
</notel>
<p>If you want to order more than one Widget, specify the quantity
and press Enter.
</info>
</area>
</panel>

```

Notice that the P tag in the note is coded *before* the NOTEL end tag, indicating that the second paragraph belongs in the note.

This is how the panel looks now:




Figure 67. Note! (NOTEL tag)

As you can see, the text of the NOTEL tag is formatted as a list under the "Notes:" heading. The text of the P tag is indented to match the list items.

### The NT tag

If the note requires more than one paragraph, you use the NT tag. You use the P tag to add any additional paragraphs in the NT definition. Use the required end tag to end the NT definition.

Another difference between the NOTE and NT tag is that the NT tag indents the note text from the left panel margin.

In this example, the note is longer than one paragraph. We use the NT tag and its required end tag to define the note, and a P tag for each additional paragraph.

```
<!doctype dm system>
<panel name=widget62 width=50>Widgets
  <area>
    <info width=48>
      <p>Choose the type of Widget you want to order by placing
        the cursor on the field and pressing Enter.
      <nt>If the Widget you wish to order is not in stock, please
        refer to the "Back Order" panel to place an order.
        <p>Back-ordered Widgets usually arrive within three days.
      </nt>
      <p>If you want to order more than one Widget, specify the quantity
        and press Enter.
    </info>
  </area>
</panel>
```

Notice that the P tag in the note is coded *before* the NT end tag, indicating that the second paragraph belongs in the note.

This is how the panel looks now:




Figure 68. Note (NT tag)

As you can see, the text of the NT tag is indented, as is the text of the P tag coded within the NT tag.

## Attention and Warning

Attention statements and warning statements alert the user of a possible risk involved with a user action, or of existing error conditions.

You must immediately precede the ATTENTION or WARNING tag with a P (paragraph) tag, LI (list item) tag, or LP (list part) tag. The warning statement formats with the term "Warning:" before the text. The attention statement formats with the term "Attention:" before the text.

The ATTENTION and WARNING tags have no associated attributes and require a matching end tag.

Here is the markup for a warning statement that formats as a paragraph.

```
<!doctype dm system>
<panel name=addfile width=50>Changing a File
  <area>
    <info width=48>
      <p>After you have made the desired changes
to the file, press Enter to save the changes.
      <p><warning>Pressing Enter saves
ALL changes made to the file.
You can cancel this operation by pressing
the F12=Cancel key.
      </warning>
    </info>
  </area>
</panel>
```

Here is the formatted result:




Figure 69. Warning

## Caution

Caution statements indicate the greatest degree of severity. Like the WARNING tag, the CAUTION tag has a required end tag, and must be preceded by a P (paragraph) tag, LI (list item) tag, or LP (list part) tag. The caution statement formats with the term "CAUTION:" followed by the caution text on the next line.

```
<!doctype dm system>
<panel name=del file width=50>Deleting a File
  <area>
    <info width=48>
      <p>To delete a file, type the file name in the
        "Delete this file" field and press Enter.
      <p>A message appears asking for verification.
        To continue the delete operation, press Enter.
      <p><b>CAUTION</b>Verifying the delete operation
        permanently deletes the file from your records.
        There is no chance of recovery.
      </caution>
    </info>
  </area>
</panel >
```

Here is the formatted result:



Figure 70. Caution

## Emphasizing Panel Text

You can emphasize text on application panels or on help panels with highlighting by using the HP (highlighted phrase) tag. You can also highlight words or phrases to indicate that additional information is available by using the RP (reference phrase) tags. On a color terminal, the emphasized text displays in a CUA defined color, or whatever color you set with the Color Change Utility.

Highlighting requires the use of 3270 attribute bytes to control the display of highlighted text. The attribute positions before and after the highlighted text display as blank spaces. These attributes might limit the formatting of your highlighted phrase or reference phrase.

For example, if you typed your text as follows:

```
<HP>To cancel this option</HP>, press the F12 key.
```

Here is the result:

**To cancel this option**, press the F12 key.

You can prevent this situation by writing statements that do not require punctuation following an HP or an RP end tag.

### Highlighted Phrases

The HP (highlighted phrase) tag provides emphasis through highlighting. You can focus the user's attention to particular sections of the panel text by highlighting words, phrases, or entire paragraphs.

The HP tag requires a matching end tag to indicate the end of a highlighted phrase.

The following markup example shows you how to use the HP tag.

```

<!DOCTYPE DM SYSTEM>

<VARCLASS NAME=date TYPE=' char 8' >
<VARCLASS NAME=numcls TYPE=' numeric 7' >
<VARCLASS NAME=namecls TYPE=' char 25' >
<VARCLASS NAME=char1cls TYPE=' char 1' >
<VARCLASS NAME=char7cls TYPE=' char 7' >

<VARLIST>
  <VARDCL NAME=whchsrch VARCLASS=char1cls>
  <VARDCL NAME=curdate VARCLASS=date>
  <VARDCL NAME=cardno VARCLASS=numcls>
  <VARDCL NAME=name VARCLASS=namecls>
  <VARDCL NAME=address VARCLASS=namecls>
  <VARDCL NAME=cardsel VARCLASS=char1cls>
  <VARDCL NAME=card VARCLASS=char7cls>
  <VARDCL NAME=north VARCLASS=char1cls>
  <VARDCL NAME=south VARCLASS=char1cls>
  <VARDCL NAME=east VARCLASS=char1cls>
  <VARDCL NAME=west VARCLASS=char1cls>
</VARLIST>

<PANEL NAME=hlitep>Library Card Registration
<AB>
  <ABC>File
    <PDC>Add Entry
      <ACTION RUN=add>
    <PDC>Delete Entry
      <ACTION RUN=delete>
    <PDC>Update Entry
      <ACTION RUN=update>
    <PDC>Exit
      <ACTION RUN=exit>
  <ABC>Search
    <PDC CHECKVAR=whchsrch MATCH=1>Search on name
      <ACTION SETVAR=whchsrch VALUE=1>
      <ACTION RUN=search>
    <PDC CHECKVAR=whchsrch MATCH=2>Search on card number
      <ACTION SETVAR=whchsrch VALUE=2>
      <ACTION RUN=search>
  <ABC>Help
    <PDC>Extended Help...
      <ACTION RUN=exhelp>
    <PDC>Keys Help...
      <ACTION RUN=keyshelp>
  </AB>
<TOPINST>Type in <HP>patron's name</HP> and <HP>card number</HP>
  (if applicable).
<TOPINST>Then select an action bar choice.
<AREA>
  <DTACOL PMTWIDTH=12 ENTWIDTH=25 DESWIDTH=25 SELWIDTH=25>
  <DTAFLD DATAVAR=curdate USAGE=out ENTWIDTH=8>Date
  <DTAFLD DATAVAR=cardno ENTWIDTH=7>Card No.
    <DTAFLDD>(A 7-digit number)
  <DTAFLD DATAVAR=name>Name
    <DTAFLDD>(Last, First, M.I.)
  <DTAFLD DATAVAR=address>Address
  </DTACOL>
<DIVIDER>
<REGION DIR=horiz>
<SELFLD NAME=cardsel PMTWIDTH=30 SELWIDTH=38>Choose
one of the following
  <CHOICE CHECKVAR=card MATCH=new>New
  <CHOICE CHECKVAR=card MATCH=renew>Renewal
  <CHOICE CHECKVAR=card MATCH=replace>Replacement
</SELFLD>
<SELFLD TYPE=multi PMTWIDTH=30 SELWIDTH=25>Check valid branches

```

```

    <CHOICE NAME=north HELP=nthlp CHECKVAR=nth>North Branch
    <CHOICE NAME=south HELP=sthhlp CHECKVAR=sth>South Branch
    <CHOICE NAME=east HELP=esthlp CHECKVAR=est>East Branch
    <CHOICE NAME=west HELP=wsthlp CHECKVAR=wst>West Branch
  </SELFLD>
</REGION>
</AREA>
<CMDAREA>Enter a command
</PANEL>

```

Here is the formatted result:

File Search Help

---

Library Card Registration

Type in **patron's name** and **card number** (if applicable).

Then select an action bar choice.

Date . . . : 08/29/90  
 Card No. . . \_\_\_\_\_ (A 7-digit number)  
 Name . . . \_\_\_\_\_ (Last, First, M.I.)  
 Address . . \_\_\_\_\_

Choose one of the following	Check valid branches
— 1. New	— North Branch
— 2. Renewal	— South Branch
— 3. Replacement	— East Branch
	— West Branch

Enter a command ==> \_\_\_\_\_

F1=Help      F2=Split      F3=Exit      F6=KEYSHELP      F9=Swap  
 F12=Cancel

Figure 71. Highlighted Phrase Example

## Reference Phrases

The RP (reference phrase) tag allows you to highlight words or phrases on panels to indicate that additional help information is available. When a help panel with reference phrases is displayed, the cursor is positioned in the first reference phrase. When an application panel containing reference phrases is displayed, the cursor will be positioned to the first reference phrase or panel input field, unless the cursor setting has been specified by the application. The reference phrase is an input-capable field so that the user can tab to successive reference phrases on the panel. The reference phrase text is refreshed whenever the panel is displayed.

When the user places the cursor on a reference phrase and requests help, the reference phrase panel or message is displayed. Reference phrase help panels themselves can also contain reference phrases. When a user cancels a reference phrase help, the panel from which the user requested the reference phrase help is displayed again. All other help facilities, such as KEYSHELP and EXHELP, are available from a reference phrase help panel.

The RP tag requires a matching end tag to indicate the end of the reference phrase text.

The following markup example shows you how to use the RP tag.

```

<!DOCTYPE DM SYSTEM>

<HELP NAME=frenchl depth=12>Help for Masters Degree in French Literature
<area>
<info>
<p>
The Masters in French Literature (MFL) Program is also available
to students interested in
<rp help=liteve>evening studies.</rp>
<p>
Please consult your program advisers for details before registering for
a class.
</info>
</area>
</help>

<help name=liteve depth=13>Help for Evening Studies
<area>
<info>
<p>
Evening Studies offered by the French Literature
graduate program are available to students
interested in part-time and full-time studies.
All core courses and many electives are offered
in the evening on a rotating basis. Please
consult your program advisers for details before
registering for a class.
</info>
</area>
</help>

```

Here is the formatted result:

Help for Masters Degree in French Literature

The Masters in French Literature (MFL) Program is also available to students interested in **evening studies**.

Please consult your program advisers for details before registering for a class.

F1=Help	F3=Exit	F5=Exhelp
F6=Keyshelp	F7=PrvTopic	F8=NxtTopic
F10=PrvPage	F11=NxtPage	F12=Cancel

*Figure 72. Reference Phrase Example*

Accordingly, when the user selects the reference phrase **evening studies**, the help panel specified by the HELP attribute (help=liteve) is displayed.




Figure 73. Reference Phrase Example of Help Attribute

The *help-panel-name* attribute specifies the name of the help panel to be displayed if the reference phrase is selected.

## Using Information Regions with Other Panel Elements

You can use information regions to complement the other elements of an application panel in many different ways. For example, you can use an information region to provide additional information for fields on an application panel.

The information region in the following markup example uses a paragraph and a compact ordered list to tell the user how to interact with the panel fields. Figure 74 on page 146 shows the formatted result.

```
<!doctype dm system>
<VARCLASS NAME=selcls TYPE='char 1'>
<VARLIST>
  <VARDCL NAME=day VARCLASS=selcls>
  <VARDCL NAME=time VARCLASS=selcls>
</VARLIST>
<panel name=appmnt>Make an Appointment
  <area>
    <info width=74>
      <p>To schedule an appointment, you must choose one
        selection from each field.
      <ol compact>
        <li>Choose a day from the first field.
        <li>Choose a time slot from the second field.
        <li>After you have completed both fields, press
          Enter to log your appointment and leave the panel.
        </ol>
    </info>
    <divider type=solid gutter=3>
    <region dir=horiz>
      <region>
        <sel fld name=day selwidth=20 pmtwidth=9>Weekdays:
          <choice>Monday
          <choice>Tuesday
          <choice>Wednesday
          <choice>Thursday
          <choice>Friday
        </sel fld>
      </region>
    <divider gutter=8>
    <region>
      <sel fld name=time selwidth=20 pmtwidth=5>Time:
        <choice>9:00
```

```

        <choi ce>10: 00
        <choi ce>11: 00
        <choi ce>12: 00
        <choi ce>1: 00
        <choi ce>2: 00
        <choi ce>3: 00
        <choi ce>4: 00
    </sel fld>
</regi on>
</regi on>
</area>
</panel >

```




Figure 74. Information Region

## Help Panels

In this section, we show you how to use the DTL to define help panels that provide help to users while they are using an ISPF application. We also show you how to link help panels with application panels.

### Defining Help Panels

The HELP tag and its required end tag define a help panel. The HELP start tag indicates the beginning of a help panel definition, and the HELP end tag closes the definition. All of the other tags that compose a help panel are coded between these two tags. You also use the HELP tag to define the help panel title in the same way you code panel title text with the PANEL tag, as tag content.

The HELP tag and its matching end tag look like this:

```

<help name=help01>Help Panel Title
</help>

```

In the above example, we added the required NAME attribute and value to the HELP start tag. The NAME value you assign must follow the standard naming convention described in “Rules for Variable Names” on page 205.

The value you assign to NAME is the value that elements such as application panels, fields, and messages use to provide help to the user.

For example, if we define the help we want to provide for an application panel in a help panel with the NAME value *help01*, we would specify that help panel like this in the PANEL definition:

```
<panel name=panel01 width=60 depth=18 help=help01>Application
```

The help panel *help01* would appear when the user requests help for that application panel.

Like the PANEL tag, the HELP tag has WIDTH and DEPTH attributes that define the dimensions of the panel. However, help panels differ from application panels. If the DEPTH attribute is specified on the AREA tag, a single panel is created with a scrollable section to allow the display of longer sections of help text. Otherwise, the conversion utility generates as many help panels as needed (up to 37) for the help text content you define. This means that you can define text for a help panel that exceeds the defined depth, and, even though the text may not appear in the initial display of the panel, the user can view the text through page scrolling. Examples of both types of help panel scrolling are shown on page 149 and Figure 81 on page 152.

Because ISPF displays all DTL-defined help panels in pop-ups, the WIDTH and DEPTH values you specify must allow for the addition of two lines (depth) and 4 characters (width) for pop-up borders. Therefore, WIDTH=76 and DEPTH=22 are the maximum values that can be used with 80-by-24 display devices. The HELP panel default values are WIDTH=50 and DEPTH=10.

Typically, you would define help panel values of WIDTH=60 and DEPTH=22 or less. The specified depth must include allowance for the panel title line and its separator. A help panel that does not end with a scrollable area also reserves four lines for the function key area.

## Defining Help Panel Text

The text you define for help panels cannot be modified by the user; it is for information purposes only. To define this text, use an information region and the tags associated with information regions. The INFO tag and its matching end tag are required in help panel definitions.

You can also use AREA definitions within help panels. Remember to code the entire INFO definition (start and end tag) within the AREA definition, just as you would on an application panel. Here is an example:

```
<help name=help01>Help Panel Title
  <area>
    <info>
    :
    </info>
  </area>
</help>
```

You can use any of the information region tags discussed earlier in this chapter in a help panel. For example, you use the P (paragraph) tag to define a paragraph of text on a help panel the same way you use it to define a paragraph on an application panel.

In the following help panel markup, we use two paragraphs, an unordered list, a figure and figure caption to define the help text. The specification of DEPTH=28 is valid only if the display terminal has 30 or more display lines. Figure 75 on page 148 shows the formatted result.

```

<!doctype dm system>

<help name=olcchl p depth=28 width=50>Help for Online Catalog
<area>
<info>
<p>The Online Catalog provides
you with:
<ul compact>
<li>The book title
<li>Catalog number
<li>Page count
<li>The author
<li>A brief description
</ul>
<p>Here is an example:
<fig>
  The Yellow Subroutine
  365 Pages          1234.56
  John-Paul Georgenringo

  A young band of British programmers embarks on
  a voyage across a perilous "sea" language in
  search of FORTRAN and fame.
<figcaption>Online Catalog Example
</figcaption>
</info>
</area>
</help>

```



*Figure 75. Help Panel*

In Figure 75, all of the text was displayed because the depth we defined for the help panel was large enough to accommodate the text. However, the amount of help you want to provide for your users can vary, and it's not always possible to

display all of the help text you define in the initial panel display, especially when you don't, or can't, specify a large DEPTH value for the help panel.

Depending on the use of the AREA tag, the conversion utility generates multiple panels or a single scrollable help panel.

The following help panel markup includes an information region that contains a paragraph, a definition list, and two unordered lists nested within the definition list.

The addition of the DEPTH attribute on the AREA tag illustrates a scrollable panel.

```
<!DOCTYPE DM SYSTEM>
```

```
<help name=helpscr width=46 depth=16>ShelfBrowse for Kids
<area depth=10>
  <info>
    <p>ShelfBrowse can help you
    find any kind of book you are looking for.
    The two main categories for books are:
    <dl tsize=12>
      <dthd>Book
      <ddhd>Description
      <dt>Fiction
      <dd>Fiction books are stories
      that never really happened.
      The writer made them up.
      For example:
      <ul>
        <li>Fairy Tales
        <li>Mysteries
        <li>Science fiction stories
      </ul>
      <dt>Nonfiction
      <dd>Nonfiction books are about
      things that really exist.
      For example:
      <ul>
        <li>History books
        <li>Reference books
        <li>How-to books
      </ul>
    </dl>
  </info>
</area>
</help>
```

When initially displayed, the first part of the scrollable text is visible. For this example, to scroll down, place the cursor on the first or last displayed line of text, and press Enter or the RIGHT (F11) key. Use the LEFT (F10) key to scroll up.




Figure 76. Help Panel (Example 1 of 4)

After scrolling down, the following panel appears:




Figure 77. Help Panel (Example 2 of 4)

After scrolling down, the following panel appears:




Figure 78. Help Panel (Example 3 of 4)

After scrolling down, the following panel appears:

Note that because there is only one additional line to display, the scroll has moved the scrollable text up only one line.




Figure 79. Help Panel (Example 4 of 4)

If no AREA tag is present or the AREA tag does not contain the DEPTH attribute, multiple help panels are generated. ISPF simulates scrolling by displaying the set of multiple help panels in sequence.

If the help panel contains additional text, the conversion utility provides an indicator at the top of the panel to notify the user. If additional text exists, the text **More:** is displayed followed by a + sign. Following scrolling, if additional text stills exists, the indicator displays as “**More:** – +”, indicating scrolling is possible in either direction. If, following scrolling, no more text is available through scrolling forward, but text is available by scrolling backward, the indicator displays as “**More:** –”. Scrolling function keys are defined by tutorial processing.

The following markup uses the previous example without a DEPTH attribute on the AREA tag to generate multiple help panels. Because all of the data does not fit in one help panel, the conversion utility created three panels: HELPSB, HELPSBX0, and HELPSBX1. The panels are displayed individually by tutorial processing. Figures 80, 81, and 82 show the formatted results with the function key area displayed in its short form.

```
<!DOCTYPE DM SYSTEM>
```

```
<help name=helpsb width=46 depth=16>ShelfBrowse for Kids
<area>
  <info>
    <p>ShelfBrowse can help you
    find any kind of book you are looking for.
    The two main categories for books are:
    <dl tsize=12>
      <dthd>Book
      <ddhd>Description
      <dt>Fiction
      <dd>Fiction books are stories
      that never really happened.
      The writer made them up.
      For example:
      <ul>
        <li>Fairy Tales
        <li>Mysteries
        <li>Science fiction stories
      </ul>
```

```

<dt>Nonfiction
<dd>Nonfiction books are about
things that really exist.
For example:
  <ul>
    <li>History books
    <li>Reference books
    <li>How-to books
  </ul>
</dl>
</info>
</area>
</help>

```




Figure 80. Help Panel (Example 1 of 3)




Figure 81. Help Panel (Example 2 of 3)




Figure 82. Help Panel (Example 3 of 3)

As we stated earlier, you can use any of the tags provided for information regions to define the text of the information regions in your help panels.



---

## Chapter 7. Messages

You use messages to communicate information to users; that is, information that you, the application developer, believe they need to know. Typically, this would be information regarding user actions, status, or problems that need correction. Additionally, ISPF issues messages when needed to inform users of situations that ISPF handles.

The Dialog Tag Language provides you with the means of defining application-provided messages. You use ISPF services to handle the display of messages. When the application calls for a message to be displayed, ISPF places it either in the message area of the application panel or within a pop-up window, known as a *message pop-up*.

Messages are defined according to their purpose and severity. The four types of messages you can define are:

<b>Information</b>	To provide information about a user-requested action.
<b>Warning</b>	To provide information about conditions the user may need to be aware of.
<b>Action</b>	To alert the user to an exception condition that requires a response from the user to correct the situation.
<b>Critical</b>	To alert the user to an exception condition that requires a response from the user to correct the situation. Critical messages are similar to action messages.

This chapter tells you how to define messages for your applications. For a complete description of ISPF message processing, refer to *ISPF Dialog Developer's Guide and Reference*.

---

### Defining Messages

The messages you define using DTL are stored within *message members*. Each regular message member can contain up to 10 messages. The conversion utility stores the message members in an ISPF message file for the application. The DTL tags you use to define messages and message members are:

<b>MSGMBR</b>	Defines a message member. The MSGMBR tag requires an end tag.
<b>MSG</b>	Defines a message within a message member. The text of the MSG tag is the text that appears as the message. Each message can be up to 512 bytes in length after variable substitution. "Variable Substitution" on page 160 describes variable substitution in messages.

You assign an identifier to each message within a message member. The message identifier is composed of two required attribute values: the NAME attribute value of the MSGMBR tag and the SUFFIX attribute value for the MSG tag.

The NAME attribute you specify for the MSGMBR tag can consist of 1–5 uppercase or lowercase alphabetic characters and 2 numeric characters.

The SUFFIX attribute values for each of the MSG tags you code within a MSGMBR definition must consist of either 1 numeric character (0–9) or a numeric character (0–9) and an optional suffix character as defined for ISPF messages. Each of the values must be unique (a message suffix cannot be defined twice in a message member).

```
<!doctype DM system>
```

```
<msgmbr name=maia00>
  <msg suffix=0>You cannot type a number in the Name field.
  <msg suffix=1>Please include your first name in the Name field.
  <msg suffix=2>Unrecognized character in Name field. Please correct.
  <msg suffix=3>Unrecognized character in Address field. Please correct.
  <msg suffix=4>You cannot type a number in the City field.
  <msg suffix=5>Unrecognized character in City field. Please correct.
  <msg suffix=6>You cannot type a number in the State field.
  <msg suffix=7>You must type two letters in the State field.
  <msg suffix=8>The Zip code exceeds the maximum length.
  <msg suffix=9>You cannot type an alphabetic character in the Zip field.
</msgmbr>
```

The value of the MSG SUFFIX attribute, when added to the MSGMBR NAME value, forms the message identifier for that message. For example, the message identifier for the message: "You must type two letters in the State field". is *maia007*. If you specify *maia007* as the MSG value on a CHECKL tag, this message is displayed when ISPF detects the error as a result of input validation.

In addition to SUFFIX, the MSG tag has an optional HELP attribute that allows you to identify a help panel for the message. for information about defining help panels, see Chapter 6, "Information Regions and Help Panels," on page 113.

## Specifying Message Severity

The severity you assign a message determines if the alarm is sounded when the message is displayed. You can specify the severity of a message with the MSGTYPE attribute of the MSG tag. ISPF accepts one of four values for the MSGTYPE attribute: INFO (the default value), WARNING, ACTION, or CRITICAL. The value can be supplied as a variable name.

### Information Messages

Use the default value INFO when you want to provide the user with feedback about the state of the application.

```
<msgmbr name=orda00>
  <msg suffix=0>Your order is being processed. Please wait...
</msgmbr>
```

### Warning Messages

Warning messages tell users that a potentially undesirable situation could occur. Users only need to respond to the message to continue, although corrective action may be required later. ISPF displays warning messages with an alarm.

```
<msgmbr name=orda00>
  <msg suffix=0>Your order is being processed. Please wait...
  <msg suffix=1 msgtype=warning>Your request for the engraving
  option is not valid.
  Please check your request, and correct it if necessary.
</msgmbr>
```

### Action and Critical Messages

Action and critical messages both represent the highest degree of severity. They tell users about exception conditions that require a response. The user must respond with a specific action to continue with the application. ISPF displays these messages with an alarm.

Action messages may appear in a pop-up or in the panel message area. Critical messages always appear in a pop-up.

```
<!doctype dm system>
```

```
<msgmbr name=orda00>
  <msg suffix=0>Your order is being received. Please wait...
  <msg suffix=1 msgtype=warning>Your request for
  the engraving option is not valid.
  Please check your request, and correct it if necessary.
  <msg suffix=2 msgtype=action>The data you have
  entered is incorrect.
  Please reenter the data.
</msgmbr>
```

## Short Messages

The SMSG attribute enables you to specify a short message. The short message does not conform to CUA architecture, but it is supported for ISPF compatibility.

## Assigning Messages

Some of the DTL tags have an optional MSG attribute that you use to specify a message-identifier. The message text associated with the message-identifier specified is displayed when conditions you define for the tag are not met by the user.

The following list contains the DTL tags that have MSG attributes associated with them, and describes the conditions for each.

- |               |  |
|---------------|--|
| <b>CHECKL</b> | Use the MSG attribute of the CHECKL tag to specify a message ISPF displays when the user's input fails the validation check defined for the check list.  |
| <b>CHOFLD</b> | Use the MSG attribute of the CHOFLD tag to specify a message ISPF displays when the user does not provide input for a required field. You can only assign a message to a data field when the REQUIRED attribute has a value of YES.  |
| <b>DTAFLD</b> | Use the MSG attribute of the DTAFLD tag to specify a message ISPF displays when the user does not provide input for a required field. You can only assign a message to a data field when the REQUIRED attribute has a value of YES.  |
| <b>LSTCOL</b> | Use the MSG attribute of the LSTCOL tag to specify a message ISPF displays when the user does not provide input for a required entry. You can only assign a message to a list column when the REQUIRED attribute has a value of YES.   |
| <b>SELFLD</b> | Use the MSG attribute of the SELFLD tag to specify a message ISPF displays when the user does not provide input for a required single-choice selection field. You can only assign a message to a selection field when the REQUIRED attribute has a value of YES.<br><br>Use the SELMSG attribute of the SELFLD tag to specify a message ISPF displays when the user selects an invalid choice. |

Use the SELMSGU attribute of the SELFLD tag to specify a message ISPF displays when the user selects an unavailable choice.

**VARCLASS** Use the MSG attribute of the VARCLASS tag to specify a message ISPF displays when the user's input fails the validity check defined by the VARCLASS TYPE attribute.

**Note:** The message specified by the MSG attribute of a VARCLASS tag is also used if enclosed checks (CHECKL tag) or translations (XLATL tag) do not include the MSG attribute.

**XLATL** Use the MSG attribute of the XLATL tag to specify a message that ISPF displays when the user's input fails a specified translation.

ISPF displays a default message for most of the situations listed above if you do not specify the MSG attribute.

To show you how messages are associated with DTL tags, the following example defines a data field that requires input from the user. It also defines a message member that contains the warning message ISPF displays if the user does not provide input for the field. Figure 83 on page 159 shows the displayed panel and message.

```
<!doctype dm system>
<varclass name=namecls type='char 30' >
<varlist>
  <vardcl name=name varclass=namecls>
</varlist>
<msgmbr name=ordb00>
  <msg suffix=0 msgtype=warning>You must type your name in the Name field.
</msgmbr>
<panel name=msgxmp1>Application Panel
  <dtafld datavar=name pmtwidth=12 required=yes msg=ordb000>Name
<cmdarea>
</panel>
```




Figure 83. Data Field and Message

## Displaying Messages

You can specify how a message will be displayed, either in the panel message area or a pop-up, using the LOCATION attribute of the MSG tag.

There are five valid values you can assign to LOCATION: AREA (the default), MODAL, MODAL(L), MODELESS, and MODELESS(L). AREA specifies that the message is to appear in the panel message area, unless the text of the message exceeds the length of the message area. If the text of the message exceeds the message area length, ISPF displays the message in a pop-up.

If you want a message that requires a response from the user to appear in a pop-up, specify the MODAL or MODAL(L) value for the LOCATION attribute. This is useful for presenting warning and action messages that have a good deal of text.

If you want a message that does not require a response from the user to appear in a pop-up, specify the MODELESS or MODELESS(L) value for the LOCATION attribute.

For further discussion of these LOCATION values, see “MSG (Message)” on page 390.

The following message member markup contains three messages, each of them with a different LOCATION value. The second and third messages display in pop-up windows.

```
<!doctype dm system>
<msgbr name=orda01>
  <msg suffix=0>Your order is being received. Please wait...
  <msg suffix=1 msgtype=warning location=modeless>Your request for
  the engraving option is not valid.
  Please check your request, and correct it if necessary.
```

```
<msg suffix=2 msgtype=action location=modal>The data you have
entered is incorrect.
Please reenter the data.
</msgmbr>
```

## Variable Substitution

You can specify a variable in the text of a message by using the VARSUB (variable substitution) tag. When the message is displayed, ISPF inserts the current value of the variable into the text of the displayed message.

You code the VARSUB tag within the text of the message where you want the substitution to be made. You use the required VAR attribute of the VARSUB tag to specify the name of a declared variable whose value is substituted in the message text.

In the following example, we used two variable substitutions in the text of the message "msga001". The first VARSUB specifies the variable *invvar*, which provides an invoice number in the message. The second VARSUB specifies the variable *datevar*, which provides a date in the message.

```
<!doctype dm system>

<varclass name=invoices type='char 10'>
<varclass name=updates type='char 8'>

<varlist>
  <vardcl name=invvar varclass=invoices>
  <vardcl name=datevar varclass=updates>
</varlist>

<msgmbr name=msg00>
  <msg suffix=0>Your request is being processed.
  <msg suffix=1>The invoice number you have requested,
    <varsub var=invvar>, was last updated on
    <varsub var=datevar>.
</msgmbr>
```

---

## Chapter 8. The Application Command Table

In addition to the commands in the ISPF system command table, DTL provides a way to define and store commands that are specific to your application. You can also define commands that override the ISPF system commands. You define and store these commands within a *command table* for your application. These application-specific commands define the responses to commands entered by the user in the command entry field and commands linked to pull-down choices and key mapping lists.

You can define only one command table for an application. ISPF locates the command table using the defined *application-identifier* for the command table.

For a complete description of ISPF command processing and a list of the ISPF system commands, refer to the *ISPF User's Guide*.

**Note:** You can use the TSO ISPCMDTB command to convert existing command tables to DTL. To use ISPCMDTB, ensure that the command table is in your table concatenation (ISPCMDTB), type **TSO ISPCMDTB applid** (where *applid* is the application id of the command table). This will place you in an edit session containing the DTL version of the command table. Use the editor CREATE or REPLACE commands to save the table to your DTL source data set.

---

### Defining the Application Command Table

The tags you use to define an application command table are:

- |               |   |
|---------------|---|
| <b>CMDTBL</b> | Begins the definition of an application command table. The required end tag ends the definition.  |
| <b>CMD</b>    | Defines a command within an application command table. You code the CMD tags within a CMDTBL definition (between the start and end tags).       |
| <b>CMDACT</b> | Defines the action taken by ISPF when a user enters a command. You code the CMDACT tag following the command (CMD) with which it is associated. |

The CMDTBL tag has a required APPLID attribute that you use to define the *application identifier* for the command table. ISPF uses the value you assign with the APPLID attribute to identify the command table. The value you assign to APPLID must be the same as the run-time application identifier specified when the application starts.

The value you assign as an application identifier can have a maximum of 4 characters, and the first character must be A-Z, a-z, @, #, or \$.

Any remaining characters can be either A-Z, a-z, @, #, \$ or 0-9. Lowercase characters are translated to their uppercase equivalents. Additionally, ISPF reserves the application identifier ISPx, where x is any character including the space character. Do not use any of these for an APPLID value.

The conversion utility uses the application identifier as a prefix to the string CMDS to form the name of the command table library. For example, the APPLID value, *demo*, results in the application command table name DEMOCMDS.

Command tables are updated using ISPF table services. Input is obtained from the ISPTLIB DDname allocation and output is written to the ISPTABL DDname allocation. Refer to the description of how to allocate libraries before starting ISPF in the *ISPF User's Guide* for more information about the use of ISPTLIB and ISPTABL.

When a user enters a command in a command-entry field or through a pull-down choice or function key, ISPF searches the command tables defined for the user. Any or all of the following tables will be searched in the order shown below if the table is present and defined.

1. Application command table
2. User command tables
3. Site command tables
4. System command table

**Note:** Up to three user and site command tables can be defined in the ISPF Configuration table. The search order of the site and system command table can be reversed if specified as such in the ISPF Configuration table.

If the command is found in a command table, ISPF performs the action defined in that command table for that command. If the command is not found in any of the command tables, ISPF passes the command to the application program for processing. If any of the command tables are not present, ISPF skips to the next command table in the hierarchy.

Use the CMD tag to define each of the commands within the application command table. The CMD tag has a required NAME attribute that you use to identify the *internal-command-name* for the command. The value you assign as an *internal-command-name* must not exceed 8 characters, and the first character must be alphabetic. Any remaining characters can be either alphabetic or numeric.

The following markup example shows a source file that contains an application command table, a key mapping list, and a panel with an action bar. The command table contains commands that are mapped to the RUN attributes of the ACTION tags associated with the pull-down choices and to the CMD attributes of the KEYI tags.

```
<!doctype dm system>

<cmdtbl applid=brws>
  <cmd name=quit>quit
  <cmdact action=...>
  <cmd name=send>send
  <cmdact action=...>
</cmdtbl>

<keyl name=panl keys>
  <keyi key=f4 cmd=quit>
  <keyi key=f6 cmd=send>
</keyl >

<panel ... >
  <ab>
    <abc>Acti ons
    <cdc>Qui t
```

```

        <action run=quit>
        <cdc>Send
        <action run=send>
        <cdc>Exit
        <action run=exit>
    </ab>
    :
</panel>

```

Because ISPF provides the EXIT command, it is not defined within the application command table. When the EXIT command is entered, ISPF finds it in the system command table.

## Specifying Command Actions

You must specify a CMDACT tag for each of the CMD tags you define within an application command table so that ISPF can process these commands. You use the CMDACT tag to define the action taken for the command. Code the CMDACT tag immediately after the CMD tag it is associated with.

### The ACTION Attribute

The CMDACT tag has a required attribute, ACTION, which you use to specify the ISPF command action. You can assign one of the ISPF command actions in the following list and some of the ISPF-provided system commands as listed in “CMDACT (Command Action)” on page 264. You can also specify command actions dynamically at run time as discussed in “Specifying Command Actions Dynamically” on page 164.

- |                 |  |
|-----------------|--|
| <b>ALIAS</b>    | To allow a command to have an alternate name, such as using QUIT as an alias for EXIT.   |
| <b>PASSTHRU</b> | To pass the command to the application. The <i>internal-command-name</i> and any command parameters are passed to the dialog in the ISPF ZCMD system variable.   |
| <b>SETVERB</b>  | To pass the command to the application. The <i>internal-command-name</i> is passed to the dialog in the ZVERB system variable, and the parameters (if any) are passed to the dialog in the ZCMD system variable. |

The ALIAS command action provides you with a way to define synonyms for commands. The *internal-command-name* you define for the ALIAS attribute value defines the command to be processed. You must enclose the keyword ALIAS, the *internal-command-name*, and any optional parameters within quotes.

When you define an ALIAS command action, you must code that command’s CMD and CMDACT tags before the command the ALIAS represents. ISPF searches the application-defined commands first, and then searches the ISPF system commands. It must locate the ALIAS definition before the aliased command.

In the following example, we’ve added the commands PREV and NEXT to the application command table. We want “PREV” and “NEXT” to be aliases for the ISPF system commands BACKWARD and FORWARD. Because the BACKWARD and FORWARD commands are provided by ISPF, we do not need to define them in the application command table. ISPF locates the aliases before the ISPF system commands they refer to.

Additionally, this example shows the CMDACT for the SEND command set to PASSTHRU, because we want the application program to process the SEND command.

```
<cmdtbl applid=brws>
  <cmd name=quit>quit
    <cmdact action='alias exit'>
  <cmd name=send>send
    <cmdact action=pass thru>
  <cmd name=prev>
    <cmdact action='alias backward'>
  <cmd name=next>
    <cmdact action='alias forward'>
</cmdtbl>
```

## Specifying Command Actions Dynamically

You can also specify a variable as the value for the ACTION attribute of the CMDACT tag. ISPF substitutes the value of the variable at run time when the command is processed. The run-time value of the variable must be one of the ISPF-supported command actions. You specify the variable using the % notation in the ACTION value.

In the following example, we specified the variable *scroll* as a command action for the SCROLL command. When the user issues the SCROLL command, ISPF obtains the value of the variable *scroll* from the variable pool to determine the action to be taken. The application can then control the direction of scrolling by setting the variable *scroll* to FORWARD or BACKWARD, or to NOP if no scrolling is possible.

```
<!doctype dm system>

<cmdtbl applid=abcd>
  <cmd name=scroll>scroll
    <cmdact action='%scroll'>
  :
</cmdtbl>
```

## Truncating Commands

Using the command facilities as we have discussed them so far in this chapter, the user must enter a full command name when typing a command in the command area. You can provide a shortcut for the user by defining *command truncations* for commands. The user can issue a truncated command in the command area by entering the minimum number of characters you specify for the command.

To specify truncation for a command, you code the T (truncation) tag within the *external-command-name* of the command.

For example, to specify “qu” as the minimum command for the QUIT command, you add the T tag to the *external-command-name*, like this:

```
<cmdtbl applid=brws>
  <cmd name=quit>qu<t>it
    <cmdact action='alias exit'>
  :
</cmdtbl>
```

The T tag follows the characters you specify as the minimum command.

With this truncation, the user can issue the QUIT command by typing the command in one of the following ways:

```
qu  
qui  
qui t
```

However, you should be careful to avoid adding truncations that duplicate other truncations in the command table. For example, these two truncations define minimum commands (“co”) that are identical:

```
<cmdtbl applid=brws>  
  <cmd name=comp>co<t>mpare  
    <cmdact action=passthru>  
  <cmd name=copy>co<t>py  
    <cmdact action=passthru>  
</cmdtbl >
```

The preceding definition would cause the conversion utility to issue a warning message.

To avoid this type of duplication, place the T tag appropriately in the CMD tag content. The above duplication can be avoided by coding the truncations as follows:

```
<cmdtbl applid=brws>  
  <cmd name=comp>com<t>pare  
    <cmdact action=passthru>  
  <cmd name=copy>cop<t>y  
    <cmdact action=passthru>  
</cmdtbl >
```





⋮  
</panel >

When the user presses the F2 key during the display of an application panel that refers to this key mapping list, ISPF processes the SEARCH command.

## ISPF Default Key List

ISPF provides a default key mapping list named ISPKYLST for application panels. If you do not specify a key mapping list to be associated with a panel (using the KEYLIST attribute of the PANEL or PANDEF tag), ISPF uses the keys defined for ISPKYLST to display in the function key area of the panel when it is displayed. See “PANEL (Panel)” on page 413 for information about coding the PANEL tag.

The key mappings for ISPKYLST are:

Key	Command
F1	HELP
F2	SPLIT
F3	EXIT
F9	SWAP
F12	CANCEL
F13	HELP
F14	SPLIT
F15	EXIT
F21	SWAP
F24	CANCEL

ISPF provides a default key mapping list named ISPHELP for help panels. If you do not specify a key mapping list to be associated with a panel (using the KEYLIST attribute of the HELP or HELPDEF tag), ISPF uses the keys defined for ISPHELP to display in the function key area of the panel when it is displayed. See “HELP (Help Panel)” on page 335 for information about coding the HELP tag and Table 4 on page 340 for key mappings of the ISPHELP keylist.

You can override the ISPF default key mapping list by specifying a KEYLIST attribute in the panel definition. All keys that you want to be active, including those for ISPF-provided commands, must be specified in the key mapping list referred to by the KEYLIST attribute.

## Displaying Keys

While all of the key assignments you define in a key mapping list are valid for the application panels that refer to the list, they only appear in the function key area (FKA) of the panel under the following conditions:

- You specify that the key is to be displayed by including FKA=YES in the KEYI tag, and
- The user has not turned off display of the function key area.

You use the FKA attribute of the KEYI tag to specify whether the key is to appear in the panel’s function key area. The default FKA value, NO, means that the key will not appear. You must specify FKA=YES for the key to be displayed in the function key area.

When function keys are displayed in the function key area, the key you assign is displayed followed by an equal sign and the FKA text defined for the KEYI tag.

## Defining Help for Key List

The conversion utility supports a keys help panel name on the KEYL tag. This allows a keys help panel to be associated with the key list. You can use the KEYLIST utility to add, change, or delete a keylist help panel name.

Alternatively, the application can provide the help panel name in the ZKEYHELP variable. However, the panel name specified as the keylist help panel either on the KEYL tag or by the KEYLIST utility overrides the panel name supplied by the ZKEYHELP variable.

In the following example, we want only the F2, F3, and F6 keys to appear in the panel function key area, with F2 mapped to the SEARCH command defined in the application command table, F3 mapped to the EXIT command, and F6 mapped to the KEYSHELP command. We also want F1 to be active to support the ISPF HELP command. No other function keys are to be active for this key mapping list. To obtain this result, we define the function key mapping list as follows:

```
<!doctype dm system>

<cmdtbl applid=abcd>
  <cmd name=search>Search
  <cmdact action=passthru>
</cmdtbl >
<keyl name=panl keys help=panl keyh>
  <keyi key=f1 cmd=help>
  <keyi key=f2 cmd=search fka=yes>Search
  <keyi key=f3 cmd=exit fka=yes>Exit
  <keyi key=f6 cmd=keyshelp fka=yes>Keyshelp
</keyl >

<panel name=panl01 keylist=panl keys>
:
:
</panel >
```

This is how the function key area appears when panel “panl01” is displayed:




Figure 84. Displayed Function Key Area



---

## Chapter 10. Using the Conversion Utility

The ISPF conversion utility is a tool that converts Dialog Tag Language (DTL) source files into ISPF panel language source format or executable preprocessed ISPF format. There are two methods of invoking the conversion utility: using the ISPF-supplied invocation panels, or using the conversion utility syntax. In either case, the conversion utility must be run under ISPF control. In this chapter, we explain both methods of calling the conversion utility.

---

### Using the ISPF-Supplied Invocation Panels

Type the following command on the command line to invoke the conversion utility and display the ISPF invocation panel:

```
ISPD TLC
```

#### Invocation Panel

The following panel appears:




Figure 85. Conversion Utility Invocation Panel (ISPCP01)

There are many options on this panel, so you will need to scroll forward several times to view them all.

You must specify:

- At least one file containing DTL source
- The panel output file
- The message output file

The language selection defaults to the current ISPF session language. The current selected language is displayed as an information field on the panel.

Select the national language you want by using the Language action bar pull-down to enter a number corresponding to the supported ISPF language. The language is used to provide formatting rules for tag text. See “Text Formatting” on page 13 for more information.

## Panel Input Fields

Additional information about the panel input fields follows:

### Member Name

If the member name is left blank or entered as a member pattern, a member list is displayed. You can select one or more members to be converted from the member list.

### DTL Source data set - n

You can specify up to three additional DTL source libraries on the invocation panel. See “Additional DTL Source Files” on page 175 for more information.

### Panel data set

If no panel output is required, you can specify NULLFILE or DUMMY in place of the panel output file name.

### Message data set

if no message output is required, you can specify NULLFILE or DUMMY in place of the message output file name.

### Log data set

The log file name is optional. If it is not specified and the messages are to be written to disk, log output is written to the ISPF log file. If the log file is a PDS, a member name must be provided. You may specify an asterisk to tell the conversion utility to use the input GML source file member name as the output log file member name. However, if the input GML member is in the special DTLLST file list format (discussed in “Conversion Utility General Information” on page 183) then a separate log file member is created for each source member converted.

### List data set

The list file name is optional. If it is not specified, list output is written to the ISPF list file. If the list file is a PDS, a member name must be provided. You may specify an asterisk to tell the conversion utility to use the input DTL source file member name as the output list file member name. However, if the input GML member is in the special DTLLST file list format (discussed in “Conversion Utility General Information” on page 183) then a separate list file member is created for each source member converted.

### SCRIPT data set

The SCRIPT file name is optional. If a SCRIPT output file is requested, it must be a PDS file. Member names for the SCRIPT file are the same as the panel file.

### Tables data set

The Tables file name is optional. If a tables file name is provided, it must be an 80 byte fixed length PDS file. When a tables file is provided, keylist and command table output is placed in this file.

### Keylist Application ID

The optional Keylist Application ID is used when the APPLID attribute is omitted on the HELP, PANEL, KEYL, or CMDTBL tags. This is the equivalent of the ID provided by the KEYAPPL option described in “Conversion Utility Syntax” on page 177.

### Conversion status message interval

When the conversion utility is running in interactive mode and the “Place ISPD TLC Messages in log file” option is selected and the “List Source Convert Messages” option is deselected, a status message containing the name of the current DTL source file member being converted is displayed in the long message area. This message provides a conversion status when you are converting multiple members using the DTLLST format member option. See page 186 for more information about the DTLLST syntax. The default message interval value is 1 which displays the message for each member processed. This value can be set to 0 to suppress the message (which is useful when running in GUI mode) or to a value that refreshes the message after a specified number of members have been converted.

### DISPLAY(W) option check interval

When the conversion utility is running in test mode and either the DISPLAY or DISPLAYW option is selected, the converted panel is displayed for visual verification. A panel is displayed periodically after the converted panel has been displayed to enable the user to control the DISPLAY or DISPLAYW function.

The “DISPLAY(W) option check interval” option on the invocation panel controls the frequency of the DISPLAY or DISPLAYW control function panel appearance. The default value is 1, so that the control function panel is displayed after each converted panel display. The control panel enables you to continue using the same display interval, cancel the DISPLAY or DISPLAYW option, or change the control panel display interval.

All files specified must be preallocated.

When the log or list file is a PDS file and the member name is not an asterisk, all of the conversion results are placed in the specified member. If the file name or member name is changed, the pending log or list information is written to the previously specified member and a new log or list is generated beginning with the next conversion. When the conversion utility ends, pending log and list files are written.

The log and list files can be either fixed or variable length, with or without printer control. When the file is allocated with print control specified, the conversion utility output begins in column 2; column 1 is blank. When print control is not specified, the conversion utility output begins in column 1.

## Panel Options

The conversion utility options are displayed either as a multi-choice selection list by scrolling the invocation panel, or in a series of multi-choice selection list panels with related options, through the Options pull-down on the action bar.

You select the options by entering a “/” in front of the option description. If you want to deselect an option, you must leave the selection choice field blank. These options are initially set to the default values described in “Conversion Utility Syntax” on page 177. The options and their valid values are equivalent to conversion utility syntax in the following manner. Note that *b* represents a blank.

Options	Valid Values
Replace Panel/Message/SCRIPT/Keylist/Command Members	/ is equivalent to REPLACE, the default. <i>b</i> is equivalent to NOREPLACE.

Options	Valid Values
Preprocess Panel Output	<i>/</i> is equivalent to PREP, the default. <i>b</i> is equivalent to NOPREP.
Place ISPD TLC Messages in log file	<i>b</i> is equivalent to SCREEN, the default. <i>/</i> is equivalent to DISK.
Suppress Messages (ISPF extensions)	<i>b</i> is equivalent to NOMSGSUPP, the default. <i>/</i> is equivalent to MSGSUPP.
Suppress Messages (CUA exceptions)	<i>b</i> is equivalent to NOCUASUPP, the default. <i>/</i> is equivalent to CUASUPP.
Use CUA Panel Attributes	<i>/</i> is equivalent to CUAATTR, the default. <i>b</i> is equivalent to NOCUAATTR.
Generate Statistics on Panel/Message/Script Members	<i>/</i> is equivalent to STATS, the default. <i>b</i> is equivalent to NOSTATS.
Generate List file	<i>b</i> is equivalent to NOLISTING, the default. <i>/</i> is equivalent to LISTING.
Generate List file with substitution	<i>b</i> is equivalent to NOFORMAT, the default. <i>/</i> is equivalent to FORMAT.
Generate SCRIPT file	<i>b</i> is equivalent to NOSCRIPT, the default. <i>/</i> is equivalent to SCRIPT.
Replace Log File Members	<i>/</i> is equivalent to LOGREPL, the default. <i>b</i> is equivalent to NOLOGREPL.
Replace List File Members	<i>/</i> is equivalent to LISTREPL, the default. <i>b</i> is equivalent to NOLISTREPL.
List Source Convert Msgs	<i>b</i> is equivalent to NOLSTVIEW, the default. <i>/</i> is equivalent to LSTVIEW.
Use Expanded Message Format	<i>b</i> is equivalent to NOMSGEXPAND, the default. <i>/</i> is equivalent to MSGEXPAND.
Allow DBCS	<i>b</i> is equivalent to NODBCS, the default. <i>/</i> is equivalent to DBCS.
Specify KANA	<i>/</i> is equivalent to KANA.
Specify NOKANA	<i>/</i> is equivalent to NOKANA.
Create panels with Action bars	<i>/</i> is equivalent to ACTBAR, the default. <i>b</i> is equivalent to NOACTBAR.
Create panels with GUI mode display controls	<i>/</i> is equivalent to GUI, the default. <i>b</i> is equivalent to NOGUI.
Add ISPD TLC version/timestamp to panel	<i>/</i> is equivalent to VERSION, the default. <i>b</i> is equivalent to NOVERSION.
Combine scrollable areas into panel body	<i>b</i> is equivalent to NOMERGESAREA, the default. <i>/</i> is equivalent to MERGESAREA.
Display converted panels (*)	<i>b</i> is equivalent to NODISPLAY, the default. <i>/</i> is equivalent to DISPLAY.
Display converted panels in a window (*)	<i>b</i> is equivalent to NODISPLAYW, the default. <i>/</i> is equivalent to DISPLAYW.
Bypass data set name validation (after first cycle).	<i>b</i> is equivalent to DSNCHK, the default. <i>/</i> is equivalent to NODSNCHK.
Enable graphic character display	<i>/</i> is equivalent to GRAPHIC, the default. <i>b</i> is equivalent to NOGRAPHIC.

Options	Valid Values
Use full names in place of Z variables	<i>b</i> is equivalent to ZVARS, the default. / is equivalent to NOZVARS.
Align DBCS prompt text with entry field	<i>b</i> is equivalent to NODBALIGN, the default. / is equivalent to DBALIGN.
Preserve leading blanks when <i>space</i> is not specified	<i>b</i> is equivalent to NOPLEB, the default. / is equivalent to PLEB.
Process multiple line comment blocks	<i>b</i> is equivalent to NOMCOMMENT, the default. / is equivalent to MCOMMENT.
Display additional DTL source data set list	<i>b</i> —second input panel is not displayed. / —second input panel is displayed.
(*): If you specify DISPLAY or DISPLAYW, ISPDTLC must be run in test mode (Option 7) to force display processing to use the current generated panel. An error message is issued if ISPDTLC is not being run in test mode and either option is specified.	

All of the entries from the panel (or panels) are saved in the user's profile.

### Additional DTL Source Files

A second input panel is displayed for entry of up to twelve additional DTL source file data set names when any of the following occurs:

- you place the cursor on the point-and-shoot panel phrase "DTL input files 5-16" and press Enter.
- the "Display additional DTL source data set list" option is selected from either the scrollable area of the main panel or the Miscellaneous section of the Options action bar pull-down
- XDTL is entered on the command line
- Option 7 is selected from the Commands action bar pull-down



## Conversion Utility Syntax


You can also invoke the conversion utility using the syntax discussed in this section. This feature provides compatibility with previous ISPD TLC releases and allows you to issue multiple calls from a user-specified EXEC file. To read the conversion utility syntax, see Chapter 11, “How to Read the Syntax Diagrams,” on page 193 for more information.

You can view the allowable syntax and a description of the options by entering the following command on the ISPF command line:

```
ISPD TLC ?
```

This command causes the general help panel to be displayed. The first line of information contains the ISPD TLC version, APAR, and PTF numbers.

This diagram shows the conversion utility syntax:



As denoted in the preceding diagram, when you specify options, a left parenthesis “(” is required before the first option. If you specify mutually exclusive options such as SCREEN and DISK, the conversion utility issues an error message and stops processing.

The syntax description follows:

**source-filespec**

Specify the *source-filespec* as a member of a partitioned data set (PDS) that contains the DTL source to be converted to ISPF dialog elements. The first-level qualifier is the “user ID” and the second-level qualifier is “GML” for the input data set name unless the PROFILE option is specified to override the default.

**Note:** The conversion utility output is stored as commands, keylists, messages and panels. A single source file might result in any or all of these objects. The source file might contain multiple command tables, keylists, message members or panels. The names for the output objects are provided by the CMDTBL, KEYL, MSGMBR, PANEL, and HELP tags. See the descriptions of these tags for additional information.

**REPLACE | NOREPLACE**

Indicates whether members generated by the conversion utility will replace existing members of the same name. If you specify NOREPLACE, the conversion utility issues a warning message for each existing member with the same name, but does not overwrite the existing member. If you specify REPLACE, the conversion utility overwrites any existing member with the same name. REPLACE and NOREPLACE affect keylists, commands, messages, panels, and SCRIPT files.

**SCREEN | DISK**

Indicates where to send information, warning, and error messages that occur while running the conversion utility. If you specify SCREEN (the default), conversion messages are sent to the display screen. If you specify DISK, conversion messages are sent to the designated log file.

**Note:** If your messages are not being written to the ISPF log, the specified conversion utility log file must be preallocated. If your messages are being written to the ISPF log, the ISPF Settings option must specify that an ISPF log is to be created.

Running the conversion utility with the DISK option causes additional messages to be appended to the existing sequential ISPD TLC log file or the ISPF log. When using the conversion utility log file, a separator record indicating the date and time of the execution is written to the log file before any messages.

Messages are written to the screen automatically when:

- The conversion utility detects errors during initialization.
- System I/O errors occur.

**DBCS | NODBCS**

Indicates whether DBCS validation is performed on tag text following the tag suffix “>”. Errors found during DBCS validation cause the conversion utility to issue error or warning messages. DBCS shift-out and shift-in characters are considered part of the text, thereby contributing to the length of the text.

**Attention:** DBCS strings cannot span records. That is, DBCS shift-out and shift-in characters (shift-in characters end the DBCS string) must be on the same record. The conversion utility ends with a severe error for incorrectly formed DBCS strings. If DBCS is specified and no language is specified, the default language is Japanese.

## **KANA | NOKANA**

Indicates whether the KANA keyword will be added to the )BODY statement on panels and the message ID line of messages. There is no default. If KANA is specified and no language is specified, the default language is Japanese. Refer to the *ISPF User's Guide* for more information.

## **KEYLAPPL=xxxx**

The KEYLAPPL=xxxx option, where "xxxx" is equal to the 1–4 character application ID, must be specified when the user includes a key list or lists in the DTL source and the APPLID attribute is omitted on the KEYL tag. The application ID is used by the conversion utility to write to the correct key list file.

**Note:** You cannot use "ISP" as an application ID, because the conversion utility is running as an ISP application.  
Refer to *ISPF User's Guide* for restrictions on updating key lists.

## **PANEL | NOPANEL**

The PANEL keyword forces the conversion utility to display the invocation panel even if a *source-filespec* has been entered. The PANEL keyword is disregarded when the conversion utility is running in a batch job.

## **MSGSUPP | NOMSGSUPP**

The MSGSUPP keyword causes the conversion utility to suppress warning messages concerning panel formatting.

## **CUASUPP | NOCUASUPP**

The CUASUPP keyword causes the conversion utility to suppress warning messages concerning CUA Architecture non-compliance.

## **PREP | NOPREP**

The NOPREP keyword causes the preprocessing of the output panel to be bypassed. Panel output is stored in ISPF panel format.

## **CUAATTR | NOCUAATTR**

The NOCUAATTR keyword forces the conversion utility to create panels with attribute definitions compatible with ISPF Version 3.1 and Version 3.2. CUAATTR causes panels to be created using CUA attribute types as defined in the *ISPF Dialog Developer's Guide and Reference*.

**Note:** If you specify NOCUAATTR, the conversion utility will issue a message and change the default GRAPHIC option to NOGRAPHIC because GRAPHIC support is implemented only for CUA attributes.

## **LSTVIEW | NOLSTVIEW**

The LSTVIEW keyword causes the conversion utility to display the "converting source file" message in line mode when the user has routed the log file messages to DISK. NOLSTVIEW causes the "converting source file" message to be displayed as a long message in full screen mode. The NOLSTVIEW keyword is disregarded when the conversion utility is running in a batch job; the "converting source file" message is written to file SYSTSPRT.

## **STATS | NOSTATS**

The NOSTATS keyword causes the conversion utility to bypass the creation of member statistics on created panels and messages. STATS and NOSTATS affect messages, panels, and SCRIPT files.

## **SCRIPT | NOSCRIPT**

The SCRIPT keyword causes the conversion utility to create a panel image template as a member of a file allocated to DTLSCR. The panel image template

has BookMaster tags included so that it may be incorporated into documentation files. Input and output fields in the panel image are shown as underscores. Run-time substitution variables are shown as "&varname". Editing will be required to supply appropriate information for input and output fields and "&varname" values.

**Note:** The specified conversion utility SCRIPT output file must be preallocated.

#### **LISTING | NOLISTING**

The LISTING keyword causes the conversion utility to create a list file of the processed source GML records. This file is allocated to DTLLIST or if no file name is provided to the conversion utility, the list is added to the standard ISPF list data set. The file you provide can be in either sequential or partitioned format.

**Note:** If your messages are not being written to the ISPF list file, the specified conversion utility list file must be preallocated.

Indentation of nested tags (to a limit of 30 columns) is provided for readability. The listing is limited to an 80-column format. Tag contents that would extend beyond the right column are flowed to multiple lines.

The formatted listing is unchanged from the original DTL source file except for indentation processing.

#### **FORMAT | NOFORMAT**

The FORMAT keyword causes the conversion utility to create a list file of the source GML records after entity substitution is performed. (The FORMAT keyword implies the LISTING keyword.) The number at the left side of the list indicates the file nest level. If the LISTING keyword is specified in combination with the NOFORMAT keyword, all substitution is bypassed and the listing can be used as a formatted input GML file.

#### **MSGEXPAND | NOMSGEXPAND**

The MSGEXPAND keyword causes the conversion utility to expand the warning and error messages to include an indicator of the major type of tag in process (PANEL, HELP, KEYL, MSGMBR, CMDTBL) along with the object name.

#### **LOGREPL | NOLOGREPL**

Indicates whether members generated by the conversion utility will replace existing log file PDS members of the same name. If you specify NOLOGREPL, the conversion utility issues a warning message for each existing member with the same name but will not overwrite the existing member.

#### **LISTREPL | NOLISTREPL**

Indicates whether members generated by the conversion utility will replace existing list file PDS members of the same name. If you specify NOLISTREPL, the conversion utility issues a warning message for each existing member with the same name but will not overwrite the existing member.

#### **ACTBAR | NOACTBAR**

Indicates whether the ISPF panel statements for action bars will be added to the generated panel. If you specify NOACTBAR, the panel sections for )ABC, )ABCINIT, and )ABCPROC and the action bar lines from the panel body are not added to the output panel. (The DTL source for action bar creation is syntax-checked in all cases.)

If a PANEL tag includes the keyword ACTBAR, this option is ignored for that panel.

#### **GUI | NOGUI**

The NOGUI keyword causes the GUI display mode panel keywords for mnemonics and check boxes to be removed from the generated panel.

If you specify MNEMGEN=YES on the AB tag or CHKBOX=YES on the SELFLD tag, this option is ignored for the specified tag. This option can be overridden by specifying the TYPE attribute on the PANEL tag.

#### **VERSION | NOVERSION**

Indicates whether the ISPDTLC version number, maintenance level, and member creation date and time are added as comments following the )END panel statement and the last message of a message member. In addition, VERSION causes the conversion language (ENGLISH, GERMAN, JAPANESE, and so on), Panel ID, and ISPF version to be added to the )ATTR panel statement line as a comment. If you specify NOVERSION, the comments are not added to the generated panel or message.

**Note:** If the PREP conversion option has been specified, the comments will not be part of the final panel because they will not be processed by the ISPPREP utility.

#### **NOMERGESAREA | MERGESAREA**

Indicates whether scrollable areas will be merged into panel body sections. Merge occurs only when the entire scrollable area can be contained within the panel body, allowing for the function key area. This option can be overridden by specifying the MERGESAREA attribute on the HELP or PANEL tag.

#### **NODISPLAY | DISPLAY**

Indicates whether the converted panel will be displayed by the conversion utility immediately after the panel is created. The display will be in full screen format. The DISPLAY keyword is disregarded when the conversion utility is running in a batch job.

**Note:** If you specify DISPLAY, ISPDTLC must be run in test mode (Option 7) to force display processing to use the current generated panel. An error message is issued if ISPDTLC is not being run in test mode and this option is specified.

DISPLAY causes each converted panel to be displayed until the user enters DISPLAY OFF on the command line of a displayed panel or selects option 2 from the display control panel. The control panel is displayed periodically, according to the interval specified in the "DISPLAY(W) option check interval" field on the invocation panel, or from the Miscellaneous choice on the Options action bar.

#### **NODISPLAYW | DISPLAYW**

Indicates whether the converted panel will be displayed by the conversion utility immediately after the panel is created. The display will be within a window. The DISPLAYW keyword is disregarded when the conversion utility is running in a batch job.

**Note:** If you specify DISPLAYW, ISPDTLC must be run in test mode (Option 7) to force display processing to use the current generated panel. An error message is issued if ISPDTLC is not being run in test mode and this option is specified.

DISPLAYW causes each converted panel to be displayed until the user enters DISPLAY OFF on the command line of a displayed panel or selects option 2 from the display control panel. The control panel is displayed periodically, according to the interval specified in the "DISPLAY(W) option check interval" field on the invocation panel, or from the Miscellaneous choice on the Options action bar.

#### **DSNCHK | NODSNCHK**

Indicates whether file validation will be performed on the files specified on the interactive panel after the first conversion cycle has been completed. If you specify NODSNCHK and any specified file is unavailable, the conversion will fail when the conversion utility attempts to use the file. The NODSNCHK keyword is disregarded when the conversion utility is running in a batch job.

#### **GRAPHIC | NOGRAPHIC**

Indicates, for host display only, whether the action bar separator line and visible horizontal divider lines will display as dashed lines or as solid lines. The GRAPHIC option can be overridden by the tag definition that generates the line. See tag attribute descriptions for

- "AB (Action Bar)" on page 206,
- "AREA (Area)" on page 217,
- "CHDIV (Choice Divider)" on page 236,
- "DA (Dynamic Area)" on page 280,
- "DIVIDER (Area Divider)" on page 289,
- "GA (Graphic Area)" on page 327,
- "GRPHDR (Group Header)" on page 332,
- "LSTFLD (List Field)" on page 377, and
- "LSTGRP (List Group)" on page 382

for information about the creation of action bar separator and various types of visible divider lines. (In GUI mode, the action bar separator always displays as a solid line, and divider lines always display as dashed lines.) If you specify NOGRAPHIC, the action bar separator line and visible divider lines will be created as dashed lines.

**Note:** If you specify NOCUAATTR, the conversion utility will issue a message and change the default GRAPHIC option to NOGRAPHIC because GRAPHIC support is implemented only for CUA attributes.

#### **ZVARS | NOZVARS**

Indicates whether variable names will be formatted as Z variables. If you specify NOZVARS, the variable name will be used in panel )BODY or )AREA formatting unless the variable name is longer than the defined field width.

#### **DBALIGN | NODBALIGN**

For DBCS language conversions only. Indicates whether fields with PMTLOC=ABOVE will be aligned so that the first position of the prompt text is formatted above the first position of the field.

#### **PLEB | NOPLEB**

Indicates whether leading blanks in ENTITY text strings are processed. This option is effective only for ENTITY definitions that do not specify the "space" keyword.

#### **MCOMMENT | NOMCOMMENT**

Indicates whether multiple line comment blocks, starting with <! -- or <: -- and ending with the first --> found are valid. Comment blocks can include DTL tags.

### **NOV3PADC | V3PADC**

Indicates whether ISPD TLC Version 3 padding is added to global definitions for input fields in the )ATTR panel section. When ISPD TLC is invoked with the V3PADC option, the ISPF keyword PADC('\_) is added to input attribute definitions if there is no PAD or PADC attribute specified on the PANEL tag.

### **PROFILE=*data-set-name* | PROFDDN=*ddname* | PROFDDN=\***

The PROFILE or PROFDDN option provides access to the data set name that contains the conversion utility defined DD names and associated PDS/sequential file names to be used by the conversion utility during I/O. A sample profile member ISPD TLP is shipped in the ISPSLIB skeleton library.

The *data-set-name* value must be a fully qualified data set name that specifies either a sequential or a partitioned data set. If the profile entry is part of a partitioned dataset, then the member name must be included in the data-set-name specification.

The *ddname* value specifies a ddname allocated to a profile data set.

The "\*" value specifies that the ddnames used in the conversion will be found as preallocated files. See page 188 for the ddnames used by ISPD TLC.

The profile data set and all data sets defined within the profile must be preallocated.

### **national-language**

Specifies the language rules to be used for formatting the tag text. Supported language keywords are:

CHI NESES	ENGLI SH	I TALI AN	PORTUGUE	UPPERENG
CHI NESET	FRENCH	JAPANESE	SGERMAN	
DANI SH	GERMAN	KOREAN	SPANI SH	

**Note:** ISPF must have been installed to support the language requested by the conversion utility.

---

## **Conversion Utility General Information**

The output panel library can be defined as either fixed length or variable length. A fixed length record library must have a record length of 80, 132, or 160 bytes. Record lengths for variable length record libraries must be increased by 4. Variable length libraries defined with a record length other than 84, 136, or 164 are treated as the next smaller standard size. Thus, a variable length file of 255 bytes is treated as 164, and a variable length file of 100 bytes is treated as 84.

The NOPREP option directs the conversion utility to write the panels being processed directly to the specified panel output file in the ISPF source format. The overall width for the created panels is limited by the record length of the designated file. Thus, if you have specified a panel library with a fixed length of 80 bytes (or a variable length of 84 bytes), the maximum panel width allowed on the PANEL tag will be 80.

The PREP (default) option causes the creation of a temporary panel library to receive the ISPF source panel format file. The temporary library is created with a record length of 160 bytes. Multiple panels created in PREP mode are stored in the temporary library and converted through one call to ISPPREP. When all of the panels are converted, the temporary library is deleted. ISPPREP is called by the conversion utility when you do the following:

- Change the name of the output panel library on the ISPD TLC invocation panel and then convert another panel.

- Deselect the Preprocess Panel Output option on the ISPD TLC invocation panel and then convert another panel.
- Change the Generate Statistics on Panel/Message/Script Members option on the ISPD TLC invocation panel and then convert another panel.
- Enter “PREP” on the command line of the ISPD TLC invocation panel or select “PREP” from the Commands action bar pull-down.
- Exit from the conversion utility.

ISPPREP is also called when:

- The number of extents of the temporary library exceeds 5.
- The number of members written to the temporary library exceeds 50.

ISPPREP output for panels longer than 80 bytes can be stored in a panel library with a fixed record length of 80 (or a variable record length of 84). Thus, you can create larger than standard panels in PREP mode while directing the final panel output to a library defined with a standard length. It is the developer’s responsibility to ensure that the WIDTH specified on the PANEL tag is appropriate for the device intended to display the panel.

When the log or list files are specified as members of a partitioned data set, and the log or list file member name is specified as an asterisk (\*) the member is written before the invocation panel is redisplayed. Otherwise, the log or list file is stored in memory (and added to for additional DTL source conversions) until one of the following occurs:

- The output log or list data set name is changed and another conversion is performed.
- The member name of the log or list file is changed on the invocation panel and another conversion is performed.
- The input DTL source member name is changed when the log or list member name is specified as an asterisk.
- You enter on the command line or select from the Commands action bar pull-down:
 

<b>SAVELOG</b>	to save the log file
<b>SAVELIST</b>	to save the list file
<b>SAVEALL</b>	to save both log and list files.
- You exit the conversion utility.

When the log file is specified as a partitioned data set, messages issued when the conversion utility ends are directed to the screen.

When the CANCEL command is entered, ISPD TLC displays a cancellation confirmation panel. This panel provides options for disposition of pending log and list file members and for any panels to be processed by ISPPREP. An option is also provided to ignore the CANCEL command and resume ISPD TLC processing.




Figure 87. ISPF Dialog Tag Language Conversion Utility - Confirm Cancel

The panel appears with option 1 preselected. You may choose another option to save log and list files only, preprocess pending panels only, save log and list files and preprocess pending panels, or resume processing.

When you enter the SUBMIT command, ISPD TLC creates and submits a batch job, using the file names and options specified on the interactive panel. After the job is submitted, the interactive panel is redisplayed. The batch JCL file is built using the ISPF skeleton ISPDTLB.

You can also run ISPD TLC from ISPF options 4 and 5 and from the workplace member list.

**Note:** From the workplace member list, enter "T" (TSO) in front of the member name to be processed. On the TSO pop-up panel enter

"ISPD TLC / (PANEL RETURN"

to run a foreground conversion or

"ISPD TLC / (PANEL SUBMIT"

to submit a batch job.

After you complete the required ISPD TLC invocation panel fields and press Enter, the conversion runs or the job is submitted, and control is returned to the previous option.

Extremely large DTL input source files (source files that contain multiple panel, message, key list, and application command table definitions) might cause memory capacity to be exceeded. Should this occur, split the DTL input source file into multiple files with fewer panels, message members, key lists, or command table definitions or reduce the record length of the input source file.

When ISPD TLC is invoked recursively, that is, more than 1 time from the same ISPF screen, the following panel is displayed.




Figure 88. ISPF Dialog Tag Language Conversion Utility - Recursive invoke

The panel appears with option 1 preselected. If you select option 2, the new invocation will be processed. Because of possible region size limitations, results are not predictable.

The recursive invocation check is based on the setting of a profile variable that is unique for each active screen. If the recursive check panel appears following an abend, the profile variable was not properly reset when the abend occurred. In this case, select option 2 to allow ISPD TLC to continue.

If the conversion utility is called without a *source-filespec* or if the PANEL option has been specified, the invocation panel is displayed. If other options have been specified, they are merged with the options from the profile before the display. The PROFILE option is disregarded when the invocation panel is displayed.

The *source-filespec* can be a special file which is a list of other files to be converted. When you use this option, you can convert multiple panels with a single call to the conversion utility. The format of the file list is :

```
DTLLST source-fi lespec 1
DTLLST source-fi lespec 2
:
```

The format of *source-filespec* is the same as any other call to the conversion utility. Duplicate *source-filespec* names within DTLLST are ignored.

The *national-language* selection UPPERENG causes the conversion utility to use the uppercase version of the ENGLISH program literals. In addition, the tag text for all tags except <SOURCE> is translated to uppercase during the conversion process.

The *national-language* selection SGERMAN causes the conversion utility to use a special German-to-Swiss German conversion routine to create Swiss German panels from either German or Swiss German DTL source files.

---

## ISPF Conversion Utility Messages

During processing, the conversion utility can issue information, warning, and error messages. For unsupported DTL tags and attributes that generate warning messages, the conversion utility either ignores the tag or attribute, or sets attribute values to the conversion utility defaults. If the conversion causes error messages,

the conversion utility will not generate the ISPF file (key list, panel, application command table, or message member) that would have been created had the error not occurred.

In the message listing, the line numbers displayed in the messages might not always match the line numbers of the source file that caused the message. This occurs because the conversion utility must sometimes continue to read the source file until it encounters an end tag or a new tag before issuing a message. You should be able to determine which source line created the message by examining the DTL source file.

There are two options required to suppress all noncritical messages.

- The MSGSUPP option is used to suppress messages related to ISPD TLC formatting.
- The CUASUPP option is used to suppress messages related to CUA architecture deviations allowed by ISPD TLC. Examples include nonstandard use of F1/F13, F3/F15, and F12/F24 keylist commands, and the use of the SMSG attribute on the MSG tag to create a short message.

When each DTL source file conversion is completed, the conversion utility issues a message listing the number of warning and error messages generated. If the MSGSUPP or CUASUPP option(s) have been specified, an additional message is issued with the total number of messages suppressed.

When the conversion utility is finished, it issues a message listing the total number of warning and error messages generated. If the MSGSUPP or CUASUPP option(s) have been specified, a message is issued with the total number of messages suppressed. The end of job messages listing the total number of messages are placed in the ISPF log file, if the log file is available; otherwise the overall totals are written to the terminal.

## Return Codes

The following list of return codes explains the results of the conversion invocation.

- |    |  |
|----|--|
| 0  | No warnings, errors, or severe errors                  |
| 1  | All messages were suppressed.                          |
| 4  | CANCEL command ended ISPD TLC                          |
| 8  | Only warnings were found                               |
| 16 | At least one DTL conversion had at least one error     |
| 20 | At least one DTL conversion ended with a severe error. |

For multiple conversions, the highest return code is used.

## Conversion Results

The results of the conversion are placed in the shared pool.

- The variable ZDTLRC contains the return code.
- The variable ZDTLNWRN contains the number of warning messages.
- The variable ZDTLNERR contains the number of error messages.
- The variable ZDTLNSUP contains the number of suppressed messages.

---

## Conversion Utility File Names

The conversion utility is shipped as a REXX exec on the ISPF product tape.

The ISPD TLC exec can reside in a CLIST data set allocated to SYSPROC or in an EXEC data set allocated to SYSEXEC. For more information about the use of REXX execs on MVS, refer to the *TSO/E Version 2 REXX User's Guide*.

**Additional Requirements:**

- All data sets must be allocated before running the conversion utility. In addition, the conversion utility uses ISPF services to produce command table and key list output, which means that a partitioned data set must be allocated to ISPTABL. Refer to the section on allocating ISPF libraries in the *ISPF User's Guide* for more information.
- To allow the user to specify the source and destination data sets when using the conversion utility syntax, seven DD names have been reserved in an allocation profile with associated data set names to be provided by the user.

**Note:** ISPD TLC profiles from previous releases can be used without change. However, a warning message is issued if the DTLMIN or DTLNLS DD name records are encountered.

- A sample profile member ISPD TLP is shipped in the ISPSLIB skeleton library. You can modify the data set names for installation or user use. DTL format comments (<!--comment text--> or (<:--comment text-->) can be used in the profile data set or member. Do not modify the DDNAMEs in the following table (column one). A sample user updated profile member follows:

DDNAME	Data Set
DTLGML	any.GML.input
DTLPAN	your.panel.output
DTLMSG	your.msg.output
DTLLOG <sup>6</sup>	your.log.output
DTLLIST <sup>6</sup>	your.list.output
DTLSCR	your.script.output
DTLTAB	your.table.output

DTLGML is the input file to the conversion utility. The last 6 files are for output and are usually the user's own data sets.

- For compatibility with previous ISPD TLC releases, the user can provide the allocation profile name on invocation:

```
ISPD TLC source-file spec (disk PROFILE=User.profile)
```

The data set name following the PROFILE keyword must be a fully-qualified data set name. When specifying the data set name, do not include quotes.

The profile data-set-name can specify either a sequential or a partitioned data set. If the profile entry is part of a partitioned dataset, then the member name must be included in the data-set-name specification. The profile data set and all data sets defined within the profile must be preallocated.

An example of the default data set names used for the conversion utility is shown in the following table. USERID is the user's TSO prefix.

---

6. The sequential data set name associated with the DTLLOG and DTLLIST ddnames should have the same characteristics and attributes as the LOG and LIST data sets for ISPF.

DDNAME	Data Set	Type	Description
DTLGML	userid.GML	PDS	The DTL source PDS where GML members reside.
DTLPAN	userid.PANELS or NULLFILE or DUMMY	PDS	PDS for panel member output. May be specified as NULLFILE or DUMMY for cases where no panel output is required.
DTLMSG	userid.MSGS or NULLFILE or DUMMY	PDS	PDS for message member output. May be specified as NULLFILE or DUMMY for cases where no message output is required.
DTLLOG	userid.ISPDTLC.LOG userid.LOGLIB(logmem)	SEQ or PDS	Optional. User's log data set for conversion utility messages. If not specified, log messages are written to the standard ISPF log data set. If file is a PDS, member name must be included in the data set name specification.
DTLLIST	userid.ISPDTLC.LIST userid.LISTLIB(listmem)	SEQ or PDS	Optional. User's list data set for conversion utility messages. If not specified, list messages are written to the standard ISPF list data set. If file is a PDS, member name must be included in the data set name specification.
DTLSCR	userid.SCRIPT	PDS	Optional. PDS for panel member documentation output. The DTLSCR data set is required only if the SCRIPT option is specified.
DTLTAB	userid.TABLES	PDS	Optional. PDS for keylist and command table output. If specified, a LIBDEF is performed for ISPTLIB and ISPTABL and the keylist and command table output is written to the data set.

The profile can contain multiple entries for each DD name. For output files, the first valid data set name in the profile is used. For the input GML file, each data set is checked in the order they are found in the profile for the member name specified. The first match by member name is used as the file to be converted.

When the data set associated with either the DTLLOG or DTLLIST ddname in the profile is a PDS, the member name may be a single asterisk. When the asterisk notation is present, the conversion utility uses the same name for the log or list file as the source GML member name.



---

## Part 2. Dialog Tag Language (DTL) Reference

This section contains the following chapters:

**Chapter 11, “How to Read the Syntax Diagrams”**

This chapter describes the elements that make up a syntax diagram.

**Chapter 12, “Markup Declarations and DTL Macro Reference”**

This chapter contains a reference listing for each DTL markup declaration.

**Chapter 13, “Tag Reference”**

This chapter contains a reference listing for each DTL tag.

Each reference listing in this section contains a syntax diagram and attribute definition list, as well as a description and examples of usage.



## Chapter 11. How to Read the Syntax Diagrams

Throughout this document, syntax is described using the structure defined below.

- Read the syntax diagrams from left to right, from top to bottom, following the path of the line.

### Symbol

#### Description

- ▶— indicates the beginning of a statement.
- ▶ indicates that the statement syntax is continued on the next line.
- ▶— indicates that a statement is continued from the previous line.
- ▶ indicates the end of a statement.

Diagrams of syntactical units other than complete statements start with the symbol and end with the symbol.

- Required items appear on the horizontal line (the main path).

—STATEMENT—requi red-i tem—

- Optional items appear below the main path.

—STATEMENT—  
└ optional -i tem ┘

- Items positioned above the syntax diagram line are default parameters.

—STATEMENT—  
└ default -i tem1 ┘

- If you can choose from two or more items, these items appear vertically, in a stack.

If you *must* choose an item in the stack, one of the required items appears on the main path.

—STATEMENT—  
└ requi red-choi ce1 ┘  
└ requi red-choi ce2 ┘

If a default is also available, it appears above the main line.

—STATEMENT—  
└ default -choi ce ┘  
└ requi red-choi ce1 ┘  
└ requi red-choi ce2 ┘

If choosing one of the items is optional, the entire stack appears below the main path.

—STATEMENT—  
└ opti onal -choi ce1 ┘  
└ opti onal -choi ce2 ┘

- An arrow returning to the left above the item indicates an item that you can repeat. Required items appear on the main line and optional items appear below the main line.



A repeat arrow indicates that you can make more than one choice from the grouped items, or repeat a single item.

- Keywords appear in uppercase (for example, PARM1). However, they can be uppercase or lowercase when they are entered. They must be spelled exactly as shown. Variables and acceptable values appear in all lowercase letters (for example, parm $x$ ). They represent names or values that you supply. Keywords and keywords followed by parameters (for example, MSG=message-i d) can be coded in any order.
- If punctuation marks, parentheses, arithmetic operators, or other symbols are shown, you must enter them as part of the syntax.

---

## Chapter 12. Markup Declarations and DTL Macro Reference

This chapter provides you with a detailed look at the following topics:

- Document-type declaration
- Entity declarations
- Sample Entity definitions
- DTL macros

---

### Document-Type Declaration

The document-type declaration (DOCTYPE) identifies the source file document type and the rules the source file must follow.

**DOCTYPE** Indicates that this is a document-type declaration.

**DM** Indicates that this is a DTL source file defining dialog elements.

**SYSTEM** Indicates that the rules for the DOCTYPE are contained in an external file.

[ | ( Indicates the beginning of the declaration subset. Either the left bracket or the open parenthesis can be used to begin the declaration subset. The declaration subset can contain entity declarations and parameter entity references. If the left bracket is coded, it must be the hex value 'AD'.

#### entity-declarations

The entity declarations you define for the source file must be coded within the declaration subset. "Entity Declarations" on page 196 contains a complete description of entity declarations.

] | ) Indicates the end of the declaration subset. Either the right bracket or the close parenthesis can be used to end the declaration subset. If the right bracket is coded, it must be the hex value 'BD'.

### Description

A document-type declaration identifies the source file document type and rules the source file must follow.

The DOCTYPE declaration must appear in a DTL source file before any tag markup, although it can be preceded by comments. Files that are embedded in a source file intended for compilation cannot contain a DOCTYPE declaration.

### Example

The DOCTYPE statement declares the source file as a DM type file.

```
<!doctype dm system>
<varclass name=varc type=' char 10' >
<varlist>
  <vardcl name=vard varclass=varc>
</varlist>
```


## Doctype

```
<panel name=panel >  
:  
:
```

---

## Entity Declarations

Entities are symbolic names that are used to insert text into a file.



- ENTITY** Indicates this is an entity declaration.
- %** Indicates a parameter entity declaration, which must be followed by at least one space.
- entity-name** The name of the entity. It must follow these rules:
- Length
    - 1–8 for file embed entity names
    - 1–8 for parameter entity names
    - 1–17 for other entity names
  - The first character must be A–Z, a–z, @, #, or \$.
  - Remaining characters, if any, can be A–Z, a–z, @, #, \$, or 0–9. When an entity name is more than 8 bytes in length, one or more of the remaining characters must be an underscore.
  - Entity names are case-sensitive.
  - The entity name for a parameter entity can be specified as a variable name (that is, `%&varname;`). The resolved name must follow the parameter entity naming rules.
- CDATA** Indicates that any delimiter characters in *entity-text* will not be interpreted as delimiters. This allows you to define entities with tags in *entity-text* that will not be interpreted as tags.
- For example the entity-text "`<panel>`" is not interpreted as the PANEL tag if the CDATA keyword is used.
- The effect of CDATA is to delay substitution of the variable until all other text manipulation is completed. For example, you should use CDATA to specify an *entity-text* string of blanks as normal text processing removes leading and trailing blanks from text strings.
- Note:** CDATA cannot be used with parameter entities.
- SPACE** Indicates that *entity-text* which spans multiple DTL source file records will be formatted like the `<p>` tag. (Leading and trailing blanks on *entity-text* lines will be compressed to a single blank character.) In addition, multiple blanks between words of *entity-text* will be compressed to a single blank character.
- REPLACE** Indicates that the current *entity-text* is to replace any previous definition of the same entity name.
- COPIES(n)** Indicates that the *entity-text* is to be expanded by repeating the provided text *n* times. For example, including `COPIES(5)` as a keyword with the text specified as `"*"` causes the entity text to be processed as `"*****"`.

<b>X2C</b>	Indicates that the specified hex format <i>entity-text</i> is to be converted to character format. Non-valid hex values are processed as a regular entity character string.
<b>ATTR</b>	Indicates that the specified <i>entity-text</i> is a CUA text attribute. Valid values are: CH, CT, DT, ET, FP, NT, PIN, PT, SAC, SI, WASL, and WT. These values are converted to their corresponding attribute byte. Non-valid attribute codes are processed as a regular entity character string.
<b>"entity-text"</b>	The text associated with the entity reference. The text must be enclosed in single or double quotes. The length of the <i>entity-text</i> must be less than or equal to 253 bytes.
<b>SYSTEM</b>	Indicates this entity refers to an external file.
<b>"filespec"</b>	The name of the file the entity refers to. The name must be enclosed in single or double quotes. If this is not specified, it defaults to the name of the entity.  The SYSTEM parameter can optionally be followed by the file name for the included file. The file name for MVS is a member name for a file provided on the invocation panel or specified as "DTLGML" entries in the ISPDTLC profile.

## Description

Entities are symbolic names that are used to insert text into a file. The text that an entity refers to can be a simple string of characters or it can be the text from an entire file.

An entity reference is used to insert the text associated with the entity. Entities must be declared in the declaration subset of the DOCTYPE declaration before they can be referred to. To refer to the entity in the source file, the entity name is preceded by an ampersand (&) to indicate it is an entity or percent (%) to indicate it is a parameter entity. Both types of entities are ended with a semicolon (;). A blank or the end of the line can be used to end the entity reference instead of the semicolon.

Because entity declarations can only be made within the declaration subset, the parameter entity is the only way to embed a file of entity declarations. Parameter entities are used when an entity reference is needed in the declaration subset. References to parameter entities can only be made in the declaration subset.

References to entities can be made anywhere in the source file *after* the end of the DOCTYPE declaration.

**Note:** To refer to an entity within a <SOURCE> tag in the source file, the entity name is preceded by a percent (%) instead of an ampersand (&).

Because entity names are case-sensitive, ensure that references to entities are specified correctly.

## Conditions

Entities that are declared do not have to be referred to.

## Example

This example uses both entities and parameter entities. It embeds the file GLBENT with global entity declarations, and a file with tags and text. It also uses entities and parameter entities that refer to text strings.

The first entity declaration declares the "glbent" parameter entity as an external file.

The file name is defaulted to GLBENT. A parameter entity is used because this file contains entity declarations. Because entity declarations can only be made in the declaration subset, the GLBENT file is embedded with an entity reference within the declaration subset. The entity declarations in GLBENT are for text that is used at the top and bottom of the panel. The "header" entity declaration refers to an external file, and the "footer" is a text string. Both of these entities are referred to in the source file.

The second entity declaration, for "list", is also a parameter entity. This declaration refers to a string, not an external file. The text is the SL tag name, which is referred to in the next two entity declarations. These two declarations, "slist" and "elist", are used as the SL start and end tags. They are defined as entities so the type of list can be changed in one place. To change the list type from a simple list (SL) to an unordered list (UL), change the parameter entity "list" from SL to UL.

This is the content of the source file:

```
<!DOCTYPE DM SYSTEM [
<!ENTITY % glbent SYSTEM -- declaration of global entity file -->
%glbent;<!-- Embeds the global entity file -->
<!ENTITY % list "sl" -- type of list -->
<!ENTITY slist "<%list;>" -- type of list start tag. -- >
<!ENTITY elist "</%list;>" -- type of list end tag. -- >
]>

<panel name=showlist depth=22 width=45>Show Departments
  <area>
    <info width=40>
      &header;
      <p>The floors and departments are shown below:
      &slist;
        <li>First floor
          &slist;
            <li>Toys
            <li>Electronics
          &elist;
        <li>Second floor
          &slist;
            <li>Boys clothes
            <li>Girls clothes
          &elist;
        &elist;
      &footer;
    </info>
  </area>
</panel>
```

This is the content of the embedded file GLBENT:

```
<!ENTITY header SYSTEM "coname">
<!ENTITY footer "<p> We're always glad to help!">
```

This is the content of the embedded file CONAME:

```
<lines>
Jeff's Children's World
Barnett, NC
</lines>
```

Figure 89 shows the formatted result:




Figure 89. Entities and Parameter Entities

## Sample Entity Definitions

The tag examples in Chapter 13, “Tag Reference,” on page 205 use entity definitions to create the sample panels. The entities used are called SAMPABC (to define the action bar); SAMPVAR1, SAMPVAR2, and SAMPVAR3 (to provide VARCLASS and VARLIST definitions); and SAMPBODY (to provide a panel body section).

The DTL definitions follow:

## Entities

### SAMPABC:

```
<ABC>File
  <PDC>Add Entry
    <ACTION RUN=add>
  <PDC>Delete Entry
    <ACTION RUN=delete>
  <PDC>Update Entry
    <ACTION RUN=update>
  <PDC>Exit
    <ACTION RUN=exit>
<ABC>Search
  <PDC CHECKVAR=whchsrch MATCH=1>Search on name
    <ACTION SETVAR=whchsrch VALUE=1>
    <ACTION RUN=search>
  <PDC CHECKVAR=whchsrch MATCH=2>Search on card number
    <ACTION SETVAR=whchsrch VALUE=2>
    <ACTION RUN=search>
<ABC>Help
  <PDC>Extended Help...
    <ACTION RUN=exhelp>
  <PDC>Keys Help...
    <ACTION RUN=keyshelp>
```

### SAMPVARI:

```
<VARCLASS NAME=date TYPE=' char 8' >
<VARCLASS NAME=numcls TYPE=' numeric 7' >
<VARCLASS NAME=namecls TYPE=' char 25' >
<VARCLASS NAME=char1cls TYPE=' char 1' >
<VARCLASS NAME=char7cls TYPE=' char 7' >

<VARLIST>
  <VARDCL NAME=whchsrch VARCLASS=char1cls>
  <VARDCL NAME=curdate VARCLASS=date>
  <VARDCL NAME=cardno VARCLASS=numcls>
  <VARDCL NAME=name VARCLASS=namecls>
  <VARDCL NAME=address VARCLASS=namecls>
  <VARDCL NAME=cardsel VARCLASS=char1cls>
  <VARDCL NAME=card VARCLASS=char7cls>
  <VARDCL NAME=north VARCLASS=char1cls>
  <VARDCL NAME=south VARCLASS=char1cls>
  <VARDCL NAME=east VARCLASS=char1cls>
  <VARDCL NAME=west VARCLASS=char1cls>
  <VARDCL NAME=nth VARCLASS=char1cls>
  <VARDCL NAME=sth VARCLASS=char1cls>
  <VARDCL NAME=est VARCLASS=char1cls>
  <VARDCL NAME=wst VARCLASS=char1cls>
</VARLIST>
```

**SAMPVAR2:**

```

<VARCLASS NAME=cascl s TYPE=' char 7' >
<VARCLASS NAME=namecl s TYPE=' char 25' >
<VARCLASS NAME=addrcl s TYPE=' char 25' >
<VARCLASS NAME=char1cl s TYPE=' char 1' >
<VARCLASS NAME=char2cl s TYPE=' char 2' >

<VARLIST>
  <VARDCL NAME=caseno VARCLASS=cascl s>
  <VARDCL NAME=name VARCLASS=namecl s>
  <VARDCL NAME=address VARCLASS=addrcl s>
  <VARDCL NAME=casesel VARCLASS=char2cl s>
  <VARDCL NAME=patin VARCLASS=char1cl s>
  <VARDCL NAME=defa VARCLASS=char1cl s>
  <VARDCL NAME=cont VARCLASS=char1cl s>
  <VARDCL NAME=priv VARCLASS=char1cl s>
  <VARDCL NAME=incr VARCLASS=char1cl s>
  <VARDCL NAME=di sp VARCLASS=char1cl s>
  <VARDCL NAME=fraud VARCLASS=char1cl s>
</VARLIST>

```

**SAMPVAR3:**

```

<VARCLASS NAME=namecl s TYPE=' char 7' >
<VARCLASS NAME=char1cl s TYPE=' char 1' >
<VARCLASS NAME=char2cl s TYPE=' char 2' >

<VARLIST>
  <VARDCL NAME=fi le VARCLASS=namecl s>
  <VARDCL NAME=type VARCLASS=char2cl s>
  <VARDCL NAME=marg VARCLASS=char2cl s>
  <VARDCL NAME=copy VARCLASS=char2cl s>
  <VARDCL NAME=dupl x VARCLASS=char1cl s>
</VARLIST>

```

**SAMPBODY:**

```

<TOPINST>Type in patron's name and card number (if applicable).
<TOPINST>Then select an action bar choice.
<AREA>
  <DTAFLD DATAVAR=curdate PMTWIDTH=12 ENTWIDTH=8 USAGE=out>Date
  <DTAFLD DATAVAR=cardno PMTWIDTH=12 ENTWIDTH=7 DESWIDTH=25>Card No
    <DTAFLDD>(A 7-digit number)
  <DTAFLD DATAVAR=name PMTWIDTH=12 ENTWIDTH=25 DESWIDTH=25>Name
    <DTAFLDD>(Last, First, M.I.)
  <DTAFLD DATAVAR=address PMTWIDTH=12 ENTWIDTH=25>Address
  <DIVIDER>
  <REGION DIR=horiz>
  <SELFLD NAME=cardsel PMTWIDTH=30 SELWIDTH=38>Choose
  one of the following
    <CHOICE CHECKVAR=CARD MATCH=NEW>New
    <CHOICE CHECKVAR=CARD MATCH=RENEW>Renewal
    <CHOICE CHECKVAR=CARD MATCH=REPLACE>Replacement
  </SELFLD>
  <SELFLD TYPE=multi PMTWIDTH=30 SELWIDTH=25>Check valid branches
    <CHOICE NAME=NORTH HELP=NTHHLP CHECKVAR=NTH>North Branch
    <CHOICE NAME=SOUTH HELP=STHHLP CHECKVAR=STH>South Branch
    <CHOICE NAME=EAST HELP=ESTHLP CHECKVAR=EST>East Branch
    <CHOICE NAME=WEST HELP=WSTHLP CHECKVAR=WST>West Branch
  </SELFLD>
  </REGION>
</AREA>
<CMDAREA>Enter a command

```

### DTL Macros

A DTL macro is a DTL source member found in the concatenated DTL source libraries allocated as input to ISPD TLC. The macro member can be empty or it can contain any DTL tag coding, including DTL comments.

The macro member is embedded into the current DTL source file when the macro name is encountered during conversion. The file embed process is similar to Entity file embed.

DTL macro tag syntax is similar to regular DTL tag syntax. You invoke a macro by specifying the macro member name using a special DTL tag open delimiter, like this:

```
<?macmemb>
```

The macro member name must conform to the DTL standard member name rules.

When ISPD TLC finds the <? open delimiter, a file embed is performed on the specified member name. The reserved member name **dummy** can be specified to create a *no operation* (NOP) situation during the embed cycle. If the specified member has no records, conversion continues with the next DTL source record.

The content of the macro member can be any valid DTL source input. The member can contain multiple tags and comment records just like any other DTL source file. DTL source file variables, sometimes referred to as entities, are substituted using standard entity processing.

An advantage to using the macro syntax instead of an entity file embed is that you need not code the entity declaration for the file to be embedded. ISPD TLC resolves the required information for you.

Another advantage is that you can specify entity values as part of the macro coding syntax, and bypass the coding of other entity declarations. For example, if the entity variables *subst\_var\_1*, *subst\_var\_2*, and *subst\_var\_3* were coded within the macro using standard DTL syntax (that is, `&subst_var_1;`, `&subst_var_2;`, and `&subst_var_3;`), you could invoke the macro and specify the substitution values like this:

```
<?macmemb subst_var_1=subval ue1 subst_var_2=subval ue2  
subst_var_3=subval ue3>
```

ISPD TLC automatically defines the entities with the specified values. The values are stored using entity REPLACE processing, so that if a previous definition exists, it is overwritten. The new definition remains in effect until replaced, and can be referenced by any other part of the DTL source file.

Macro tags placed within the document declaration function use the same rules as macro tags found after the document declaration. For example, you can use the macro syntax in place of parameter entities. The parameter entity (really a file of other entity definitions) member **pentmem** can be embedded easily by coding

```
<?pentmem>
```

within the document declaration. This syntax replaces the more complicated parameter entity coding of

```
<:ENTITY % pentmem; system>  
%pentmem;
```

In another example, the macro syntax can be used in place of entity tags.

```
<?dummy panel_title='ISPF macro example'
        panel_width=60
        panel_depth=18>
```

This syntax replaces multiple entity definitions:

```
<:ENTITY panel_title 'ISPF macro example' >
<:ENTITY panel_width '60' >
<:ENTITY panel_depth '18' >
```

In the previous example the macro name **dummy** is used to bypass the file embed and enable the attribute resolution process to establish the entity values.

The macro name *dummy* can also be used within a macro definition to provide default values for macro entity variables. Example:

```
<!-- macro/include ISPZ@EX1 to format a 2 column example -->
<?dummy ?col1_indent=0 ?col1_width=30>

<region dir=horiz>
  region dir=vert width=&col1_width; indent=&col1_indent; >
  <pnl inst>&col1_text;
</region>

  <region dir=vert>
    <pnl inst>&col2_text;
  </region>
</region>
```

In this example the entity variables *col1\_width* and *col1\_indent* have default values specified by the **dummy** tag. The special syntax '?variable=value' is used to provide the default values.

If you invoke the ISPZ@EX1 macro like this:

```
<?ispz@ex1 col1_text='text left' col2_text='text right' >
```

the default values for *col1\_width* and *col1\_indent* will be used.

If you invoke ISPZ@EX1 macro like this:

```
<?ispz@ex1 col1_width=40 col1_indent=4
  col1_text='text left' col2_text='text right' >
```

the default values for *col1\_width* and *col1\_indent* will be overridden by those specified.

## Entities

---

## Chapter 13. Tag Reference

This chapter contains an alphabetical reference of the Dialog Tag Language (DTL) tags.

Each reference listing contains:

- A diagram of the valid syntax for the tag
- A list describing the tag attributes
- A description of the tag
- Conditions of usage
- A table of the tags that can be nested within the tag
- An example of how the tag is used within DTL source markup.

---

### Rules for Variable Names

Variable names supplied as attribute values on DTL tags must have the following characteristics:

- 1–8 characters in length
- The first character must be A–Z, a–z, @, #, or \$.
- Remaining characters, if any, can be A–Z, a–z, @, #, \$, or 0–9.

Lowercase characters are translated to their uppercase equivalents

Names composed of valid characters that are longer than 8 bytes are truncated to 8 bytes. Names that are not valid are set to blank.

---

### Rules for “%variable” Names

When a “%varname” notation is found as an attribute value, the “%varname” entry must have the following characteristics:

- 2–9 characters in length
- The first character is a “%”.
- The second character must be A–Z, a–z, @, #, or \$.
- Remaining characters, if any, can be A–Z, a–z, @, #, \$, or 0–9.

Lowercase characters are translated to their uppercase equivalents


The first position of a valid name is replaced by an “&”.

Names composed of valid characters that are longer than 9 bytes are truncated to 9 bytes. Names that are not valid are set to blank.

It is the responsibility of the application to provide a valid value in the variable before the panel is displayed.

## AB (Action Bar)

The AB tag defines an action bar on an application panel.



### MNEMGEN=YES | NO

**Note:** When the conversion utility is operating in DBCS mode, the default value for MNEMGEN is NO.

This attribute controls the automatic generation of mnemonic characters for the entire action bar. When MNEMGEN=NO, mnemonic characters are determined only by the use of the M tag within action bar or pull-down choice description text. See “Mnemonic Choice Selection” on page 38 and “M (Mnemonic)” on page 388 for additional information.

When MNEMGEN=YES, the NOGUI invocation option is ignored and mnemonics will be generated automatically.

### ABSEPSTR=ab-separator-string

This attribute provides a string of data to be overlaid at the right end of the action bar separator line.

**Note:** This attribute is NOT recommended for general use because the action bar separator line is not displayed when operating in GUI mode.

### ABSEPCHAR=ab-separator-character

This attribute provides a replacement character for the action bar separator line. When the GRAPHIC invocation option has been specified, the action bar separator will default to a solid line for host display. You can use the ABSEPCHAR attribute to provide a different character such as a dash.

## Description

The AB tag defines an action bar on an application panel. The action bar appears on the panel above the panel title line. The action bar provides a way for users to view all actions that apply to the panel it is coded within.

The conversion utility inserts a line between the action bar and the panel title line. The GRAPHIC invocation option creates a solid line. NOGRAPHIC creates a dashed line. If required by the length or number of action bar choices, the conversion utility will format multiple lines for the action bar.

ABC tags, which you code within an AB definition, define application panel choices for the action bar. PDC tags, which you code within ABC tag definitions, define the action bar pull-down choices.

To define an action bar and its associated pull-downs, you code the AB tag (and other tags that define the action bar choices and pull-downs) within a PANEL definition.

## Conditions

- The AB tag requires an end tag.
- You must code the AB tag within a PANEL definition. Each application panel can include only one action bar. See “PANEL (Panel)” on page 413 for a complete description of this tag.
- You must code at least one ABC tag within an action bar definition.
- To conform to CUA rules, you must include a help action bar choice.

## Nested Tags

You can code the following tag within an AB definition:

Tag	Name	Usage	Page	Required
ABC	Action bar choice	Multiple	208	Yes

## Example

The following markup contains the action bar markup for the application panel illustrated in Figure 90 on page 208.

```
<!DOCTYPE DM SYSTEM(
  <!entity sampvar1 system>
  <!entity sampbody system>)>
&sampvar1;

<PANEL NAME=ab KEYLIST=keyl xmp>Library Card Registration
<AB>
<ABC>File
  <PDC>Add Entry
    <ACTION RUN=add>
  <PDC>Delete Entry
    <ACTION RUN=delete>
  <PDC>Update Entry
    <ACTION RUN=update>
  <PDC>Exit
    <ACTION RUN=exit>
<ABC>Search
  <PDC CHECKVAR=whchsrch MATCH=1>Search on name
    <ACTION SETVAR=whchsrch VALUE=1>
    <ACTION RUN=search>
  <PDC CHECKVAR=whchsrch MATCH=2>Search on card number
    <ACTION SETVAR=whchsrch VALUE=2>
    <ACTION RUN=search>
<ABC>Help
  <PDC>Extended Help...
    <ACTION RUN=exhelp>
  <PDC>Keys Help...
    <ACTION RUN=keyshelp>
</AB>
&sampbody;
</PANEL>
```

```

File Search Help
-----
Library Card Registration

Type in patron's name and card number if applicable.

Then select an action bar choice.

Date . . . :
Card No. . . _____ (A 7-digit number)
Name . . . _____ (Last, First, M.I.)
Address . . _____


Choose one of the following          Check valid branches
— 1. New                            _ North Branch
  2. Renewal                         _ South Branch
  3. Replacement                     _ East Branch
                                      _ West Branch

Enter a command ==>> _____
F1=Help      F2=Split      F3=Exit      F6=KEYSHELP      F9=Swap
F12=Cancel
    
```

Figure 90. Action Bar

## ABC (Action Bar Choice)

The ABC tag defines a choice in an action bar and serves as a base for associated pull-down choice tags.



**HELP=NO | YES | help-panel-name | \*help-message-id | %varname | \*%varname**

This attribute specifies the help action taken when the user requests help on the action bar choice.

When HELP=YES, control is returned to the application. You can specify either a help panel or a message identifier. If a message identifier is used, it must be prefixed with an asterisk (\*).

The help attribute value can be specified as a variable name. When **%varname** is coded, a panel variable name is created. When **\*%varname** is coded, a message variable name is created.

If the user requests help on an action bar choice and no help is defined, the extended help panel is displayed. If an extended help panel is not defined for the panel, the application or ISPF tutorial is invoked.

The *help-panel-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

See “HELP (Help Panel)” on page 335 for information on creating help panels. For information about creating messages, see “MSG (Message)” on page 390.

#### **PDCVAR=*pdv-variable-name***

This attribute provides the name of a variable to contain the value of the pull-down choice. When a variable name is provided, it replaces the default ZPDC variable name. The *pdv-variable-name* is not initialized to blank.

The *pdv-variable-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

#### **choice-description-text**

This is the text that appears in the action bar. The text is limited to 64 bytes.

If the *choice-description-text* exceeds the panel width, the conversion utility issues a warning message and truncates the text. If the *choice-description-text* for multiple ABC tags exceeds the panel width, the conversion utility formats a multiple-line action bar.

## **Description**

The ABC tag defines a choice in an action bar and serves as a base for associated pull-down choice tags. The pull-down choices appear in a pull-down when the action bar choice is selected.

If the text of an action bar choice contains multiple words, multiple blanks between the words are not compressed.

## **Conditions**

- You must code the ABC tag within an AB definition. See “AB (Action Bar)” on page 206 for a complete description of this tag.
- You must code at least one PDC tag within each ABC definition. See “PDC (Pull-Down Choice)” on page 428 for a complete description of this tag.
- The maximum number of action bar choices that will be generated is 40.

## **Nested Tags**

You can code the following tags within an ABC definition:

Tag	Name	Usage	Page	Required
COMMENT	Comment	Multiple	275	No
M	Mnemonic	Single	388	No
PDC	Pull-down choice	Multiple	428	Yes
PDSEP	Pull-down Separator	Multiple	432	No
SOURCE	Source	Multiple	482	No

## **Example**

The following markup illustrates the use of the PDCVAR attribute to specify an application variable for the first action bar choice. It produces the action bar on the application panel shown in Figure 91 on page 210.

```

<!DOCTYPE DM SYSTEM(
  <!entity sampvar1 system>
  <!entity sampbody system)>
&sampvar1;

<PANEL NAME=abc1 KEYLIST=keyl xmp>Library Card Registration
<AB>
<ABC PDCVAR=foptns>File
  <PDC>Add Entry
    <ACTION RUN=add>
  <PDC>Delete Entry
    <ACTION RUN=delete>
  <PDC>Update Entry
    <ACTION RUN=update>
  <PDC>Exit
    <ACTION RUN=exit>
<ABC>Search
  <PDC CHECKVAR=whchsrch MATCH=1>Search on name
    <ACTION SETVAR=whchsrch VALUE=1>
    <ACTION RUN=search>
  <PDC CHECKVAR=whchsrch MATCH=2>Search on card number
    <ACTION SETVAR=whchsrch VALUE=2>
    <ACTION RUN=search>
<ABC>Help
  <PDC>Extended Help...
    <ACTION RUN=exhelp>
  <PDC>Keys Help...
    <ACTION RUN=keyshelp>
</AB>
&sampbody;
</PANEL>

```

File Search Help

---

Library Card Registration

Type in patron's name and card number if applicable.

Then select an action bar choice.

Date . . . . :

Card No. . . . \_\_\_\_\_ (A 7-digit number)

Name . . . . \_\_\_\_\_ (Last, First, M.I.)

Address . . . \_\_\_\_\_

Choose one of the following	Check valid branches
— 1. New	— North Branch
— 2. Renewal	— South Branch
— 3. Replacement	— East Branch
	— West Branch


Enter a command ===> \_\_\_\_\_

F1=Help      F2=Split      F3=Exit      F6=KEYSHELP      F9=Swap  
F12=Cancel


Figure 91. Action Bar Choices

## ACTION (Action)


The ACTION tag defines the action that occurs when a pull-down choice or a selection field choice is selected.




### Keyword 1:




### Keyword 2:




### Keyword 3:



### ISPF options:



## ACTION



### **RUN=internal-command-name | %varname**

When the ACTION tag is associated with a PDC tag, this attribute specifies the internal name of a command to be executed. The command is found in the application or system command table unless `APPLCMD=YES` is specified. The search for the command follows the normal command processing rules. For information on defining commands, see “CMD (Command Definition)” on page 262.

The RUN action is an ending action. Thus, if multiple ACTION tags are coded for a given pull-down, those following a RUN action are ignored.

When the ACTION tag is associated with a CHOICE tag (under a SELFLD tag that specifies `TYPE=MENU` or `TYPE=MODEL`), the TYPE attribute and related RUN attribute values are:

TYPE	RUN attribute value
CMD	Command name
PGM	Program name
PANEL	Panel name
WSCMD	Workstation command name and parameters
WSCMDV	The name of a variable that contains the workstation command and parameters.

When the ACTION tag is associated with a CHOICE tag under a SELFLD tag that specifies `TYPE=TUTOR`, the TYPE attribute is forced to **PANEL**. The RUN attribute must provide a panel name. None of the other ISPF selection menu attributes are valid for tutorial panels.

If `TYPE=CMD` is specified and the *internal-command-name* should start with a %, you must code an additional % before the *internal-command-name* to distinguish it from a variable name. (For example, to specify the *internal-command-name* “%abc”, code “%%abc”. If `TYPE=EXIT` is specified, the RUN attribute is required for conversion utility processing, but is not used in the generated panel.

**Note:** This attribute is not supported if the ACTION tag is associated with a CHOICE tag under a SELFLD tag that specifies `TYPE=SINGLE` or `TYPE=MULTI`.

### **PARM=parameters | %varname**

These are the command parameters. These parameters are passed to command processing with the command specified on the RUN attribute. Command processing handles the specified parameters the same way parameters entered in the command area are handled. You can specify the name of a dialog variable (using % notation) whose value at run time will be passed as the parameter data. When the ACTION tag is associated with

a PDC tag, the conversion utility limits the length of the command parameters to 72 single-byte characters.

When a ACTION tag is used to build a menu selection choice for TYPE=CMD or TYPE=PGM, and the NEWWINDOW attribute has been specified, the conversion utility limits the length of the command parameters to 249 single-byte characters; otherwise, the parameter is added to the selection as coded. The PARM attribute is not used when TYPE=WSCMD.

**APPLCMD=NO | YES**

This attribute specifies whether the command provided by the RUN attribute is to be passed directly to the application, bypassing the command table search. When APPLCMD=YES, the length of the command name is limited to 7 bytes to allow the passthru character ">" to be prefixed to the command name.

This attribute is valid only on an ACTION tag that is associated with a PDC tag.

**The following attributes are valid only when generating an ISPF selection menu or edit model selection menu. (When the SELFLD tag specifies TYPE=TUTOR, the TYPE attribute is forced to "PANEL" and none of the other ISPF selection menu attributes are valid.)**

**TYPE=CMD | PGM | PANEL | WSCMD | WSCMDV | EXIT**

This attribute specifies the type of selection to be generated for the selection menu. The attributes NEWAPPL, NEWWINDOW, PASSLIB, NEWPOOL, SUSPEND, SCRNAME, NOCHECK, ADDPOP, OPT, MODE, LANG, BARRIER, NEST, WSDIR, WSINVOKE, WSSIZE, and WSVIEW are not valid when TYPE=EXIT is specified.

**NEWAPPL=application-id**

The NEWAPPL keyword may be specified with or without an application identifier. This attribute specifies that the NEWAPPL keyword (and the application identifier, if present) will be added to the selection menu choice.

**NEWWINDOW**

This attribute specifies that the selection menu choice will be created specifying the ISPSTRT programming interface. The NEWWINDOW attribute is valid only when TYPE=PANEL, TYPE=PGM, or TYPE=CMD.

**PASSLIB**

This attribute specifies that the PASSLIB keyword will be added to the selection menu choice.

**NEWPOOL**

This attribute specifies that the NEWPOOL keyword will be added to the selection menu choice.

**SUSPEND**

This attribute specifies that the SUSPEND keyword will be added to the selection menu choice.

**SCRNAME=screen-name**

This attribute specifies that the SCRNAME keyword will be added to the selection menu choice. ISPF reserved values for *screen-name* are LIST, NEXT, PREV, ON, and OFF.

## ACTION

### **NOCHECK**

This attribute specifies that the NOCHECK keyword will be added to the selection menu choice. The NOCHECK attribute is valid only when TYPE=CMD or TYPE=PGM.

### **ADDDPOP**

This attribute specifies that the ADDPOP keyword will be added to the selection menu choice. The ADDPOP attribute is valid only when TYPE=PANEL.

### **OPT=option | %varname**

This attribute specifies that the OPT keyword will be added to the selection menu choice to specify an initial option for the panel. The OPT attribute is valid only when TYPE=PANEL.

### **MODE=LINE | FSCR**

This attribute specifies that the MODE keyword will be added to the selection menu choice. The MODE attribute is valid only when TYPE=CMD or TYPE=PGM.

### **LANG=APL | CREX**

This attribute specifies that the LANG keyword will be added to the selection menu choice. The LANG attribute is valid only when TYPE=CMD. LANG(CREX) is optional if the compiled REXX has been link-edited to include any of the stubs EAGSTCE, EAGSTCPP, or EAGSTMP.

### **BARRIER**

This attribute specifies that the BARRIER keyword will be added to the selection menu choice. The BARRIER attribute is valid only when TYPE=CMD.

### **NEST**

This attribute specifies that the NEST keyword will be added to the selection menu choice. The NEST attribute is valid only when TYPE=CMD.

### **WSDIR=ws-directory**

This attribute specifies that the WSDIR(*ws-directory*) keyword will be added to the selection menu choice. WSDIR provides the name of a dialog variable that contains the directory name from which the workstation command should be invoked. The WSDIR attribute is valid only when TYPE=WSCMD or TYPE=WSCMDV.

### **WSINVOKE=MODELESS | MODAL**

This attribute specifies either the MODELESS or MODAL keyword will be added to the selection menu choice. The WSINVOKE attribute is valid only when TYPE=WSCMD or TYPE=WSCMDV.

### **WSSIZE=MAX | MIN**

This attribute specifies either the MAX or MIN keyword will be added to the selection menu choice. The WSSIZE attribute is valid only when TYPE=WSCMD or TYPE=WSCMDV.

### **WSVIEW=VIS | INVIS**

This attribute specifies either the VIS or INVIS keyword will be added to the selection menu choice. The WSVIEW attribute is valid only when TYPE=WSCMD or TYPE=WSCMDV.

**SETVAR=variable-name**

This attribute sets a value into a dialog variable. The SETVAR attribute names the variable to set. The *variable-name* must be coded without the leading % sign.

**VALUE=1 | string | %varname**

This is the value to set into the variable named on the SETVAR attribute. If you code the SETVAR attribute but omit the VALUE attribute, ISPF assigns the variable a value of 1. You can specify the name of a variable (using % notation) whose value at run time will be used to set the variable.

When defining the ACTION tag for selection fields, be aware that the variable name defined in the SELFLD tag for single-choice selection fields or in the CHOICE tag for multiple-choice selection fields will contain the value entered by the user when the selection is made. In addition, if the CHECKVAR attribute is specified in the CHOICE tag, the value of the MATCH attribute associated with the choice is set into the variable named by the CHECKVAR attribute. Therefore, it is not necessary to use the ACTION tag SETVAR attribute for the application to know which selection field choice or choices were made by the user.

**TOGVAR=variable-name**

This attribute allows you to alternate the value of a single variable between two values. The TOGVAR attribute names the variable to set. The *variable-name* must be coded without the leading % sign.

The function of the TOGVAR action can be depicted as follows:

```
if (TOGVAR-variable-name = VALUE1-string)
  TOGVAR-variable-name = VALUE2-string
else
  TOGVAR-variable-name = VALUE1-string
```

**VALUE1=0 | string | %varname**

This is the value to set into the variable named on the TOGVAR attribute if it is not currently equal to this value. If you code the TOGVAR attribute, but omit the VALUE1 attribute, the variable is assigned a value of 0. You can specify the name of a variable (using % notation) whose value at run time will be used to set the variable.

**VALUE2=1 | string | %varname**

This is the value to set into the variable named on the TOGVAR attribute if it is currently equal to the value specified with the VALUE1 attribute. If you code the TOGVAR attribute, but omit the VALUE2 attribute, the variable is assigned a value of 1. You can specify the name of a variable (using % notation) whose value at run time will be used to set the variable.

## Description

The ACTION tag defines the action that occurs when a pull-down choice or a selection field choice is selected. Code the ACTION tag within the PDC or CHOICE definition it is associated with. You can specify multiple ACTION tags for a given choice. The conversion utility builds the logic to carry out the actions in the order in which you code the ACTION tags.

When defining action bar pull-downs, you should code the SETVAR attribute in the ACTION tags associated with each PDC tag if the application needs to know which pull-down choice the user selected. Unlike selection fields, there is no variable name associated with a pull-down definition and the PDC CHECKVAR

## ACTION

variable is not set to indicate the user's choice. Therefore, dialogs must refer to the SETVAR *variable-name* to determine the pull-down choice the user has selected.

The TYPE, NEWAPPL, NEWWINDOW, PASSLIB, NEWPOOL, SUSPEND, SCRNAME, NOCHECK, ADDPOP, OPT, MODE, LANG, BARRIER, NEST, WSDIR, WSINVOKE, WSSIZE, and WSVIEW attributes are used by the conversion utility to build an ISPF selection menu. They are valid only when they appear on an ACTION tag associated with a CHOICE tag which is nested within a SELFLD tag that specifies TYPE=MENU, TYPE=MODEL, or TYPE=TUTOR (when the SELFLD tag specifies TYPE=TUTOR, the only valid selection menu attribute is TYPE=PANEL). They will not be processed in other situations. Refer to the *ISPF User's Guide* for a description of the function of these keywords in ISPF option menus.

## Conditions

- You must code the ACTION tag within the PDC or CHOICE definition it is associated with. See "PDC (Pull-Down Choice)" on page 428 and "CHOICE (Selection Choice)" on page 255 for descriptions of these tags.
- You must code one (and only one) of these attributes on each ACTION tag: RUN, SETVAR, or TOGVAR.
- You can code the RUN attribute when:
  - The ACTION tag is associated with a PDC tag.
  - The ACTION tag is associated with a CHOICE tag under a SELFLD tag that specifies TYPE=MENU, TYPE=MODEL, or TYPE=TUTOR.
- When a "%varname" notation is found on any of the attributes that allow a variable name, the "%varname" entry must follow the standard naming convention described in "Rules for "%variable" Names" on page 205.

## Nested Tags

None.

## Example

In the following markup, each of the PDC tags have associated ACTION tags that specify the command that is executed when the pull-down choice is selected. Many of the PDC tags have additional ACTION tags associated with them that specify the SETVAR attribute to let the application know which pull-down choice was selected.

The use of ACTION tags associated with CHOICE tags is illustrated in the example for "PS (Point-and-Shoot)" on page 438.

```
<!DOCTYPE DM SYSTEM>

<PANEL NAME=action1>Library Card Listing
<AB>
<ABC>File
  <PDC>Add Entry
    <ACTION SETVAR=fchoice VALUE=add>
    <ACTION RUN=add>
  <PDC>Delete Entry
    <ACTION SETVAR=fchoice VALUE=delete>
    <ACTION RUN=delete>
  <PDC>Update Entry
    <ACTION SETVAR=fchoice VALUE=update>
    <ACTION RUN=update>
  <PDC>Exit
```


```

    <ACTION RUN=exit>
<ABC>Sort sequence
  <PDC CHECKVAR=whchsort MATCH=1>Sort on name
    <ACTION SETVAR=whchsort VALUE=1>
    <ACTION RUN=sort>
  <PDC CHECKVAR=whchsort MATCH=2>Sort on card number
    <ACTION SETVAR=whchsort VALUE=2>
    <ACTION RUN=sort>
<ABC>Help
  <PDC>Extended Help...
    <ACTION RUN=exhelp>
  <PDC>Keys Help...
    <ACTION RUN=keyshelp>
</AB>
<TOPINST>Choose the size of the list needed.
<TOPINST>Then select action bar choice "Sort sequence" to
indicate the desired sort sequence.
<AREA>
  <SELFLD NAME=aa PMTWIDTH=30 PMTLOC=before SELWIDTH=38>Choose
  one of the following
    <CHOICE>New this month
    <CHOICE>New this year
    <CHOICE>All (this will take time to process)
  </SELFLD>
</AREA>
<CMDAREA>Enter a command
</PANEL>


```

## AREA (Area)


The AREA tag defines portions of a panel body, one or more of which can be scrollable.



### DEPTH Options:



### DIV Options:



## AREA

### **MARGINW=1 | n**

This attribute defines a margin along the left and right sides of the panel area. This attribute allows you to specify the width of the margin in characters. The minimum value you can specify is 1 and the maximum value is 32. If you do not specify a value, the margin is set to 1.

The MARGINW cannot be larger than one half the panel width minus 2. Specification of the MARGINW should always allow enough room in the panel body section of the ISPF panel being generated to contain all non-wrapped data without truncation. Specification of one half the panel width minus 2 results in no panel area in which panel body text can be written.

### **MARGIND=0**

This attribute defines a margin along the top and bottom of the panel area.

The conversion utility will only support a margin depth of zero in an effort to use all of the available space on the panel body. Any definition of margin depth that is not equal to zero will be changed to zero.

### **INDENT=n**

This attribute defines the number of columns to indent the current AREA from the current MARGINW value.

### **DEPTH=n | \***

This attribute defines the minimum size of a scrollable panel area. If DEPTH is not specified for HELP panels, the conversion utility will generate multiple HELP panels for compatibility with previous releases. When EXTEND=OFF, the minimum DEPTH is 2 lines. When EXTEND=ON, the minimum DEPTH is 1 line. When DEPTH=\*, the conversion utility will reserve the remaining available panel depth for the scrollable area.

### **EXTEND=OFF | ON | FORCE**

This attribute defines the run-time display size for the scrollable area. If EXTEND=ON is specified, the panel definition is expanded from the minimum DEPTH to the size of the logical screen. Only one EXTEND=ON attribute value is allowed on a panel. The first tag (AREA, DA, GA, REGION, SELFLD) with EXTEND=ON is accepted; the EXTEND attribute on any subsequent AREA tag is ignored.

If you intend to display the panels in a pop-up window, it is recommended that you code EXTEND=OFF.

If the EXTEND attribute is specified without a DEPTH attribute, a warning message is issued and the EXTEND attribute is ignored.

If EXTEND=FORCE is specified within a horizontal area, the EXTEND(ON) keyword is added to the scrollable area attribute statement in the )ATTR panel section. The conversion utility issues a message to advise of a potential error if other panel fields are formatted on or after the last defined line of the scrollable area.

### **DIV=NONE | BLANK | SOLID | DASH | TEXT**

This attribute specifies the type of divider line to be placed before and after the scrollable area. If this attribute is not specified, or has the value NONE, no divider line is generated. The value BLANK produces a blank line. You must specify SOLID, DASH, or TEXT to produce a visible divider line. When the GRAPHIC invocation option is specified, SOLID produces a solid line for host display and DASH produces a dashed line. When NOGRAPHIC is specified or the panel is displayed in GUI mode, both SOLID and DASH produce a dashed line. A visible divider formats with a non-displayable attribute byte on each end of the line.

If the DIV attribute is found without the DEPTH attribute, a warning message is issued and the DIV attribute is ignored.

**DIVWIDTH=MAX | MIN**

This attribute specifies the width of the divider line. If DIVWIDTH=MAX, the divider line extends across the entire width of the panel defined by the AREA tag. If DIVWIDTH=MIN, the divider line is formatted to allow for the MARGINW and INDENT attribute values.

**FORMAT=START | CENTER | END**

This attribute specifies the position of the *divider-text* within the divider line. You must specify both the FORMAT attribute and the TEXT attribute to create a divider line containing text.

**TEXT=divider-text**

This attribute specifies the text to be placed on the divider line. You must specify both the FORMAT attribute and the TEXT attribute to create a divider line containing text.

**WIDTH=n**

This attribute defines the width of a panel area. If WIDTH is not specified the area formats to the remaining available panel width.

**DIR=VERT | HORIZ**

This attribute allows areas to be placed side by side on the panel. You use the WIDTH attribute in combination with the DIR attribute to tell the conversion utility to position areas horizontally. When the current horizontal AREA right boundary reaches or exceeds the right panel boundary, the next AREA will be formatted below the current AREA(s), at the left edge of the panel.

## Description

The AREA tag defines portions of a panel body. The conversion utility uses the DEPTH attribute value to reserve lines in the formatted panel body for a scrollable area. The DEPTH value cannot be more than the number of panel body lines still available for formatting when the AREA tag is processed.

The maximum DEPTH that you can specify is 2 lines less than the DEPTH value specified on the HELP or PANEL tag.

**Notes:**

1. If you specify the CMDAREA tag within your DTL source file, it must appear before the AREA tag when DEPTH=\* is specified. The AREA tag DEPTH may have to be adjusted to allow for additional lines which result from tags present within the panel definition following the end AREA tag.
2. For HELP panels, the presence of additional tags following a scrollable area causes the conversion utility to reserve 4 lines at the bottom of the screen to provide for the function key area.

The first line of the scrollable area is always reserved for the scrolling indicator line, which is provided by ISPF at run time. If all of the scrollable portion of the panel is displayed within the available DEPTH, the scroll indicator line is blank; otherwise, the value **"More: +"**, **"More: - +"**, or **"More: -"** will appear. On application panels, this portion includes the interactive fields and text of the panel. On help panels, this portion is the area of the panel that contains help text.

The DIR attribute is used to place entire areas side by side on the panel. Formatting within the AREA tag is always in a vertical direction. Panel areas are

## AREA

formatted horizontally when multiple AREA tags (specifying DIR=HORIZ) are placed sequentially in the DTL source file. Any other tag which occurs between an end AREA tag and a start AREA tag causes the overall panel formatting direction to be set to vertical.

### Conditions

- The AREA tag requires an end tag.
- You must code AREA tags within a HELP or PANEL definition. See “HELP (Help Panel)” on page 335 and “PANEL (Panel)” on page 413 for descriptions of these tags.
- Only one area can be defined with EXTEND=ON. This includes other AREA tags as well as any dynamic area defined by the DA tag, graphic area defined by the GA tag, scrollable section lists defined by the SELFLD tag, or scrollable regions defined by the REGION tag.

### Nested Tags

#### Application Panel

You can code the following tags within an AREA definition on an application panel:

Tag	Name	Usage	Page	Required
COMMENT	Comment	Multiple	275	No
DA	Dynamic area	Multiple	280	No
DIVIDER	Area divider	Multiple	289	No
DTACOL	Data column	Multiple	300	No
DTAFLD	Data field	Multiple	306	No
GA *	Graphic area	Single	327	No
GENERATE	Generate	Multiple	330	No
GRPHDR	Group header	Multiple	332	No
INFO	Information region	Multiple	350	No
LSTFLD *	List field	Single	377	No
PNLINST	Panel Instruction	Multiple	436	No
REGION	Region	Multiple	446	No
SELFLD	Selection field	Multiple	464	No
SOURCE	Source	Multiple	482	No

**Note:** Tags marked with \* are not valid within an ISPF selection menu panel.

#### Help Panel

You can code the following tags within an AREA definition on a help panel:

Tag	Name	Usage	Page	Required
COMMENT	Comment	Multiple	275	No
DIVIDER	Area divider	Multiple	289	No
GENERATE	Generate	Multiple	330	No
INFO	Information region	Multiple	350	No
REGION	Region	Multiple	446	No

## Example

The application panel in the following example contains four data fields and two selection fields coded within the AREA definition. The top instructions and command area are coded outside of the AREA definition. In addition, the panels illustrate a scrollable panel. Figure 92 on page 222, Figure 93 on page 222 and Figure 94 on page 223, show the formatted results.

```
<!DOCTYPE DM SYSTEM(
  <!entity sampvar2 system>
  <!entity sampabc system>)>
&sampvar2;

<PANEL NAME=area1 KEYLIST=keyl xmp>File-A-Case
<AB>
&sampabc;
</AB>
<TOPINST COMPACT>
  Type in client's name and case number (if applicable).
<TOPINST>Then select an action bar choice.
<AREA>
  <DTAFLD DATAVAR=caseno PMTWIDTH=12 ENTWIDTH=25 DESWIDTH=25>Case no
  <DTAFLDD>(A 7-digit number)
  <DTAFLD DATAVAR=name PMTWIDTH=12 ENTWIDTH=25 DESWIDTH=25>Name
  <DTAFLDD>(Last, First, M.I.)
  <DTAFLD DATAVAR=address PMTWIDTH=12 ENTWIDTH=25>Address
  <DIVIDER>
  <SELFLD NAME=casesel PMTWIDTH=30 PMTLOC=before SELWIDTH=38>Choose
  one of the following
  <CHOICE CHECKVAR=case MATCH=civ>Civil
  <CHOICE CHECKVAR=case MATCH=estate>Real estate
  <CHOICE CHECKVAR=case MATCH=envi ron>Envi ronmental
  </SELFLD>
</AREA>
<AREA DEPTH=6>
  <SELFLD TYPE=multi PMTWIDTH=35 SELWIDTH=50>Check type of offense committed
  <CHOICE NAME=patin HELP=patin CHECKVAR=val>Patent infringement
  <CHOICE NAME=defa HELP=defame CHECKVAR=def>Defamation
  <CHOICE NAME=cont HELP=cont CHECKVAR=qua>Breach of valid contract
  <CHOICE NAME=priv HELP=priv CHECKVAR=pri>Invasion of privacy
  <CHOICE NAME=incr HELP=incr CHECKVAR=icr>Interference with
  contractual relations
  <CHOICE NAME=di sp HELP=di sp CHECKVAR=di s>Improper disposal of
  medical by-products
  <CHOICE NAME=fraud HELP=fraud CHECKVAR=fra>Fraud
  </SELFLD>
</AREA>
<CMDAREA>Enter a command
</PANEL>
```

## AREA

```
File Search Help
-----
File-A-Case

Type in client's name and case number (if applicable).
Then select an action bar choice.

Case no . . . _____ (A 7-digit number)
Name . . . . _____ (Last, First, M.I.)
Address . . . _____

Choose one of the following   ___  1. Civil
                                   2. Real estate
                                   3. Environmental
                                   More:      +

Check type of offense committed
_ Patent infringement
_ Defamation
_ Breach of valid contract
Enter a command ==> _____
F1=Help      F3=Exit      F5=Display      F6=Keyshelp      F10=Actions
F12=Cancel
```

Figure 92. Application Panel Area

After scrolling, the panel appears as follows:

```
File Search Help
-----
File-A-Case

Type in client's name and case number (if applicable).
Then select an action bar choice.

Case no . . . _____ (A 7-digit number)
Name . . . . _____ (Last, First, M.I.)
Address . . . _____

Choose one of the following   ___  1. Civil
                                   2. Real estate
                                   3. Environmental
                                   More:      - +

_ Breach of valid contract
_ Invasion of privacy
_ Interference with contractual relations
_ Improper disposal of medical by-products
Enter a command ==> _____
F1=Help      F3=Exit      F5=Display      F6=Keyshelp      F10=Actions
F12=Cancel
```

Figure 93. Application Panel Area

After scrolling, the last choice in the list is visible.

```

File Search Help
-----
File-A-Case

Type in client's name and case number (if applicable).
Then select an action bar choice.

Case no . . . _____ (A 7-digit number)
Name . . . . _____ (Last, First, M.I.)
Address . . . _____

Choose one of the following   _ 1. Civil
                               _ 2. Real estate
                               _ 3. Environmental
                               More: -

_ Invasion of privacy
_ Interference with contractual relations
_ Improper disposal of medical by-products
_ Fraud
Enter a command ==>> _____
F1=Hel p      F3=Exi t      F5=Di spl ay      F6=Keyshel p      F10=Acti ons
F12=Cancel

```

Figure 94. Application Panel Area

An example of horizontal AREA formatting is shown in “Multiple AREA Tags” on page 44.

## ASSIGNI (Assignment List Item)

The ASSIGNI tag defines an assignment in an assignment list.

```

-<ASSIGNI [VALUE=test-value] [RESULT=assigned-value]>
</ASSIGNI >

```

### VALUE=test-value

This attribute specifies the value to be matched when performing the assignment.

The value of the data field variable is compared to the value of each VALUE attribute in succession until a match is found. The *test-value* must be the same case as the value to be matched. You can specify XLATL FORMAT=UPPER within the variable class associated with the data field to convert user input to uppercase before the assignment test is processed.

When ISPF finds a match, it assigns the value in the RESULT attribute to the variable named on the ASSIGNL tag. If ISPF does not find a match, no assignment is made.

If you omit this attribute, any value satisfies the test and ISPF assigns *assigned-value* to the dialog variable.

If a *test-value* appears more than once in the list, the first occurrence is used.

### RESULT=assigned-value

This attribute specifies the resulting value of the assignment if a match occurs on the *test-value* specified by VALUE.

## ASSIGNI

*Assigned-value* specifies the character string value for the conversion utility to assign to the variable named on the ASSIGNL tag. If you omit this attribute, the *test-value* is assigned to the variable.

### Description

The ASSIGNI tag defines an assignment in an assignment list. Each ASSIGNI tag provides information necessary to assign a value (the RESULT attribute) to a variable (specified with the ASSIGNL tag) based on the *test-value* (the VALUE attribute) of the variable named on the DTAFLD tag. As many ASSIGNI tags as are necessary (up to a limit of 126) can be included within the assignment list. The ISPF TRANS() function is used for ASSIGNI processing.

If both the VALUE and RESULT attributes are omitted, the DESTVAR attribute of the ASSIGNL tag is assigned the value of the data field's data variable (DATAVAR).

### Conditions

- You must code an ASSIGNI tag within an ASSIGNL definition. See "ASSIGNL (Assignment List)" on page 225 for a complete description of this tag.

### Nested Tags

None.

### Example

The following source file markup contains an application panel containing a data field. Within the data field is an assignment list that sets the dialog variable *rmtyp* to 1 when "SINGLE" is entered in the data field, or to 2 when "DOUBLE" is entered in the data field. The associated variable declarations and variable classes are also shown.

```
<!DOCTYPE DM SYSTEM>

<VARCLASS NAME=roomvar TYPE=' char 6' >
  <XLATL FORMAT=upper>
</XLATL>

<VARCLASS NAME=rmtypvar TYPE=' char 1' >

<VARLIST>
  <VARDCL NAME=room VARCLASS=roomvar>
  <VARDCL NAME=rmtyp VARCLASS=rmtypvar>
</VARLIST>

<PANEL NAME=assigni DEPTH=12 WIDTH=50>Hotel Register
<AREA>
  <DTAFLD DATAVAR=room ENTWIDTH=6 DESWIDTH=20 PMTWIDTH=15>Room type
    <ASSIGNL DESTVAR=rmtyp>
      <ASSIGNI VALUE=SINGLE RESULT=1>
      <ASSIGNI VALUE=DOUBLE RESULT=2>
    </ASSIGNL>
    <DTAFLDD>(Single or Double)
  </AREA>
<BOTINST>Press Enter to continue.
</PANEL>
```

## ASSIGNL (Assignment List)

The ASSIGNL tag defines an assignment list.

```
—<ASSIGNL—DESTVAR=destination-variable-name—>—</ASSIGNL>—
```

### DESTVAR=destination-variable-name

DESTVAR specifies the variable that receives the assignment value. You can code multiple assignment lists if you need to assign values to additional variables.

**Note:** If the *destination-variable-name* is a variable name used for another field on the panel, the value of the other field will be overlaid by the assignment value. The *destination-variable-name* should only be used for an output field variable.

## Description

The ASSIGNL tag defines an assignment list. ASSIGNI tags, which define the elements of the assignment list, are coded within the ASSIGNL tag.

Assignment lists are optional and provide a means of assigning a value to one variable based on the content of another. ISPF compares the value of the variable specified with the DATAVAR attribute of the DTAFLD tag against the values in the ASSIGNI tags.

Processing of assignment lists occurs at panel end (after translates and checks).

## Conditions

- The ASSIGNL tag requires an end tag.
- You must code an ASSIGNL tag within the DTAFLD definition it is associated with. See “DTAFLD (Data Field)” on page 306 for a complete description of this tag.

## Nested Tags

You can code the following tag within an ASSIGNL definition:

Tag	Name	Usage	Page	Required
ASSIGNI	Assignment list item	Multiple	223	No

## Example

The assignment list in the following markup assigns a value to the variable *decimal* dependent on the value the user enters in the data field variable *hexvar*. The associated variable declarations and variable classes are also shown.

```
<!DOCTYPE DM SYSTEM>

<VARCLASS NAME=varcls1 TYPE='char 1'>

<VARCLASS NAME=varcls2 TYPE='char 2'>

<VARLIST>
  <VARDCL NAME=hexvar VARCLASS=varcls1>
  <VARDCL NAME=decimal VARCLASS=varcls2>
</VARLIST>
```

## ASSIGNL

```
<PANEL NAME=assignl>Hex to Decimal
<TOPINST>Enter a hexadecimal digit.
<AREA>
<DTAFLD DATAVAR=hexvar PMTWIDTH=23 ENTWIDTH=1>Hexadecimal Value
  <ASSIGNL DESTVAR=decimal>
    <ASSIGN VALUE=0>
    <ASSIGN VALUE=1>
    <ASSIGN VALUE=2>
    <ASSIGN VALUE=3>
    <ASSIGN VALUE=4>
    <ASSIGN VALUE=5>
    <ASSIGN VALUE=6>
    <ASSIGN VALUE=7>
    <ASSIGN VALUE=8>
    <ASSIGN VALUE=9>
    <ASSIGN VALUE=a RESULT=10>
    <ASSIGN VALUE=b RESULT=11>
    <ASSIGN VALUE=c RESULT=12>
    <ASSIGN VALUE=d RESULT=13>
    <ASSIGN VALUE=e RESULT=14>
    <ASSIGN VALUE=f RESULT=15>
    <ASSIGN RESULT="??">
  </ASSIGNL>
<DTAFLD DATAVAR=decimal USAGE=out PMTWIDTH=23 ENTWIDTH=2>Decimal Value
</AREA>
</PANEL>
```

---

## ATTENTION (Attention)

The ATTENTION tag defines text that alerts the user to a risk of possible error conditions in the system.

```
—<ATTENTION>—┌───┐</ATTENTION>—
                  │   │
                  └───┘
                    text
```

**text** This is the text of the attention message.

### Description

The ATTENTION tag defines text that alerts the user to a risk of possible error conditions in the system.

The ATTENTION tag is one of the tags that alert the user of a possible risk; CAUTION and WARNING are the others.

Code an attention statement before the text to which it pertains so that the user can read about the possible risks before reading the text.

When an attention statement is displayed, the string "Attention:" (or its translated equivalent) appears on the screen before the text of the statement.

You can code additional paragraphs of text by coding the P (paragraph) tag within an ATTENTION definition. You can also code other tags allowed in an information area within an ATTENTION definition.

### Conditions

- The ATTENTION tag requires an end tag.

- You must code the ATTENTION tag within an INFO definition. See “INFO (Information Region)” on page 350 for a complete description of this tag.
- The ATTENTION tag must be immediately preceded by a P, LI, or LP tag. If the ATTENTION tag is coded on the same line as one of these tags, there can be no intervening blanks. See “P (Paragraph)” on page 406, “LI (List Item)” on page 358, and “LP (List Part)” on page 364 for descriptions of these tags.
- You cannot nest ATTENTION, WARNING or CAUTION tags within each other.

## Nested Tags

You can code the following tags within an ATTENTION definition:

Tag	Name	Usage	Page	Required
DL	Definition list	Multiple	292	No
FIG	Figure	Multiple	324	No
HP	Highlighted phrase	Multiple	348	No
LINES	Lines	Multiple	360	No
NOTE	Note	Multiple	396	No
NOTEL	Note List	Multiple	399	No
NT	Note	Multiple	402	No
OL	Ordered list	Multiple	404	No
P	Paragraph	Multiple	406	No
PARML	Parameter list	Multiple	424	No
PS	Point-and-Shoot	Multiple	438	No
RP	Reference phrase	Multiple	454	No
SL	Simple list	Multiple	480	No
UL	Unordered list	Multiple	491	No
XMP	Example	Multiple	508	No

## Example

The following help panel markup contains a warning statement. The warning statement starts at the left margin because it is embedded in the LP tag.

```
<!DOCTYPE DM SYSTEM>

<HELP NAME=attentn DEPTH=20>Help For Changing a File
<AREA>
<INFO>
  <OL>
    <LI>Type over the existing data
    in the entry fields with the new data.
    <LP><ATTENTION>Performing the next step will save
    all changes and delete the existing data.
    <P>To quit this function without
    deleting the existing data, press F12.
    </ATTENTION>
    <LI>Press Enter to save the
    updated data.
  </OL>
</INFO>
</AREA>
</HELP>
```






Figure 95. Attention Statement

## ATTR (Attribute)

The ATTR tag defines a panel attribute used within a dynamic area or a preformatted displayable panel section. Refer to the *ISPF Dialog Developer's Guide and Reference* for a complete discussion of panel )ATTR section keywords.



**ATTRCHAR=code**

This attribute can be a single character or a two-position entry of valid hex digits. If you enter an incorrect value, a warning message is issued and the value is set to null. Hex entries are converted to character. Hex values '00'-'2F' are reserved for use by the conversion utility.

**TYPE=DATAIN | DATAOUT | CHAR**

This attribute specifies the characteristic of the field within the dynamic area. Use DATAIN and DATAOUT attribute values for specifying unprotected or protected fields, respectively, within the dynamic area. The CHAR attribute value defines a character attribute that is recognized only when found within a shadow variable.

When the ATTR tag is coded within the GENERATE tag, TYPE can also be specified as any CUA attribute type, or as %varname.

**INTENS=HIGH | LOW | NON | %varname**

This attribute defines the intensity of a field. You can define this attribute as a variable name preceded by a "%".

**CAPS=OFF | ON | IN | OUT | %varname**

This attribute specifies the uppercase or lowercase attribute of a field. You can define this attribute as a variable name preceded by a "%".

**JUST=ASIS | LEFT | RIGHT | %varname**

This attribute specifies how the contents of the field are to be justified when displayed. You can define this attribute as a variable name preceded by a "%".

**PAD=NULLS | USER | char | %varname**

This attribute specifies the pad character for initializing the field. You can define this attribute as a variable name preceded by a "%".

**PADC=NULLS | USER | char | %varname**

This attribute specifies the conditional padding character to be used for initializing the field. You can define this attribute as a variable name preceded by a "%".

**SKIP=OFF | ON | %varname**

This attribute specifies the autoskip attribute of the field. You can define this attribute as a variable name preceded by a "%".

**GE=OFF | ON | %varname**

This attribute specifies that ISPF will place a graphic escape order before the character defined as a character level attribute by TYPE=CHAR. You can define this attribute as a variable name preceded by a "%".

**COLOR=WHITE | RED | BLUE | GREEN | PINK | YELLOW | TURQ | %varname**

This attribute specifies the color of the field. You can define this attribute as a variable name preceded by a "%".

**HILITE=USCORE | BLINK | REVERSE | %varname**

This attribute specifies the extended highlighting attribute of the field. You can define this attribute as a variable name preceded by a "%".

**NUMERIC=OFF | ON | %varname**

This attribute specifies whether Numeric Lock is to be activated for data typed in the field. You can define this attribute as a variable name preceded by a "%".

**FORMAT=EBCDIC | DBCS | MIX | %varname**

This attribute specifies the character format for the field. You can define this attribute as a variable name preceded by a "%".

**OUTLINE=NONE | L | R | O | U | BOX | %varname**

This attribute provides for displaying lines around the field on a DBCS terminal. You can define this attribute as a variable name preceded by a "%".

**PAS=OFF | ON | %varname**

This attribute controls the availability of the point-and-shoot function for dynamic areas. You can define this attribute as a variable name preceded by a "%".

**CKBOX=OFF | ON | %varname**

This attribute controls the generation of check boxes for dynamic areas when the panel is displayed while running in GUI mode. You can define this attribute as a variable name preceded by "%".

**CUADYN=CEF | EE | LEF | NEF | VOI | LID | LI | CH | CT | DT | ET | FP | NT | PIN | PT | SAC | SI | SUC | WASL | WT | %varname**

This attribute specifies a standard CUA attribute for the DATAIN and DATAOUT panel attribute definitions.

Values CEF, EE, LEF, and NEF are valid when TYPE=DATAIN. The remaining values are valid when TYPE=DATAOUT. You can define this attribute as a variable name preceded by a "%".

The conversion utility will issue a warning message if the CUADYN attribute is specified and the invocation option is NOCUAATTR.

**CSRGRP=NO | YES | n**

The CSRGRP attribute is valid only when TYPE=DATAOUT. When CSRGRP=YES, the conversion utility generates a cursor group number to be used for this DATAOUT attribute. When CSRGRP=n, the number provided is used for this attribute. The PAS attribute must be specified as ON or %varname.

**ATTN=NO | YES | %varname**

This attribute specifies the attention-select attribute of the field. You can define this attribute as a variable name preceded by a "%".

## Description

The ATTR tag is used to create an entry in the )ATTR panel section for fields to be displayed within a dynamic area, or preformatted panel section.

## Conditions

- You must code an ATTR tag within a Dynamic Area or GENERATE tag definition. See "DA (Dynamic Area)" on page 280 and "GENERATE (Generate)" on page 330 for a complete description of these tags.
- If ATTRCHAR is not specified, an error is logged and the output panel is not saved.
- If ATTRCHAR is a duplicate of a previously specified attribute, or conflicts with an attribute reserved by the conversion utility, an error is logged and the output panel is not saved.
- If TYPE is not specified, an error is logged and the output panel is not saved. If TYPE is specified, but the value is invalid, the value is set to DATAIN.
- If both PAD and PADC have been specified, PAD is ignored and PADC is used.
- When a "%varname" notation is found on any of the attributes that allow a variable name, the "%varname" entry must follow the standard naming convention described in "Rules for "%variable" Names" on page 205.

## Nested Tags

None.

## Example

```

<!DOCTYPE DM SYSTEM(
  <!entity sampvar1 system>
  <!entity sampabc system>)>
&sampvar1;

<PANEL NAME=attr KEYLIST=keyl xmp>Library Card Registration
<AB>
&sampabc;
</AB>
<TOPINST> Type in patron's name and card number (if applicable)
<AREA>
  <DTACOL PMTWIDTH=12 ENTWIDTH=25 DESWIDTH=25 SELWIDTH=25>
  <DTAFLD DATAVAR=curdate USAGE=out ENTWIDTH=8>Date
  <DTAFLD DATAVAR=cardno ENTWIDTH=7>Card No.
    <DTAFLDD>(A 7-digit number)
  <DTAFLD DATAVAR=name>Name
    <DTAFLDD>(Last, First, M.I.)
  <DTAFLD DATAVAR=address>Address
</DTACOL>
<DIVIDER>
<DA NAME=darea DIV=solid DEPTH=6 SHADOW=shadwvar>
  <ATTR ATTRCHAR=# TYPE=datain PADC='_' COLOR=BLUE>
  <ATTR ATTRCHAR=| TYPE=dataout COLOR=green>
  <ATTR ATTRCHAR=$ TYPE=char COLOR=red>
</DA>
</AREA>
<CMDAREA>Enter a command
</PANEL>

```

---

## BOTINST (Bottom Instruction)

The BOTINST tag defines bottom instructions for an application panel.

```

--<BOTINST [COMPACT] [instruction-text] </BOTINST>

```

### COMPACT

This attribute causes the bottom instruction to format without a blank line before the text.

### instruction-text

This is the text of the bottom instruction. The *instruction-text* must fit in the remaining panel depth.

## Description

The BOTINST tag defines bottom instructions for an application panel. The *instruction-text* formats as a paragraph based on the width of the application panel. You can code multiple paragraphs of instruction text by using a new bottom instruction tag for each new paragraph.

If the COMPACT attribute is not specified, the conversion utility inserts a blank line before the bottom instruction text.

## Conditions

- You must code the BOTINST within a PANEL definition. See “PANEL (Panel)” on page 413 for a complete description of this tag.

- You cannot code a BOTINST tag within an AREA definition. If you define an area for the panel, code the BOTINST tag after the AREA end tag.

## Nested Tags

You can code the following tags within a BOTINST definition:

Tag	Name	Usage	Page	Required
HP	Highlighted phrase	Multiple	348	No
PS	Point-and-Shoot	Multiple	438	No
RP	Reference phrase	Multiple	454	No

## Example

The following application panel markup contains two bottom instructions. Figure 96 shows the formatted result.

```
<!DOCTYPE DM SYSTEM>

<VARCLASS NAME=choiccls TYPE='char 2' >
<VARLIST>
  <VARDCL NAME=choices VARCLASS=choiccls>
</VARLIST>

<PANEL NAME=botinst1 WIDTH=35 DEPTH=22>Four Choices
<AREA>
  <SELFLD NAME=choices PMTWIDTH=20 SELWIDTH=33>Choose one:
    <CHOICE>Raindrops on roses
    <CHOICE>Whiskers on kittens
    <CHOICE>Bright copper kettles
    <CHOICE>Warm woolen mittens
  </SELFLD>
</AREA>
<BOTINST>Press Enter to continue.
<BOTINST>Press F12 to cancel.
</PANEL>
```

## CAUTION




Figure 96. Bottom Instructions

---

## CAUTION (Caution)

The CAUTION tag defines a statement that alerts the user of a possible risk.

```
—<CAUTION>—┐└</CAUTION>—
```

└text┘

**text** This is the text of the caution statement.

### Description

The CAUTION tag defines a statement that alerts the user of a possible risk. Use the CAUTION tag to alert the user to a condition that might have serious consequences, such as the deletion of a file.

The CAUTION tag is one of the tags that alert the user to a possible risk; the others are ATTENTION and WARNING.

Code a caution statement before the text to which it pertains so that the user can read about the possible risks before reading the text. When a caution statement is displayed, the string "CAUTION:" or its translated equivalent appears on the screen and the caution text displays on the following line.

You can code additional paragraphs of caution text by coding the P (paragraph) tag within a CAUTION definition. You can also code other tags allowed in an information area within a CAUTION definition.

CAUTION text is formatted with an attribute byte that causes it to be emphasized.

### Conditions

- The CAUTION tag requires an end tag.

- A CAUTION tag must be immediately preceded by an LI, LP, or P tag. See “LI (List Item)” on page 358, “LP (List Part)” on page 364, and “P (Paragraph)” on page 406 for descriptions of these tags.
- You must code the CAUTION tag only within an INFO definition. See “INFO (Information Region)” on page 350 for a complete description of this tag.
- You cannot nest ATTENTION, CAUTION, or WARNING tags within each other.

## Nested Tags

You can code the following tags within a CAUTION definition:

Tag	Name	Usage	Page	Required
DL	Definition list	Multiple	292	No
FIG	Figure	Multiple	324	No
HP	Highlighted phrase	Multiple	348	No
LINES	Lines	Multiple	360	No
NOTE	Note	Multiple	396	No
NOTEL	Note list	Multiple	399	No
NT	Note	Multiple	402	No
OL	Ordered list	Multiple	404	No
P	Paragraph	Multiple	406	No
PARML	Parameter list	Multiple	424	No
PS	Point-and-Shoot	Multiple	438	No
RP	Reference phrase	Multiple	454	No
SL	Simple list	Multiple	480	No
UL	Unordered list	Multiple	491	No
XMP	Example	Multiple	508	No

## Example

The following help panel markup contains a caution statement. Figure 97 on page 236 shows the formatted result.

```
<!DOCTYPE DM SYSTEM>


<HELP NAME=caution DEPTH=20>Help for DELETE Command
<AREA>
  <INFO>
    <P>The DELETE command erases the specified file from storage.
    <P><CAUTION>
      Issuing the DELETE command permanently
      removes the file from storage.
      There is no possibility of recovery.
    </CAUTION>
    <P>You can exit from the DELETE operation
    by pressing F12.
  </INFO>
</AREA>
</HELP>
```



Figure 97. Caution Statement

## CHDIV (Choice Divider)

The CHDIV tag creates a blank or visible divider between CHOICE tags.



### **TYPE=NONE | SOLID | DASH | TEXT**

This attribute specifies the type of divider line. The line width is one character.

The default value is *none*, which produces a blank line. You must specify *solid*, *dash*, or *text* to produce a visible divider line. When the GRAPHIC invocation option is specified, SOLID produces a solid line for host display and DASH produces a dashed line. When NOGRAPHIC is specified or the panel is displayed in GUI mode, both SOLID and DASH produce a dashed line.

### **GUTTER=1 | n**

This attribute specifies the total width of the divider. If the GUTTER value is an even number, the conversion utility increases the number by 1 so that the divider is centered within the defined width.

The minimum and default GUTTER value is 1.

### **FORMAT=START | CENTER | END**

This attribute specifies the position of the divider text within the width of the divider line. The divider width is the same as the CHOICE tag text formatting width.

### **divider-text**

This is the text of the choice divider.

## Description

The CHDIV tag creates a blank or solid divider between CHOICE tags.

## Conditions

- You must code the CHDIV tag within an SELFLD definition. See “SELFLD (Selection Field)” on page 464 for a description of this tag.

## Nested Tags

You can code the following tags within a CHDIV definition:

Tag	Name	Usage	Page	Required
HP	Highlighted phrase	Multiple	348	No

## Example

The following example illustrates the creation of an ISPF selection menu. The CHDIV tag is included to separate the Exit option from the other selection choices. The FCHOICE attribute specifies that the first selection number is 0. The choice selection for Exit is specified on the CHOICE tag. The ACTION tag for the Exit choice selection specifies both the RUN and TYPE attributes because RUN is required on the ACTION tag and TYPE is necessary to specify the ISPF selection for the generated ZSEL panel statement.

```
<!doctype dm system (>
<!-- Sample selection menu -->
<varclass name=vc1 type='char 80'>
  <xlat1 format=upper>
    </xlat1>

<varlist>
  <vardcl name=zcmd varclass=vc1>
</varlist>

<panel name=chdiv1 menu keylist=keylxmlp>
  Sample Selection Panel with CHDIV tag
  <topinst>This is a selection panel.
  <selfld type=menu pmtloc=before fchoice=0 trail=nextsel
    selwidth=40 pmtwidth=10>Select an option
    <choice checkvar=xtest1 match=a>
      Selection #0 (Command Selch0)
      <action run=Selch0>
    <choice checkvar=xtest1 match=b>
      Selection #1 (Command Selch1)
      <action run=Selch1 parm='1 2 3 4'
        passlib newpool suspend>
    <choice checkvar=xtest1 match=c>
      Selection #2 (Command Selch2)
      <action run=Selch2 parm=1234>
    <choice checkvar=xtest1 match=d>
      Selection #3 (Command Selch3)
      <action run=Selch3 parm=abcd>
    <choice checkvar=xtest1 match=e>
      Selection #4 (Command Selch4)
      <action run=Selch4 parm='a b c d'>
    <bchdiv>
    <choice selchar=X>
      Exit
      <action run=exit type=exit>
  </selfld>
  <cmdarea>
</panel>
```

## CHDIV

Figure 98 shows the formatted result.

```
Sample Selection Panel with CHDIV tag
Option ==> _____
This is a selection panel.
Select an
option . . 0 Selection #0 (Command Selch0)
           1 Selection #1 (Command Selch1)
           2 Selection #2 (Command Selch2)
           3 Selection #3 (Command Selch3)
           4 Selection #4 (Command Selch4)
           X Exit
Option ==> _____
F1=Hel p      F3=Exi t      F5=Di spl ay      F6=Keyshel p      F10=Acti ons
F12=Cancel
```

Figure 98. Choice Divider

---

## CHECKI (Validity Check Item)

The CHECKI tag defines a test of an input value.

```
--<CHECKI--TYPE=--| First set of Keywords |-->
                                   |</CHECKI>|
```

### First set of Keywords

RANGE	PARM1=	low-bound	PARM2=	high-bound
		%varname		%varname
ALPHA				
CHARS	PARM1=EQ		PARM2=character-set	
VALUES	PARM1=EQ		PARM2=value-list	
VALUESX	PARM1=NE		PARM2=value-list	
BIT				
NAME				
NAMEF				
PICT	PARM1=EQ		PARM2=pictstring	
PICTCN	PARM1=mask-character		PARM2=field-mask	PARM3=string
NUM				
DBCS				
LISTV	PARM1=EQ		PARM2=varlist	
LISTVX	PARM1=NE		PARM2=varlist	
ALPHAB				
LEN	PARM1=	operator	PARM2=	length
		%varname		%varname
EBCDIC				
ENUM				
DSNAME				
DSNAMEF				
DSNAMEFM				
DSNAMEPQ				
DSNAMEQ				
MIX				
HEX				
FILEID				
INCLUDE		PARM1=IMBLK	PARM2=	ALPHA
				ALPHAB
				NUM
			PARM3=	ALPHA
				ALPHAB
				NUM
DATE				
STDDATE				
JDATE				
JSTD				
ITIME				
STDTIME				
IPADDR4				

**TYPE=**

This attribute specifies the type of check to be performed. The valid types are:

**RANGE**

This allows you to check for an integer value within a range. The specified range includes the end points. The range delimiters can include 16 digits. The range delimiters can also contain a sign (- or +). If no sign is coded, the value is assumed to be positive.

## CHECKI

### Attention:

In ISPF, the VER(variable RANGE,lower,upper) statement limits the length of the specified variable to 16 digits. If the application developer specifies the CHECKI TYPE=RANGE on a variable that is longer than 16 positions in length, the variable may not be correctly validated.

For example, assume an application developer defines a data field with a length of 20 and defines the following validity check for the field:

```
<CHECKI TYPE=RANGE PARM1=1 PARM2=9999999999999999>
```

If the number 12345678901234567890 were entered into the field, only the first 16 digits of the field would be verified and the number would be within the defined range, even though the entire number entered is outside of the defined range.

### **PARM1=low-bound | %varname**

This attribute supplies the low value, if any or the name of a variable that contains the low value. If you do not supply a value, the default is “ -” followed by sixteen 9s (that is, -9999...99). Negative values must be coded with the minus sign on the left.

ISPF restrictions on the VER(variable RANGE,lower,upper) apply. The lower value specified in PARM1 can be positive or negative. The length of the lower limit is limited to 16 digits, in addition to the plus or minus sign if used.

### **PARM2=high-bound | %varname**

This attribute supplies the high value, if any or the name of a variable that contains the high value. If you do not supply a value, the default is sixteen 9s (that is, 9999...99). Negative values must be coded with the minus sign on the left.

ISPF restrictions on the VER(variable RANGE,lower,upper) apply. The upper value specified in PARM2 can be positive or negative. The length of the upper limit is limited to 16 digits, in addition to the plus or minus sign if used.

### **ALPHA**

This limits the character set to A-Z, a-z, and #, \$, @. The conversion utility builds the VER(variable ALPHA) statement.

### **CHARS**

Specifies the CHARS check of characters allowed within an input string.

The conversion utility uses the TYPE=CHARS check to support ISPF VER(variable BIT), VER(variable HEX) and VER(variable NUM). BIT, HEX, and NUM are the only types of support provided by ISPF for the TYPE=CHARS check.

### **PARM1=EQ**

This attribute contains EQ to specify that PARM2 contains a value that must be matched. If PARM1 contains any other value, the check is ignored and the conversion utility issues a warning message.

### **PARM2=character-set**

This attribute specifies a set of characters to be matched.

- If TYPE=CHARS, PARM1='EQ', and PARM2='01', the conversion utility generates VER(variable BIT).

- If TYPE=CHARS, PARM1='EQ', and PARM2='0123456789ABCDEFabcdef', the conversion utility generates VER(variable HEX).
- If TYPE=CHARS, PARM1='EQ', and PARM2='0123456789', the conversion utility generates VER(variable NUM).

**Note:** If these options are used, the PARM2 value must be specified exactly as shown above.

- If PARM2 contains any other values, the check is ignored and the conversion utility issues a warning message.

## VALUES

Specifies that the value entered must be the same as one of the values specified in PARM2.

The VER LIST statement built by the conversion utility is case-sensitive to the values entered in PARM2 (no folding of PARM2 to uppercase). This means that ISPF looks for an exact match in the verification process. You can specify XLATL FORMAT=UPPER within the variable class definition before the CHECKL tag to convert user input to uppercase before the VALUES check is processed.

### PARM1=EQ

This attribute contains EQ to specify that PARM2 contains values that must be matched. If PARM1 contains any other value, the check is ignored and the conversion utility issues a warning message.

### PARM2=value-list

This attribute specifies the list of values. If the list contains more than one value, it must be enclosed in quotes. If a value in the list contains blanks, then it must be enclosed in single quotes and the entire list enclosed in double quotes. Each value in the list must be separated by blanks or enclosed quotes. For example:

```
dog
'dog cat bird lion'
"parsley onion 'black pepper' garlic"
```

The maximum number of values allowed is 100.

**Note:** You should surround the entire value for PARM2 with double quotes and then surround any value in the list that contains blanks with single quotes. Double quotes surrounding a list are supported by the conversion utility.

The conversion utility generates VER(variable LIST,value-list) from PARM2.

## VALUESX

Specifies that the value entered cannot be any of the values specified in PARM2. This is the opposite of VALUES.

The VER LISTX statement built by the conversion utility is case-sensitive to the values entered in PARM2 (no folding of PARM2 to uppercase). This means that ISPF looks for an exact match in the verification process. You can specify XLATL FORMAT=UPPER within the variable class definition before the CHECKL tag to convert user input to uppercase before the VALUES check is processed.

### PARM1=NE

this attribute contains ne to specify that parm2 contains values that

## CHECKI

cannot be entered. If parm1 contains any other value, the check is ignored and the conversion utility issues a warning message.

### PARM2=VALUE-LIST

This attribute specifies the list of values. If the list contains more than one value, it must be enclosed in quotes. If a value in the list contains blanks, then it must be enclosed in single quotes and the entire list enclosed in double quotes. Each value in the list must be separated by blanks or enclosed quotes. For example:

```
dog  
'dog cat bird lion'  
"parsley onion 'black pepper' garlic"
```

The maximum number of values allowed is 100.

**Note:** You should surround the entire value for PARM2 with double quotes and then surround any value in the list that contains blanks with single quotes. Double quotes surrounding a list are supported by the conversion utility.

The conversion utility generates VER(variable LISTX,value-list) from PARM2.

### BIT

Specifies that the variable must be all 0's and 1's. The conversion utility builds the VER(variable BIT) statement.

### NAME

Specifies that the variable must contain a valid name, following the rules of member names. The conversion utility builds the VER(variable NAME) statement.

### NAMEF

Specifies that the variable must contain a valid name filter. The conversion utility builds the VER(variable NAMEF) statement.

### PICT

Specifies that the variable must contain characters that match the corresponding type of character in *pictstring*.

### PARM1=EQ

This attribute contains EQ to specify that PARM2 contains values that must be matched. If PARM1 contains any other value, the check is ignored and the conversion utility issues a warning message.

### PARM2=pictstring

This 'pictstring' parameter must be the actual value to be used in the generated VER statement. ISPF does not support a variable name for this value.

If PARM2 contains invalid characters as defined by ISPF, the check is ignored and the conversion utility issues a warning message.

The conversion utility builds the VER(variable PICT,pictstring) statement.

### PICTCN

Specifies that the variable must contain specific constants along with other standard ISPF picture verification characters.

**PARM1=mask-character**

The mask-character is any special character that represents itself. It cannot be one of the ISPF picture string characters (C,A,N,X,9,c,a,n,x)

**PARM2=field-mask**

The field-mask provides the required characters for the field. All other field positions must be represented by the mask-character. For example, if the field is to contain a string **VnnRnnMnn** (for Version, Release, and Modification) and the mask-character is an asterisk (\*), the field mask is **V\*\*R\*\*M\*\***.

**PARM3=string**

The string must be the same length as the field-mask. It contains all of the required characters in the same positions as the field-mask. The positions defined with the mask-character in the field-mask contain one of the standard ISPF picture characters (C,A,N,X,9,c,a,n,x). To complete the example used above, the string is **VnnRnnMnn**. The resulting verification statement is:

```
VER(variable,PICTCN,*,V**R**M**,VnnRnnMnn)
```

The variable is verified for **V** in position 1, **R** in position 4, **M** in position 7, and numeric characters in positions 2,3,5,6,8, and 9.

The conversion utility builds the `VER(variable,PICTCN,mask-character,field-mask,string)` statement.

**NUM**

Specifies that the variable must contain all numeric characters (0–9). The conversion utility builds the `VER(variable NUM)` statement.

**DBCS**

Specifies that the variable must contain all valid DBCS characters. The conversion utility builds the `VER(variable DBCS)` statement.

**LISTV**

Specifies that the variable must be one of the values provided by *varlist*.

**PARM1=EQ**

This attribute contains **EQ** to specify that **PARM2** contains values that must be matched. If **PARM1** contains any other value, the check is ignored and the conversion utility issues a warning message.

**PARM2=%varlist**

This attribute must be a variable name entered with “%” as the first character. The variable contents are provided by the application and must be a list of valid values.

The conversion utility builds the `VER(variable LISTV,&varlist)` statement.

**LISTVX**

Specifies that the variable cannot be any of the values provided by *varlist*. This is the opposite of **LISTV**.

**PARM1=NE**

This attribute contains **NE** to specify that **PARM2** contains values that cannot be entered. If **PARM1** contains any other value, the check is ignored and the conversion utility issues a warning message.

**PARM2=%VARLIST**

This attribute must be a variable name entered with “%” as the first

character. The variable contents are provided by the application and must be a valid list of excluded values.

The conversion utility builds the VER(variable LISTVX,&varlist) statement.

**ALPHAB**

Specifies that the variable must be all alphabetic characters (A–Z or a–z). The conversion utility builds the VER(variable ALPHAB) statement.

**LEN**

Specifies that the variable must satisfy the condition expressed by the relational operator and the expected length.

**PARM1=operator | %varname**

This attribute can be a relational operator (EQ, LT, GT, LE, GE, NE, NG, or NL) or a variable name that contains a relational operator. If a variable name is entered, it must be preceded by a “%”.

**PARM2=length | %varname**

The parameter must be either a number or a variable name. If a number is entered, it must be in the range of 1–99999. If a variable name is entered, it must be preceded by a “%”.

The conversion utility builds the VER(variable operator,length) statement.

**EBCDIC**

Specifies that the variable must contain all valid EBCDIC characters. The conversion utility builds the VER(variable EBDIC) statement.

**ENUM**

Specifies that the variable can contain extended numeric notation. The conversion utility builds the VER(variable ENUM) statement.

**DSNAME**

Specifies that the variable must contain a valid TSO data set name. The conversion utility builds the VER(variable DSNAME) statement.

**DSNAMEF**

Specifies that the variable must contain a valid TSO data set name filter. The optional member name cannot be specified as a member pattern. A missing close parentheses and ending quotation mark are automatically added by ISPF. The conversion utility builds the VER(variable DSNAMEF) statement.

**DSNAMEFM**

Specifies that the variable must contain a valid data set name. The optional member name can be specified as a member pattern. A missing close parentheses and ending quotation mark are automatically added by ISPF. The conversion utility builds the VER(variable DSNAMEFM) statement.

**DSNAMEPQ**

Specifies that the variable must contain a valid TSO data set name. A missing close parentheses and ending quotation mark are automatically added by ISPF. The conversion utility builds the VER(variable DSNAMEPQ) statement.

**DSNAMEQ**

Specifies that the variable must contain a valid TSO data set name. A missing ending quotation mark is automatically added by ISPF. The conversion utility builds the VER(variable DSNAMEQ) statement.

**MIX**

Specifies that the variable must contain all valid DBCS and EBCDIC characters. The conversion utility builds the VER(variable MIX) statement.

**HEX**

Specifies that the variable must contain all hexadecimal characters (0–9, a–f or A–F). The conversion utility builds the VER(variable HEX) statement.

**FILEID**

Specifies that the variable must contain a valid file ID in CMS syntax. The conversion utility builds the VER(variable FILEID) statement.

Refer to the *ISPF User's Guide* for additional information concerning panel variable validation.

**INCLUDE**

Specifies that the variable must contain valid characters from at least one of the ISPF defined VER groups ALPHA, ALPHAB or NUM.

**PARM1=IMBLK**

This attribute contains IMBLK to specify that the IMBLK keyword be added to the generated VER statement. If PARM1 contains any other value, it will be reset to the value IMBLK.

**PARM2=ALPHA | ALPHAB | NUM**

This attribute must contain either the value ALPHA, ALPHAB, or NUM. If PARM2 is not specified or contains any other value, the INCLUDE check is ignored and the conversion utility issues a warning message.

**PARM3=ALPHA | ALPHAB | NUM**

This attribute must contain either the value ALPHA, ALPHAB, or NUM. The value specified for PARM3 should be different than the value specified for PARM2. If the values for PARM2 and PARM3 are the same, the PARM3 value is ignored and the conversion utility issues a warning message.

The conversion utility builds the VER(variable INCLUDE [,IMBLK], parm2 [,parm3]) statement.

**IDATE**

Specifies that the variable must contain a valid 8 character international date. The conversion utility builds the VER(variable,IDATE) statement.

**STDDATE**

Specifies that the variable must contain a valid 10 character standard date. The conversion utility builds the VER(variable,STDDATE) statement.

**JDATE**

Specifies that the variable must contain a valid 6 character Julian date. The conversion utility builds the VER(variable,JDATE) statement.

**JSTD**

Specifies that the variable must contain a valid 8 character standard Julian date. The conversion utility builds the VER(variable,JSTD) statement.

**ITIME**

Specifies that the variable must contain a valid 5 character international time. The conversion utility builds the VER(variable,ITIME) statement.

## CHECKI

### STDTIME

Specifies that the variable must contain a valid 8 character standard time. The conversion utility builds the VER(variable,STDTIME) statement.

### IPADDR4

Specifies that the variable must contain a valid 15-position IP address. The conversion utility builds the VER(variable,IPADDR4) statement.

#### Compatibility Considerations

In ISPF Version 3.1, the conversion utility also supported the CHECKI attribute and value TYPE=NUMERIC. If used, the conversion utility will generate a VER(variable ENUM) and a warning message. This support provides backward compatibility with ISPF Version 3.1.

You should now use the TYPE=NUMERIC attribute of the VARCLASS tag to specify that checking for a numeric value should be performed. See "VARCLASS (Variable Class)" on page 493 for more information.

## Description

The CHECKI tag defines a test of an input value. Validity checking occurs only on input.

## Conditions

- You must code the CHECKI tag within a CHECKL definition. The conversion utility supports only one CHECKI within each CHECKL definition. If multiple CHECKI definitions are coded within a single CHECKL definition, the additional CHECKI tags are ignored and are not syntax checked. See "CHECKL (Validity Check List)" on page 247 for a complete description of this tag.
- The conversion utility builds a VER statement in the ISPF )PROC section of the panel definition for a CHECKI tag.
- When a "%varname" notation is found on any of the attributes that allow a variable name, the "%varname" entry must follow the standard naming convention described in "Rules for "%variable" Names" on page 205.

## Nested Tags

None.

## Example

In this example, variables associated with the variable class *aa* must have a value that contains only alphabetic characters. Values associated with the variable class *bb* can only be SINGLE or DOUBLE.

```

<!DOCTYPE DM SYSTEM>

<VARCLASS NAME=aa TYPE='char 18' >
  <CHECKL MSG=msgF881>
    <CHECKI TYPE=ALPHA>
  </CHECKL>

<VARCLASS NAME=bb TYPE='char 6' >
  <XLATL FORMAT=upper>
</XLATL>
  <CHECKL MSG=msgF883>
    <CHECKI TYPE=VALUES PARM1=EQ PARM2="SINGLE DOUBLE">
  </CHECKL>

<VARLIST>
  <VARDCL NAME=checka VARCLASS=aa>
  <VARDCL NAME=checkb VARCLASS=bb>
</VARLIST>

<PANEL NAME=checki><CHECKI audits
  <DTAFLD DATAVAR=checka ENTWIDTH=18 PMTWIDTH=20>Enter Last Name
  <DTAFLD DATAVAR=checkb ENTWIDTH=6 PMTWIDTH=20>Enter Room Type
  <CMDAREA>
</PANEL>

```

---

## CHECKKL (Validity Check List)

The CHECKKL tag defines a validity check for input variables.

```

—<CHECKL _____>—</CHECKL>—
      |MSG=message-identifier|

```

### MSG=message-identifier

This attribute identifies the message to be issued if the value fails the embedded test. The conversion utility adds this *message-identifier* to the VER statement generated by the enclosed CHECKI tag. If you do not specify your own message, ISPF issues a message specified on the enclosing VARCLASS tag or the default message associated with the type of VER statement generated. See “MSG (Message)” on page 390 for information about creating messages.

## Description

The CHECKKL tag defines a validity check for input variables. The CHECKI tag coded within the check list performs the validation test.

Field validity checking follows standard ISPF conventions based on the verification statements generated. For details, see “CHECKI (Validity Check Item)” on page 238.

## Conditions

- The CHECKKL tag requires an end tag.
- You must code the CHECKKL tag within a VARCLASS definition. See “VARCLASS (Variable Class)” on page 493 for a complete description of this tag.
- The CHECKKL tag must be coded after any and all XLATL tags in the same variable class.

## CHECKL

### Nested Tags

You can code the following tag within a CHECKL definition:

Tag	Name	Usage	Page	Required
CHECKI	Validity check item	Single	238	No

### Example

The following source file markup contains two variable classes that each contain a validity check list. The second variable class also contains a translate list that translates variable values to uppercase. Notice that the translate list is coded in the variable class before the validity check list.

```
<!DOCTYPE DM SYSTEM>

<VARCLASS NAME=aa TYPE='char 18' >
  <CHECKL MSG=msgf881>
    <CHECKI TYPE=ALPHA>
  </CHECKL>

<VARCLASS NAME=bb TYPE='char 6' >
  <XLATL FORMAT=upper>
  </XLATL>
  <CHECKL MSG=msgf883>
    <CHECKI TYPE=VALUES PARM1=EQ PARM2="SINGLE DOUBLE">
  </CHECKL>


<VARLIST>
  <VARDCL NAME=checka VARCLASS=aa>
  <VARDCL NAME=checkb VARCLASS=bb>
</VARLIST>


<PANEL NAME=checkI>CHECKL audits
  <DTAFLD DATAVAR=checka ENTWIDTH=18 PMTWIDTH=20>Enter Last Name
  <DTAFLD DATAVAR=checkb ENTWIDTH=6 PMTWIDTH=20>Enter Room Type
  <CMDAREA>
</PANEL>
```

---


## CHOFLD (Choice Data Field)

The CHOFLD tag defines an input field, an output field, or an input/output field within the text of a CHOICE tag.





**IMAP Options:**



**DATAVAR=field-data**

This attribute specifies the variable name for the data in the field. The value coded must be a variable-name without the leading % notation.

**VARCLASS=variable-class-name**

This attribute specifies the name of the variable class, defined using a VARCLASS tag, that overrides the default variable class referred to by the VARDCL that declared the data variable for this field.

**HELP=**NO | YES | **help-panel-name** | \***help-message-id** | %**varname** | \*%**varname**

This attribute specifies the help action taken when the user requests help for this choice data field. This is field-level help.

When HELP=YES, control is returned to the application. You can specify either a help panel or a message identifier. If a message identifier is used, it must be prefixed with an asterisk (\*).

The help attribute value can be specified as a variable name. When %**varname** is coded, a panel variable name is created. When \*%**varname** is coded, a message variable name is created.

If the user requests help for the choice data field and no help is defined, the extended help panel is displayed. If an extended help panel is not defined for the panel, the application or ISPF tutorial is invoked.

The *help-panel-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

See “HELP (Help Panel)” on page 335 for information about creating help panels. For information about creating messages, see “MSG (Message)” on page 390.

**USAGE=**BOTH | IN | OUT

This attribute indicates whether the field is for input only, output only, or both.

**REQUIRED=**NO | YES

This attribute indicates if the field requires input. This attribute is valid only when USAGE=IN or BOTH.

If REQUIRED=YES is coded, a VER(variable,NONBLANK) statement will be built by the conversion utility and placed in the )PROC section of the ISPF panel generated.

**MSG=****message-identifier**

This attribute specifies the message that is displayed when the user does not complete a required entry (defined with the REQUIRED attribute). If you do not specify a *message-identifier*, ISPF displays a default message.

If you specify the MSG attribute and REQUIRED=YES, a VER(variable,NONBLANK,MSG=message-identifier) statement is built by the conversion utility and placed in the )PROC section of the ISPF panel generated. If you specify the MSG attribute and REQUIRED=NO (the default), the conversion utility issues a warning message.

See “MSG (Message)” on page 390 for information about creating messages.

**Note:** You can specify messages pertaining to other validations using XLATL and CHECKL tags within a VARCLASS definition. See the descriptions of these tags for additional information.

**AUTOTAB=**NO | YES

When AUTOTAB=YES, the cursor moves to the next field capable of input when the user enters the last character in this field. If no other field capable of user input exists on the panel, the cursor returns to the beginning of this field. The ISPF SKIP keyword is not supported when running in GUI mode.

AUTOTAB=YES is valid only when the value for USAGE is either BOTH or IN. If specified, this attribute overrides the AUTOTAB value of the DTACOL tag.

**ENTWIDTH=n**

This attribute specifies the number of bytes used for the choice data field. The minimum width is 1 and the maximum is the remaining available panel width, less the required amount of space for field attributes. If ENTWIDTH is not provided on either the CHOFLD tag or the enclosing DTACOL tag, the conversion utility will use the width determined by the TYPE value of the associated VARCLASS.

If specified, this attribute overrides the ENTWIDTH value of the DTACOL tag.

**FLDSPACE=n**

This attribute specifies the number of bytes reserved for the choice data field. The minimum width is 2 and the maximum is the remaining available panel (or region) width. The FLDSPACE value should include the actual entry width plus the number of entry field attributes. If the value specified by ENTWIDTH is less than the specified FLDSPACE value, the entry field is padded with blanks to the FLDSPACE value. This will create blank space between the entry field and following *choice-description-text* and allows you to align description text from successive CHOFLD definitions.

If specified, this attribute overrides the FLDSPACE value of the DTACOL tag.

**ALIGN=START | CENTER | END**

This attribute specifies the alignment of data within the display field after all translations have been performed. Use this attribute to align the data with the start, the end, or the center of the display field.

This is accomplished in the conversion utility by using an attribute character for the field that specifies JUST(LEFT) if ALIGN=START or JUST(RIGHT) if ALIGN=END. ALIGN=CENTER will use an attribute character for the field that specifies JUST(ASIS).

Alignment occurs if the transformed value of the dialog variable is shorter than the display width of the field. When ALIGN=END, there is no underscore padding performed. Instead, blanks are used.

**DISPLAY=YES | NO**

This attribute specifies whether data will display on the screen when the user types it in. If you specify NO, the data will not display. This attribute is useful when creating fields for passwords or other information which you do not want to appear on the screen.

**NOENDATTR**

This attribute, which is valid only when WINDOW=NO is specified on the PANEL tag or DIR=HORIZ is specified on the REGION tag, specifies that no ending attribute will be placed after the choice data field. NOENDATTR is ignored for the last field on each panel line unless WINDOW=NO has been specified on the PANEL tag. NOENDATTR is valid only when the CHOFLD tag is followed by a CHOFLD, CHOICE, or CHDIV tag.

**PAD=NULLS | USER | char | %varname**

This attribute specifies the pad character for initializing the field. You can define this attribute as a variable name preceded by a "%".

If specified, this attribute overrides the PAD value of the DTACOL tag.

**PADC=NULLS | USER | char | %varname**

This attribute specifies the conditional padding character to be used for initializing the field. You can define this attribute as a variable name preceded by a "%".

If specified, this attribute overrides the PADC value of the DTACOL tag.

**OUTLINE=NONE | L | R | O | U | BOX | %varname**

This attribute provides for displaying lines around the field on a DBCS terminal. You can define this attribute as a variable name preceded by a "%".

If specified, this attribute overrides the OUTLINE value of the DTACOL tag.

**PSVAR=point-and-shoot-variable | %varname**

This attribute provides the name of a variable that is to be set when a CHOFLD is clicked on for point-and-shoot selection. You can define this attribute as a variable name preceded by a "%".

The *point-and-shoot-variable* must follow the standard naming convention described in "Rules for Variable Names" on page 205.

**PSVAL=point-and-shoot-value | %varname**

This attribute provides the value to be placed in the field specified by the PSVAR attribute. You can define this attribute as a variable name preceded by a "%". To specify a blank value, the "' '" (quotation mark, apostrophe, blank, apostrophe, quotation mark) coding notation should be used.

**PAS=%varname**

This attribute can be used to provide a variable name to specify ON or OFF for point-and-shoot. When PSVAR and PSVAL have been specified without the PAS attribute, the point-and-shoot field will be automatically enabled.

**EXPAND**

The EXPAND attribute, used in combination with EXPAND=xy on the PANEL definition, causes the expand characters to be added to the CHOFLD definition, effectively allowing ENTWIDTH to expand. The ENTWIDTH value must be specified as 4 or greater for the EXPAND function to operate.

**Note:** If the PANEL tag attribute EXPAND is defined with no value specified, the CHOFLD tag EXPAND attribute is not used.

**ATTRCHANGE=NO | YES | NEW**

When ATTRCHANGE=YES or ATTRCHANGE=NEW, the conversion utility formats an additional entry in the panel )ATTR section (that can apply to multiple data fields) instead of creating a unique .ATTR(field-name) entry in the )INIT section for this field. With this option, multiple CHOFLD tags with the same characteristics require fewer panel logic statements. ATTRCHANGE=NEW creates a new entry. ATTRCHANGE=YES uses an existing entry, if possible.

**INIT=initial-value**

When the INIT attribute is specified, the conversion utility adds a statement to the panel )INIT section to initialize the field to the *initial-value*.

**IMAPNAME= image-name | %varname**

This attribute specifies the name of an image to be placed on the point-and-shoot push button when it is displayed in GUI mode. The *image-name* is not used when the panel is displayed in host mode.

The *image-name* must follow the standard naming convention described in "Rules for Variable Names" on page 205.

**IMAPNAMEP=image-namep | %varname**

This attribute specifies the name of an image to be placed on the point-and-shoot push button after it has been pushed when it is displayed in GUI mode. The *image-namep* is not used when the panel is displayed in host mode.

The *image-namep* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

**PLACE=ABOVE | BELOW | LEFT | RIGHT**

This attribute specifies the position of the image relative to the text within the point-and-shoot push button.

**ATTRCHAR=code**

This attribute can be a single character or a two-position entry of valid hex digits. If you enter an incorrect value, a warning message is issued and the value is set to null. Hex entries are converted to character. Hex values '00'-'2F' are reserved for use by the conversion utility.

**CAPS=OFF | ON**

When CAPS=ON, the data in the field is displayed in uppercase characters.

**choice-description-text**

This is the text for the choice data field. The *choice-description-text* appears following the field.

## Description

The CHOFLD tag is similar to the DTAFLD tag. When the enclosing SELFLD tag is defined within a DTACOL tag, the CHOFLD tag will use default values defined by the DTACOL tag in the same way as the DTAFLD tag.

The CHOFLD tag defines an input field, an output field, or an input/output field within CHOICE tag description text on an application panel.

The formatted width of the field is 2 positions more than the ENTWIDTH value to provide for an attribute byte both before and after the field.

## Conditions

- You must code the CHOFLD tag within a CHOICE tag definition. The CHOFLD tag can be placed anywhere within the *choice-description-text*. See “CHOICE (Selection Choice)” on page 255 for a description of this tag.
- The variable name specified in the DATAVAR attribute should have an associated VARDCL definition. See “VARDCL (Variable Declaration)” on page 497 for a complete description of this tag.
- If both PAD and PADC have been specified, PAD is ignored and PADC is used.
- When a “%varname” notation is found on any of the attributes that allow a variable name, the %varname entry must follow the standard naming convention described in “Rules for “%variable” Names” on page 205.

## Nested Tags

You can code the following tags within a CHOFLD definition:

Tag	Name	Usage	Page	Required
ACTION	Action	Multiple	211	No
COMMENT	Comment	Multiple	275	No
HP	Highlighted phrase	Multiple	348	No
PS	Point-and-Shoot	Multiple	438	No
RP	Reference phrase	Multiple	454	No
SOURCE	Source	Multiple	482	No

## Example

The following source file markup contains an application panel that is similar to the example for the CHOICE tag. In this example, the first selection field is modified to illustrate the CHOFLD tag. The first choice includes a panel input/output field named *cardtype* which must be completed when the *new* choice is selected.

Notice that the reference CHOICE source file has been modified to:

- Add a VARCLASS for the *cardtype* field *before* the include file which has both VARCLASS and VARDCL tags.
- Add a VARDCL for the *cardtype* field *after* the include file which has both VARCLASS and VARDCL tags.
- Add the CHOFLD tag to define the choice data field.
- Add a DTACOL tag definition to allow for a SOURCE tag that provides an audit of *cardtype* only when *new* is selected.

Figure 99 on page 255 shows the formatted result.

```
<!DOCTYPE DM SYSTEM(
  <!entity sampvar1 system>
  <!entity sampabc system>)>

<VARCLASS NAME=char9cls TYPE='char 9' >
  <XLATL FORMAT=upper>
  </XLATL>

&sampvar1;

<VARLIST>
  <VARDCL NAME=cardtype VARCLASS=char9cls>
</VARLIST>

<PANEL NAME=chofld KEYLIST=keyl xmp>Library Card Registration
<AB>
&sampabc;
</AB>
<TOPINST>Type in patron's name and card number (if applicable).
<TOPINST>Then select an action bar choice.
<AREA>
  <DTAFLD DATAVAR=curdate PMTWIDTH=12 ENTWIDTH=8 USAGE=out>Date
  <DTAFLD DATAVAR=cardno PMTWIDTH=12 ENTWIDTH=7 DESWIDTH=25>Card No
    <DTAFLDD>(A 7-digit number)
  <DTAFLD DATAVAR=name PMTWIDTH=12 ENTWIDTH=25 DESWIDTH=25>Name
    <DTAFLDD>(Last, First, M.I.)
  <DTAFLD DATAVAR=address PMTWIDTH=12 ENTWIDTH=25>Address
  <DIVIDER>
  <REGION DIR=horiz>
  <SELFLD NAME=cardsel PMTWIDTH=30 SELWIDTH=38>Choose
  one of the following
    <CHOICE CHECKVAR=card MATCH=new>
      New Type:
      <CHOFLD datavar=cardtype autotab=yes entwidth=9>
        (Permanent or Temporary)
  <CHOICE CHECKVAR=card MATCH=renew>Renewal
  <CHOICE CHECKVAR=card MATCH=replace>Replacement
  </SELFLD>
  <DTACOL>
  <SOURCE>
  IF (&CARSEL = 1)
    VER(&CARDTYPE, NB, LIST, TEMPORARY, PERMANENT)
  </SOURCE>
  </DTACOL>
  <SELFLD TYPE=multi PMTWIDTH=30 SELWIDTH=25>Check valid branches
```

```

<CHOICE NAME=north HELP=nthlp CHECKVAR=nth>North Branch
<CHOICE NAME=south HELP=sthhlp CHECKVAR=sth>South Branch
<CHOICE NAME=east HELP=esthlp CHECKVAR=est>East Branch
<CHOICE NAME=west HELP=wsthlp CHECKVAR=wst>West Branch
</SELFLD>
</REGION>
</AREA>
<CMDAREA>Enter a command
</PANEL>

```






Figure 99. Choice Data Fields

## CHOICE (Selection Choice)

The CHOICE tag defines information about a choice in a selection field.



## CHOICE



### NAME=choice-name

Specifies the name of the choice. The *choice-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

**Note:** This attribute is required for choices defined for a multiple-choice selection field because the *choice-name* is used as the input field for multiple choice selections.

For multiple-choice selection fields, the *choice-name* can also be used to position the cursor on the choice or to position a pop-up.

**Note:** This attribute is not supported by the conversion utility for single-choice selection fields. In this case, the NAME value of the SELFLD tag is used as the field name.

### HELP=NO | YES | help-panel-name | \*help-message-id | %varname | \*%varname

This attribute specifies the help action taken when the user requests for a multiple-choice selection field. This is field-level help.

When HELP=YES, control is returned to the application. You can specify either a help panel or a message identifier. If a message identifier is used, it must be prefixed with an asterisk (\*).

The help attribute value can be specified as a variable name. When %varname is coded, a panel variable name is created. When \*%varname is coded, a message variable name is created.

If the user requests help on a choice and no help is defined, the extended help panel is displayed. If an extended help panel is not defined for the panel, the application or ISPF tutorial is invoked.

The *help-panel-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

See “HELP (Help Panel)” on page 335 for information about creating help panels. For information about creating messages, see “MSG (Message)” on page 390.

**Note:** This attribute is valid only when the SELFLD tag has been specified with TYPE=MULTI.

### CHECKVAR=variable-name

This attribute defines a variable whose value indicates whether the choice is

preselected when the selection field is displayed. If the value of the variable is equivalent to the *string* you specify with the MATCH attribute, the item is marked as selected when the panel displays.

The preselection indicator depends on the value of the TYPE attribute from the SELFLD tag and whether the display mode is host or GUI.

TYPE	LISTTYPE	Host Display Indicator	GUI Display Indicator
MULTI	n/a	slash	check
SINGLE	(not used) RADIO LISTBOX DDLIS COMBO	Choice number Choice number Choice number Choice number Choice number	Choice number Radio button selected Choice highlighted in list Choice displayed in field Choice placed in field
MENU	n/a	Choice number	Choice number
MODEL	n/a	Choice number	Choice number
TUTOR	n/a	Choice number	Choice number

When the SELFLD tag has been specified with TYPE=MENU, TYPE=MODEL, or TYPE=TUTOR, the CHOICE number (or SELCHAR value) is placed in the command line.

The *variable-name* is updated to the value specified by the MATCH attribute when the user selects the choice being defined. For multiple-choice selection fields (SELFLD TYPE=MULTI), if you do not select a choice, or you deselect a choice, the associated *variable-name* is set to the value of the NOMATCH attribute or to 0 if the NOMATCH attribute is not specified.

Use a different variable for *variable-name* than what has been specified for *choice-name*.

Do not use the same variable for the *variable-name* as you use for the *variable-name* specified for the SETVAR or TOGVAR attributes of the ACTION tag.

For single-choice selection fields (SELFLD TYPE=SINGLE), ISPF selection menus (SELFLD TYPE=MENU), edit model selection menus (SELFLD TYPE=MODEL), or tutorial selection menus (SELFLD TYPE=TUTOR), the *variable-name* should be the same for all of the choices. For multiple-choice selection fields (SELFLD TYPE=MULTI), the *variable-name* should be different for each choice.

The CHECKVAR attribute value must be specified without a leading % sign. The *variable-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

#### **MATCH=1 | string**

Defines the value for the check variable that causes the item to be preselected. The *string* can be any character string. MATCH=1 is the default.

#### **NOMATCH=0 | string**

Defines the value for setting the check variable when the item is not selected. NOMATCH=0 is the default.

**Note:** This attribute is valid only when the SELFLD tag has been specified with TYPE=MULTI.

## CHOICE

### **AUTOTAB=**YES | NO

When **AUTOTAB=**YES, the cursor moves to the next field capable of input when the user enters the last character in this field. If no other field capable of user input exists on the panel, the cursor remains on this field.

The ISPF SKIP keyword is not supported when running in GUI mode.

**Note:** This attribute is valid only when the SELFLD tag has been specified with **TYPE=**MULTI.

### **SELCHAR=**'char(s),n'

This attribute specifies an alphanumeric character(s) to be used as the selection menu, edit model selection menu, or tutorial selection menu choice in place of the normal numeric value automatically supplied by the conversion utility. The number of characters accepted is controlled by the ENTWIDTH attribute of the SELFLD tag. The *char(s)* value is used as coded, that is, it is not uppercase.

When the HIDE attribute is also specified, the number of characters to be used for the hidden choice selection may be specified as part of the SELCHAR attribute. If specified, the *n* value overrides the number of characters normally obtained from the ENTWIDTH attribute of the SELFLD tag. The *n* value can be a numeric value from 1 to the number of bytes provided as the *char(s)* value, or you can specify an "\*" to tell the conversion utility to use all of the *char(s)* provided for the choice selection. The *n* value is ignored when the HIDE attribute is not specified.

**Note:** This attribute is valid only when the SELFLD tag has been specified with **TYPE=**MENU, **TYPE=**MODEL, or **TYPE=**TUTOR.

### **PAD=**NULLS | USER | char | %varname

This attribute specifies the pad character for initializing the field. You can define this attribute as a variable name preceded by a "%".

**Note:** This attribute is valid only when the SELFLD tag has been specified with **TYPE=**MULTI.

### **PADC=**NULLS | USER | char | %varname

This attribute specifies the conditional padding character to be used for initializing the field. You can define this attribute as a variable name preceded by a "%".

**Note:** This attribute is valid only when the SELFLD tag has been specified with **TYPE=**MULTI.

### **OUTLINE=**NONE | L | R | O | U | BOX | %varname

This attribute provides for displaying lines around the field on a DBCS terminal. You can define this attribute as a variable name preceded by a "%".

**Note:** This attribute is valid only when the SELFLD tag has been specified with **TYPE=**MULTI.

### **HIDE**

This attribute causes a choice entry for a single-choice, menu-choice, model-choice, or tutor-choice selection to be removed from the selection list display.

This allows the creation of a numbered selection list when the choice numbers are not continuous by adding a 'dummy' CHOICE tag at the appropriate place

in the DTL source. The number assigned to the hidden CHOICE does not appear in the selection list. Normal )INIT and )PROC section entries are not affected.

**Note:** This attribute is valid only when the SELFLD tag has been specified with TYPE=SINGLE, TYPE=MENU, TYPE=MODEL, or TYPE=TUTOR.

### HIDEX

This attribute causes a choice entry for a model-choice selection to be removed both from the selection list display and from the selection processing.

This attribute is used in combination with the TRUNC attribute and the SELCHAR attribute to supply an alternate CHOICE tag definition with an alternate hidden model selection keyword.

For example, if an edit model panel has a selectable description of "VER", but you also want to allow the full word "VERIFY" to select the same model, two CHOICE tags are required. The first one defines the choice with the text "VER". The alternate CHOICE uses the same SELCHAR information, adds the attribute HIDEX and TRUNC=3, and specifies the tag text as "VERIFY". The conversion utility uses the first definition to build the panel text and the selection processing statement and uses the alternate CHOICE to accept the entry "VERIFY" by truncating it to "VER".

**Note:** This attribute is valid only when the SELFLD tag has been specified with TYPE=MODEL.

### UNAVAIL=variable-name

This attribute defines a variable whose value indicates whether the choice is available when the selection field is displayed. If the value of the variable is equivalent to the *string* you specify with the UNAVAILMAT attribute (or to the default value "1"), the item is displayed as an unavailable choice.

#### UNAVAILMAT=1 | string

Defines the value for the UNAVAIL variable that causes the choice to be unavailable. The *string* can be any character string. UNAVAILMAT=1 is the default.

### TRUNC=n

This attribute is used for model-choice selection to specify the minimum number of characters required to identify the model choice. If the TRUNC attribute is not specified, the entire model choice name must be used to identify the model selection.

**Note:** This attribute is valid only when the SELFLD tag has been specified with TYPE=MODEL.

### AUTOSEL=YES | NO

This attribute is used for tutor-choice selection to control the automatic selection of this choice by tutorial processing. When AUTOSEL=NO, the choice is not automatically selected.

### choice-description-text

The text of the selection choice.

## Description

The CHOICE tag defines a choice within a selection field. The behavior and appearance of the choice depends on whether it is coded within a single-choice,

## CHOICE

multiple-choice, or menu-choice selection field. The single-choice entries are further affected in GUI mode by the value of the LISTTYPE attribute on the SELFLD tag.

For menu-choice selection fields, the text is preceded by a number (not followed by a period), the input field is the command line, and the choice selection is displayed with the CUA type Normal Text (NT).

For a single-choice selection list:

- When the LISTTYPE attribute of the SELFLD tag is not specified, the text is preceded by a number (followed by a period), the conversion utility provides an input field before the first choice for entry of the number of the selected choice, and the choice selection is displayed with the CUA type Select Available Choices (SAC).
- When LISTTYPE=RADIO is specified on the SELFLD tag, the choice selection is displayed as a radio button in GUI mode.
- When LISTTYPE=LISTBOX is specified on the SELFLD tag, the choice selection is displayed as a list box in GUI mode.
- When LISTTYPE=DDLST is specified on the SELFLD tag, the choice selection is displayed as a drop-down list in GUI mode.
- When LISTTYPE=COMBO is specified on the SELFLD tag, the choice selection is displayed in a combination box in GUI mode.

The field name for single-choice selection fields is the value specified for the NAME attribute of the SELFLD tag. The default field name for an ISPF selection menu choice is the field name used to identify the command line, normally ZCMD.

The text of each choice in a multiple-choice selection field is preceded by an input field. The field name for multiple-choice selection fields is the value specified for the NAME attribute of the CHOICE tag.

You can define an action for each choice using the SETVAR or TOGVAR attribute in an ACTION tag associated with the choice. Typically, an application knows what choice was selected by the application user by the value in the selection field name. The CHOICE field name for a multi-choice selection is set to a “/” when control is returned to the application. The SELFLD field name contains the number of the choice for single choice selection when control is returned to the application. The command line variable name contains the number of a menu selection choice when control is returned to the application. Alternatively, the application can use the value of the check variable or use SETVAR or TOGVAR to set another named variable.

## Conditions

- You must code the CHOICE tag within a SELFLD definition. See “SELFLD (Selection Field)” on page 464 for a complete description of this tag.
- If coded within a multiple-choice selection field (SELFLD TYPE=MULTI), the *choice-name* can have an associated VARDCL definition.
- If both PAD and PADC have been specified, PAD is ignored and PADC is used.
- When a “%varname” notation is found on any of the attributes that allow a variable name, the “%varname” entry must follow the standard naming convention described in “Rules for “%variable” Names” on page 205.
- If the *choice-description-text* contains HP (Emphasized Text) or RP (Reference Phrase) tags, the UNAVAIL attribute is ignored.

## Nested Tags

You can code the following tags within a CHOICE definition:

Tag	Name	Usage	Page	Required
ACTION	Action	Multiple	211	No
CHOFLD	Choice data field	Multiple	248	No
COMMENT	Comment	Multiple	275	No
HP	Highlighted phrase	Multiple	348	No
PS	Point-and-Shoot	Multiple	438	No
RP	Reference phrase	Multiple	454	No
SOURCE	Source	Multiple	482	No

## Example

The application panel in the following markup contains two selection fields. The first is a single-choice selection field that can be preselected depending on the value assigned to the variable *card*. When *card* is equal to *new*, *renew*, or *replace*, the selection field's input data field is assigned a value of 1, 2, or 3, respectively; otherwise, it is not preselected and the input data field remains blank.

The second selection field is a multiple-choice selection field. This field can be preselected by assigning values to the variables *nth*, *sth*, *est* and *wst*. If the given variable equals 1, the corresponding selection field is marked with a /. More than one of the choices may be selected. Any nonblank character in the choice entry-field will select that choice. Preselected choices can be deselected by typing a blank character over the field.

Figure 100 on page 262 shows the formatted result.

```
<!DOCTYPE DM SYSTEM(
  <!entity sampvar1 system>
  <!entity sampabc system>)>
&sampvar1;

<PANEL NAME=choice1 KEYLIST=keyl xmp>Library Card Registration
<AB>
&sampabc;
</AB>
<TOPINST>Type in patron's name and card number (if applicable).
<TOPINST>Then select an action bar choice.
<AREA>
  <DTAFLD DATAVAR=curdate PMTWIDTH=12 ENTWIDTH=8 USAGE=out>Date
  <DTAFLD DATAVAR=cardno PMTWIDTH=12 ENTWIDTH=7 DESWIDTH=25>Card No
    <DTAFLDD>(A 7-digit number)
  <DTAFLD DATAVAR=name PMTWIDTH=12 ENTWIDTH=25 DESWIDTH=25>Name
    <DTAFLDD>(Last, First, M.I.)
  <DTAFLD DATAVAR=address PMTWIDTH=12 ENTWIDTH=25>Address
  <DIVIDER>
  <REGION DIR=horiz>
  <SELFLD NAME=cardsel PMTWIDTH=30 SELWIDTH=38>Choose
one of the following
  <CHOICE CHECKVAR=card MATCH=new>New
  <CHOICE CHECKVAR=card MATCH=renew>Renewal
  <CHOICE CHECKVAR=card MATCH=replace>Replacement
</SELFLD>
<SELFLD TYPE=multi PMTWIDTH=30 SELWIDTH=25>Check valid branches
  <CHOICE NAME=north HELP=nthhlp CHECKVAR=nth>North Branch
  <CHOICE NAME=south HELP=sthhlp CHECKVAR=sth>South Branch
  <CHOICE NAME=east HELP=esthlp CHECKVAR=est>East Branch
```

## CHOICE

```
<CHOICE NAME=west HELP=wsthlp CHECKVAR=wst>West Branch
</SELFLD>
</REGION>
</AREA>
<CMDAREA>Enter a command
</PANEL>
```

The screenshot shows a terminal window titled "Library Card Registration". At the top, there are menu options: "File Search Help". Below this, a dashed line separates the header from the main content. The main content includes instructions: "Type in patron's name and card number (if applicable). Then select an action bar choice." There are several input fields: "Date . . . :", "Card No. . . . (A 7-digit number)", "Name . . . . (Last, First, M.I.)", and "Address . . . .". Below these are two columns of choices. The first column is titled "Choose one of the following" and lists: "1. New", "2. Renewal", "3. Replacement". The second column is titled "Check valid branches" and lists: "North Branch", "South Branch", "East Branch", "West Branch". At the bottom, there is a command prompt "Enter a command ===>" followed by a horizontal line. Below the line are function key definitions: "F1=Help", "F2=Split", "F3=Exit", "F6=KEYSHELP", "F9=Swap", and "F12=Cancel".

Figure 100. Selection Field Choices

## CMD (Command Definition)

The CMD tag defines a command within an application command table.

```
—<CMD—NAME=internal-command-name—>
      |ALTDESCR=command-description|
_____
|external-command-name| |</CMD>|
```

### NAME=internal-command-name

This attribute specifies an internal name for the command. The *internal-command-name* must have the following characteristics:

- 2–8 single-byte characters in length
- The first (or only) character must be A–Z, a–z, @, #, or \$.
- Remaining characters, if any, can be A–Z, a–z, @, #, \$, —, or 0–9.

Lowercase characters are translated to their uppercase equivalents.

The *internal-command-name* is used in two ways:

- As the command table search criteria when:
  - A key defined in the current key list is pressed
  - A pull-down choice with an associated RUN action is selected
  - A command is entered in the command area of a panel.

- As the value passed to dialogs when the command action is PASSTHRU or SETVERB. See “CMDACT (Command Action)” on page 264 for more information about the PASSTHRU and SETVERB command actions.

**ALTDESCR=command-description**

This attribute provides a description of the command. It is placed in the ISPF variable ZCTDESC. The *command-description* text length is limited to 80 bytes.

**external-command-name**

Specifies the external name for this command.

**Note:** The *external-command-name* must be equal to the *internal-command-name*. You must use the *external-command-name* to support the ability provided by ISPF for truncated command entry and the T (truncation) tag. For more information, see “T (Truncation)” on page 484.

## Description

The CMD tag defines a command within an application command table. The defined command can be issued by an application user by entering the *internal-command-name* in the panel command area, or pressing a function key, or selecting a pull-down choice that references the command’s *internal-command-name*. See “KEYI (Key Item)” on page 352 and “ACTION (Action)” on page 211 for additional information.

The action to be taken when a command is issued is defined with the CMDACT tag. See “CMDACT (Command Action)” on page 264 for information about defining command actions.

## Conditions

- The CMD tag must be coded within a CMDTBL definition. See “CMDTBL (Command Table)” on page 273 for a complete description of this tag.

## Nested Tags

You can code the following tags within a CMD definition:

Tag	Name	Usage	Page	Required
CMDACT	Command action	Single	264	Yes
T	Truncation	Single	484	No

## Example

The following source file markup contains a command table that defines the commands UPDATE, ADD, DELETE, and SEARCH. The DELETE and UPDATE commands have defined truncations.

## CMD

```

<!DOCTYPE DM SYSTEM>

<CMDTBL APPLID=conv>
  <CMD NAME=update>Upd<T>ate
    <CMDACT ACTION=' alias add' >
  <CMD NAME=add>Add
    <CMDACT ACTION=setverb>
  <CMD NAME=delete>Del<T>ete
    <CMDACT ACTION=passthru>
  <CMD NAME=search>Search
    <CMDACT ACTION=passthru>
</CMDTBL>

```


The following table shows the resultant ISPF application command table.

Table 1. ISPF Application Command Table

ZCTVERB	ZCTTRUNC	ZCTACT
UPDATE	3	ALIAS ADD
ADD	0	SETVERB
DELETE	3	PASSTHRU
SEARCH	0	PASSTHRU

## CMDACT (Command Action)

The CMDACT tag defines the action that occurs when the associated command is issued.



### ACTION=

This attribute indicates the action that should be performed when the associated command is issued. The ACTION attribute value is limited to 240 characters. The value must be one of the following:

#### SELECT select-parameters

Causes the ISPF SELECT service to be issued.

#### ALIAS internal-command-name

Provides an alternate way to express a command. For example, you can assign QUIT as an alias for the command EXIT.

The ALIAS *internal-command-name* has a maximum length of 8 characters. In the command table, an alias must precede the command for which it is an alias.

You can create a chain of command aliases in a command table, as long as the result is a valid executable action. The last command and parameter values that ISPF encounters in the alias chain are the ones executed. The command and the parameter values do not necessarily come from the same command definition entry. For example:

<b>Command Name</b>	<b>Command Action</b>
EASYKEY	ALIAS CMD PARM1 PARM2
CMD	ALIAS CMD1 PARM3
CMD1	ALIAS CMD2

In this example, if the EASYKEY command is issued, the command that would ultimately be executed would be CMD2 PARM3.

#### **parameters**

If any ALIAS parameters are specified, they take precedence over any parameters included with the command when issued from a command line or the ACTION tag RUN attribute when a pull-down choice is selected.

If the ALIAS *internal-command-name* does not include parameters, ISPF accepts parameters from the command line or ACTION tag.

#### **PASSTHRU**

The PASSTHRU action causes the command and any parameters to be passed to the dialog program in the ZCMD dialog variable.

#### **SETVERB**

This is an alternate way to pass a command to the dialog. The SETVERB action causes the *internal-command-name* to be passed to the dialog in the ZVERB dialog variable. Any command parameters are passed in the ZCMD dialog variable.

#### **BACKWARD**

Specifies the ISPF system command BACKWARD as the command action.

#### **CANCEL**

Specifies the ISPF system command CANCEL as the command action.

#### **EXIT**

Specifies the ISPF system command EXIT as the command action.

#### **EXHELP**

Specifies the ISPF system command EXHELP as the command action.

#### **FKA**

Specifies the ISPF system command FKA as the command action.

#### **FORWARD**

Specifies the ISPF system command FORWARD as the command action.

#### **HELP**

Specifies the ISPF system command HELP as the command action.

#### **PANELID**

Specifies the ISPF system command PANELID as the command action.

## RETRIEVE

Specifies the ISPF system command RETRIEVE as the command action.

## %varname

You can specify a command action dynamically at run time by specifying the name of a variable (using % notation) for the ACTION attribute. If you specify a variable name, ISPF retrieves the action value when the command is issued. The variable value must be one of the actions previously listed.

The “%varname” entry must follow the naming conventions described in “Rules for “%variable” Names” on page 205.

## application-command

Specifies an application-unique command as the command action. The command action is created as an ALIAS unless the ASIS keyword is specified.

**ASIS** Specifies that the application-unique command is to be created without the ALIAS designation.

## Description

The CMDACT tag defines the action that occurs when the associated command is issued.

## Conditions

- The CMDACT tag must be coded within the CMD definition it is associated with. See “CMD (Command Definition)” on page 262 for a complete description of this tag.
- You must specify the ACTION attribute on the CMDACT tag.

## Nested Tags

None.

## Example

The following source file markup contains a command table that defines the commands UPDATE, ADD, DELETE and SEARCH. The ADD command sets the ZVERB variable equal to *add*. The DELETE command sets the ZCMD variable to *delete*. The UPDATE command is an alias for ADD.

```
<!DOCTYPE DM SYSTEM>
<CMDTBL APPLID=conv>
  <CMD NAME=update>Upd<T>ate
    <CMDACT ACTION='alias add'>
  <CMD NAME=add>Add
    <CMDACT ACTION=setverb>
  <CMD NAME=delete>Del<T>ete
    <CMDACT ACTION=passthru>
  <CMD NAME=search>Search
    <CMDACT ACTION=passthru>
</CMDTBL>
```


The following table shows the resultant ISPF application command table.

Table 2. ISPF Application Command Table


ZCTVERB	ZCTTRUNC	ZCTACT
UPDATE	3	ALIAS ADD
ADD	0	SETVERB
DELETE	3	PASSTHRU
SEARCH	0	PASSTHRU

## CMDAREA (Command Area)


The CMDAREA tag defines a command entry area on an application panel.




## CMDAREA



### PB Group:



### IMAP Options



**HELP=NO | YES | help-panel-name | \*help-message-id | %varname | \*%varname**

This attribute specifies the help action taken when the user requests help for the command area.

When HELP=YES, control is returned to the application. You can specify either a help panel or a message identifier. If a message identifier is used, it must be prefixed with an asterisk (\*).

The help attribute value can be specified as a variable name. When %varname is coded, a panel variable name is created. When \*%varname is coded, a message variable name is created.

If the user requests help on a choice and no help is defined, the extended help panel is displayed. If an extended help panel is not defined for the panel, the application or ISPF tutorial is invoked.

The *help-panel-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

See “HELP (Help Panel)” on page 335 for information about creating help panels. For information about creating messages, see “MSG (Message)” on page 390.

### PMTLOC=BEFORE

This attribute defines the location of the prompt text. The text defined by *command-prompt-text* appears on the same line as the command area entry field.

**NOINIT**

This attribute controls the initial display of the command line. When this attribute is specified, the ZCMD field is not initialized to blanks before the panel is displayed.

**PAD=NULLS | USER | char | %varname**

This attribute specifies the pad character for initializing the field. You can define this attribute as a variable name preceded by a "%".

**PADC= NULLS | USER | char | %varname**

This attribute specifies the conditional padding character to be used for initializing the field. You can define this attribute as a variable name preceded by a "%".

**OUTLINE=NONE | L | R | O | U | BOX | %varname**

This attribute provides for displaying lines around the field on a DBCS terminal. You can define this attribute as a variable name preceded by a "%".

**NAME=cmdarea-variable-name**

This attribute specifies a command area name to replace the default name ZCMD.

The *cmdarea-variable-name* must follow the standard naming convention described in "Rules for Variable Names" on page 205.

**ENTWIDTH=n**

This attribute is used to specify the length of the command field. It is used in combination with WINDOW=NO on the PANEL tag to create a command line which is longer than a single panel line.

**PMTTEXT=YES | NO**

This attribute is used to control the formatting of the *command-prompt-text*. When PMTTEXT=NO, the *command-prompt-text* is not used, leaving only the "====>" indicator for the command field.

**CMDLOC=DEFAULT | ASIS**

This attribute is used to control the placement of the command line in the generated panel. When CMDLOC=DEFAULT (or when CMDLOC is not specified) the command area is placed at line 2 in the panel, and the display position is controlled by the option specified on the Settings panel. When CMDLOC=ASIS is specified, the command area is placed in the generated panel in the same relative position as the CMDAREA tag is found in the DTL source, and the Settings option is ignored when the panel is displayed.

**CMDLEN=DEFAULT | MAX**

This attribute is used to control the length of the command line in the generated panel. When CMDLEN=DEFAULT (or when CMDLEN is not specified) the command line length is taken from the specified (or defaulted) WIDTH attribute of the PANEL tag. When CMDLEN=MAX is specified, the command line length is taken from the record length of the output panel file.

This attribute is valid only when WINDOW=NO is specified on the PANEL tag.

**AUTOTAB=NO | YES**

When AUTOTAB=YES, the cursor moves to the next input field when you enter the last character in the command field. If there is no other input field on the panel, the cursor returns to the beginning of the command line. The ISPF SKIP keyword is not supported in GUI mode.

**SCROLLVAR=scroll-variable**

This attribute specifies the name of a variable that the application uses to

obtain scrolling information. The *scroll-variable* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

If the attribute is specified, the conversion utility creates a scroll entry on the command line, providing that the resulting command area allows at least 8 bytes for a command entry.

**SCRVHELP=NO | YES | scroll-help-panel-name | \*scroll-help-message-id | %varname | \*%varname**

This attribute specifies the help action taken when the user requests help for the field specified with the SCROLLVAR attribute.

When SCRHELP=YES, control is returned to the application. You can specify either a help panel or a message identifier. If a message identifier is used, it must be prefixed with an asterisk (\*).

The help attribute value can be specified as a variable name. When %varname is coded, a panel variable name is created. When \*%varname is coded, a message variable name is created.

If the user requests help on a choice and no help is defined, the extended help panel is displayed. If an extended help panel is not defined for the panel, the application or ISPF tutorial is invoked.

The *scroll-help-panel-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

See “HELP (Help Panel)” on page 335 for information about creating help panels. For information about creating messages, see “MSG (Message)” on page 390.

**SCROLLTAB=NO | YES**

When SCROLLTAB=YES, the cursor moves to the next input field when you enter the last character in the scroll amount field. If there is no other input field on the panel, the cursor returns to the beginning of the command line. The ISPF SKIP keyword is not supported in GUI mode.

**SCRCAPS=OFF | ON**

When SCRCAPS=ON, the data in the scroll field is displayed in uppercase characters.

**PSBUTTON=cmd-pb-text**

This attribute requires that the PSVAR and PSVAL attributes also be specified.

This attribute specifies that a command push button is to be placed at the end of the command line, provided that the resulting command area allows at least 8 bytes for a command entry. The push button text area is created as a point-and-shoot field.

**PSVAR=point-and-shoot-variable | %varname**

This attribute provides the name of a variable that is to be set when the *cmd-pb-text* is clicked on for point-and-shoot selection. You can define this attribute as a variable name preceded by a percent (%) sign.

The *point-and-shoot-variable* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

**PSVAL=point-and-shoot-value | %varname**

This attribute provides the value to be placed in the field specified by the PSVAR attribute. You can define this attribute as a variable name preceded by a percent (%) sign. To specify a blank value, use the coding notation `'' ''` (quotation mark, apostrophe, blank space, apostrophe, quotation mark).

**IMAPNAME=***image-name* | %varname

This attribute specifies the name of an image to be placed on the point-and-shoot push button when it is displayed in GUI mode. The *image-name* is not used when the panel is displayed in host mode. The *image-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

**IMAPNAMEP=***image-namep* | %varname

This attribute specifies the name of an image to be placed on the point-and-shoot push button after it has been pushed when it is displayed in GUI mode. The *image-namep* is not used when the panel is displayed in host mode. The *image-namep* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

**PLACE=**ABOVE | BELOW | LEFT | RIGHT | %varname

This attribute specifies the position of the image relative to the text within the point-and-shoot push button.

**CAPS=**OFF | ON

When CAPS=ON, the data in the field is displayed in uppercase characters.

**NOJUMP=**OFF | ON

When NOJUMP=ON, the JUMP function is disabled for the field.

**VARDCL=**YES | NO

When VARDCL=NO the *cmdarea-variable-name* is not checked to the declared variable information provided with the VARCLASS and VARDCL tags.

**command-prompt-text**

The *command-prompt-text* specifies the prompt text for the command entry area. The maximum prompt text (not including the command area prefix ===>) is 59 bytes for a standard 76 byte-width panel. The conversion utility reserves 8 bytes for a minimum command entry field and 3 additional bytes are required for panel attributes. One blank is placed between the *command-prompt-text* and the command area prefix. One blank is placed between the end of the command line and the right panel boundary (unless the WINDOW=NO attribute has been specified) to prevent the cursor from skipping into the right panel window border. These formatting considerations mean that the maximum length of the *command-prompt-text* for a panel 76 bytes in width is 59. If the length of the *command-prompt-text* exceeds the available space, a message is issued and the *command-prompt-text* is truncated. If your panel requires that the Scroll field be added to the Command line, or the SCROLLVAR attribute is specified in the CMDAREA definition, the *command-prompt-text* must be further reduced to allow for the Scroll field. If your panel specifies the PSBUTTON attribute, the *command-prompt-text* must be further reduced to allow for the Command push button.

If you do not provide *command-prompt-text*, the word “Command” (or its translated equivalent) is the default, unless you are creating an ISPF selection panel, in which case the word “Option” (or its translated equivalent) is the default. The Common User Access command area prefix (===>) is always added automatically in front of the entry field.

## Description

The CMDAREA tag defines a command entry area on an application panel. The command entry area extends to the right side of the panel, unless limited by the ENTWIDTH attribute or the presence of a Scroll field. Application users use the command entry area to enter commands.

## CMDAREA

**Note:** If you specify the CMDAREA tag within your DTL source file:

- It must appear before the AREA, DA, GA, REGION, or SELFLD tag when DEPTH=\* is specified.
- It must appear before the SELFLD tag when TYPE=MENU and CHECKVAR or UNAVAIL attributes are specified on nested CHOICE tags.

## Conditions

- You must code the CMDAREA tag within a PANEL definition. You can code only one command area definition for each panel. See “PANEL (Panel)” on page 413 for a complete description of this tag.
- The data entered on the command line is processed “as is”. To translate the data to uppercase, you must either provide a VARDCL definition for the field ZCMD with a reference to a VARCLASS containing an XLATL tag which specifies FORMAT=UPPER, or specify CAPS=ON.
- You cannot code the CMDAREA tag within an AREA definition. The Command area is generated at the top of the panel source to allow for floating of the command line. Refer to the *ISPF User's Guide* for more information.
- If both PAD and PADC have been specified, PAD is ignored and PADC is used.
- When a “%varname” notation is found on any of the attributes that allow a variable name, the “%varname” entry must follow the standard naming convention described in “Rules for “%variable” Names” on page 205.

## Nested Tags

You can code the following tag within a CMDAREA definition:

Tag	Name	Usage	Page	Required
HP	Highlighted phrase	Multiple	348	No

## Example

The following application panel markup contains a command area. The *command-prompt-text* “Use this area to enter a command” is specified in the markup to override the default text “Command”. Figure 101 shows the formatted result.



prefix to the string "CMDS" to form the name of the command table. The *application-identifier* must have the following characteristics:

- 1–4 characters in length
- The first (or only) character must be A–Z or a–z @, #, or \$.
- Remaining characters, if any, must be A–Z, a–z, @, #, \$, or 0–9.

Lowercase characters are translated to their uppercase equivalents.

The name of the command table is member name xxxxCMDS, where xxxx represents the *application-identifier*.

Command tables are updated using ISPF table services. Input is obtained from the ISPTLIB DDname allocation and output is written to the ISPTABL DDname allocation. Refer to the description of how to allocate libraries before starting ISPF in the *ISPF User's Guide* for more information about the use of ISPTLIB and ISPTABL.

**SORT=NO | YES**

When SORT=YES is specified, the command table is sorted in command-name sequence. Any commands defined as an ALIAS to other commands are placed in the command table first, in command-name sequence. The regular commands follow the ALIAS entries in command-name sequence.

If SORT=NO or the SORT attribute is not specified, commands are placed in the command table in the sequence the CMD tags are encountered in the DTL source file.

**Description**

The command table tag provides support to define the ISPF application command table. ACTION tags and definitions of key lists reference the command definitions within an application command table.

**Note:** To access commands through the use of the key list function keys, specify the KEYLAPPL ID invocation parameter for the conversion utility with the same APPLID value used for the CMDTBL tag.

**Note:** You can use the TSO ISPCMDTB command to convert existing command tables to DTL. To use ISPCMDTB, ensure that the command table is in your table concatenation (ISPCMDTB), type TSO ISPCMDTB *applid* (where *applid* is the application id of the command table). This will place you in an edit session containing the DTL version of the command table. Use the editor CREATE or REPLACE commands to save the table to your DTL source data set.

**Conditions**

- The CMDTBL tag requires an end tag.
- You cannot code the CMDTBL tag within any other tag definition.
- You can code only one command table for any application.

**Nested Tags**

You can code the following tag within a CMDTBL definition:

Tag	Name	Usage	Page	Required
CMD	Command definition	Multiple	262	Yes

## Example

The following source file markup contains a command table that defines the commands UPDATE, ADD, DELETE and SEARCH.

```
<!DOCTYPE DM SYSTEM>

<CMDTBL APPLID=conv>
  <CMD NAME=update>Upd<T>ate
    <CMDACT ACTION=' alias add' >
  <CMD NAME=add>Add
    <CMDACT ACTION=setverb>
  <CMD NAME=delete>Del <T>ete
    <CMDACT ACTION=passthru>
  <CMD NAME=search>Search
    <CMDACT ACTION=passthru>
</CMDTBL>
```


The following table shows the resultant ISPF application command table.

Table 3. ISPF Application Command Table

ZCTVERB	ZCTTRUNC	ZCTACT
UPDATE	3	ALIAS ADD
ADD	0	SETVERB
DELETE	3	PASSTHRU
SEARCH	0	PASSTHRU

## COMMENT (Comment)

The COMMENT tag adds comment text to the generated panel or message member.



**TYPE=END | CCSID | PANEL | ATTR | ABCINIT | ABCPROC | INIT | REINIT | PROC | HELP | PNTS | LIST**

This attribute specifies the section of the panel that is to contain the comment text. The default is END. TYPE=END is assumed if the COMMENT tag is used within the MSGMBR tag.

COMMENT tags that specify the TYPE as ABCINIT or ABCPROC must follow an ABC or PDC tag.

When a COMMENT tag is coded within a HELP panel, the TYPE value is limited to CCSID, PANEL, ATTR, INIT, PROC, or END.

## COMMENT

### comment-text

The *comment-text* is flowed to a width of 66 bytes. The conversion utility adds “/\* ” before and “ \*/” after the resulting text.

When no *comment-text* is present, a blank comment line is added to the specified (or defaulted) panel section.

## Description

The COMMENT tag adds comments to the generated ISPF format panel. If the PREP conversion option has been specified, the comments will not be part of the final panel because they will not be processed by the ISPPREP utility.

Lines of text from a COMMENT tag are added to the specified panel section when encountered in the DTL source file.

**Note:** If the panel section specified will not be generated by other conversion processing, comments will be formatted as follows:

<b>TYPE</b>	<b>Comments will be placed:</b>
<b>CCSID</b>	Following the )PANEL statement.
<b>LIST</b>	Before the )END statement.

Comments added to the )END panel section are placed following any entries from the COPYR tag and comments containing the ISPD TLC version number and panel creation date. Lines placed in the )END section of a HELP panel are added to each continuation HELP panel.

## Conditions:

- You must code the COMMENT tag within an ABC, AREA, CHOICE, DA, DTACOL, DTAFLD, HELP, LSTCOL, LSTFLD, LSTGRP, PANEL, PDC, REGION or SELFLD tag definition.

## Nested Tags

None.

## Example

The following source file markup contains a comment of several lines that will be placed after the )END panel statement. Figure 102 on page 277 shows portion of the ISPF format panel containing the formatted result.

```
<!doctype dm system>
<!-- COMMENT tag example - PANEL tag -->
<!-- )END section - after CMDAREA tag -->

<varclass name=vc1 type=' char 10' >
<varclass name=vc2 type=' char 6' >
<varlist>
<vardcl name=lst1 varclass=vc1>
<vardcl name=lst2 varclass=vc2>
</varlist>

<panel name=comment1 depth=19 width=50>
This is panel Comment1

<LSTFLD >
<LSTGRP headline=yes>
<LSTCOL colwidth=10 datavar=lst1 usage=in varclass=vc1 line=1
      required=yes autotab=yes align=end help=h1 msg=abcd101>COL1
```

```

<LSTCOL colwidth=6 datavar=lst2 usage=in varclass=vc2 line=2
    required=yes autotab=yes align=end help=h1 msg=abcd101>COL2
</LSTGRP>
</LSTFLD>
<cmdarea>
<comment type=end>
    comment line 1
      comment line 2
        comment line 3
    comment line 4
      comment line 5
        comment line 6
    comment line 7
      comment line 8
        comment line 9
</panel>

```

```


:
)END
/* comment line 1 comment line 2 comment line 3 comment line 4 */
/* comment line 5 comment line 6 comment line 7 comment line 8 */
/* comment line 9 */

```


Figure 102. Comment text added to a panel

## COMPOPT (Compiler Options)

The COMPOPT tag sets compiler options for the current source file.



## COMPOPT



With the exception of ADD and RESET, all of the option keywords used for the COMPOPT tag are the same as those used for “Conversion Utility Syntax” on page 177. Refer to that chapter for information about these keywords.

The COMPOPT tag keyword RESET restores the conversion utility options to their original invocation settings.

### Description

The COMPOPT tag can be placed within the Doctype definition to encompass the entire DTL source file or it can be placed before the first PANEL, HELP, MSGMBR, KEYL, or CMDTBL tag that requires a compiler option change.

Unless the ADD option is specified when the COMPOPT tag is processed, all conversion utility options except PANEL, DISK, SCREEN, DISPLAY, DISPLAYW, DBCS, and KANA are first reset to the defined default values. The options specified on the COMPOPT tag are then applied.

When the ADD option is included, the original options remain in effect and the options from the COMPOPT tag are added to the current list. ADD overrides any existing option.

The options set by this tag remain in effect for the current source file until another COMPOPT tag is processed. If you are converting a list of members, either from member list selections or from a DTLLST list of members, the conversion utility options are reset to their original invocation settings when the current source file is completed.

The PROFILE and PROFDDN options defined as part of the conversion utility invocation syntax are not supported by the COMPOPT tag.

### Conditions:

None.

### Nested Tags

None.

### Example

The following source file markup contains a compiler options line that specifies the compiler options to be used converting this source file.

```

<!doctype dm system>
<varclass name=vc1 type=' char 10' >
<varclass name=vc2 type=' char 6' >
<varlist>
<vardcl name=lst1 varclass=vc1>
<vardcl name=lst2 varclass=vc2>
</varlist>

<compopt noprep noreplace>

<panel name=compopt depth=19 width=50>
This is panel Compopt

<LSTFLD >
  <LSTGRP headline=yes>
    <LSTCOL colwidth=10 datavar=lst1 usage=in varclass=vc1 line=1
      required=yes autotab=yes align=end help=h1 msg=abcd101>COL1
    <LSTCOL colwidth=6 datavar=lst2 usage=in varclass=vc2 line=2
      required=yes autotab=yes align=end help=h1 msg=abcd101>COL2
  </LSTGRP>
</LSTFLD>
<cmdarea>
</panel >

```

---

## COPYR (Copyright)

The COPYR tag adds copyright text to the generated panel or message member.

```

—<COPYR>
└── copyright-text ─┘ └── </COPYR> ─┘

```

### copyright-text

The *copyright-text* is limited to 66 bytes. It is automatically formatted as a panel comment with a “/\* ” in front and a “ \*/” following the supplied text.

## Description

The COPYR tag adds copyright information to the panel.

The COPYR tag must be placed before the first PANEL, HELP, or MSGMBR definition within the DTL source file that is to contain the copyright information.

You can use multiple COPYR tags. Each tag creates one comment line, which is placed after the )END panel statement, or the last message in the message member, in the order found in the DTL source.

The *copyright-text* is added to each subsequent panel or message member generated from the same DTL source file member. If the PREP conversion option has been specified, the copyright will not be part of the final panel because comments are not processed by the ISPPREP utility.

## Conditions

None.

## Nested Tags

None.

## Example

The following source file markup contains two copyright lines that will be placed after the )END panel statement. Figure 103 shows a portion of the ISPF format panel containing the formatted result.

```
<!doctype dm system>
<!-- COPYR tag example - PANEL tag -->

<varclass name=vc1 type=' char 10' >
<varclass name=vc2 type=' char 6' >
<varlist>
<vardcl name=lst1 varclass=vc1>
<vardcl name=lst2 varclass=vc2>
</varlist>

<copyr>Copyright statement 1
<copyr>Copyright statement 2

<panel name=copyrt1 depth=19 width=50>
This is panel Copyrt1

<LSTFLD >
<LSTGRP headline=yes>
<LSTCOL colwidth=10 datavar=lst1 usage=in varclass=vc1 line=1
      required=yes autotab=yes align=end help=h1 msg=abcd101>COL1
<LSTCOL colwidth=6 datavar=lst2 usage=in varclass=vc2 line=2
      required=yes autotab=yes align=end help=h1 msg=abcd101>COL2
</LSTGRP>
</LSTFLD>
<cmdarea>
</panel >
```


```


:
)END
/* Copyright statement 1 */
/* Copyright statement 2 */
```

Figure 103. Copyright statement added to a panel


## DA (Dynamic Area)

The DA tag defines a dynamic area in the panel )BODY section.





### DIV Options:



### NAME=varname

This attribute defines the name of a dynamic area. This name is the dialog variable specified by the application that contains the data for the dynamic area. The *varname* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

### EXTEND=OFF | ON | FORCE

This attribute defines the run-time display size of the dynamic area. If EXTEND=ON is specified, the dynamic area definition is expanded to the size of the logical screen. If you intend to display the panels in a pop-up window, use EXTEND=OFF (which is the default).

If EXTEND=FORCE is specified within a horizontal area or region, the EXTEND(ON) keyword is added to the dynamic area attribute statement in the )ATTR panel section. The conversion utility issues a message to advise of a potential display error if other panel fields are formatted on or after the last defined line of the dynamic area.

### LVLLINE=variable-name

This attribute allows you to specify the name of a variable that contains the result of the ISPF function LVLLINE. The *variable-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

**SCROLL=OFF | ON | CMDLINE**

If you specify SCROLL=ON or SCROLL=CMDLINE, ISPD TLC adds the scroll amount field provided by the SCROLLVAR attribute to the command line.

If you specify SCROLL=ON, ISPD TLC also automatically enables scrolling commands by adding SCROLL(ON) to the dynamic area attribute definition.

**Note:** When SCROLL(ON) is *not* part of the dynamic area attribute definition, data in the scroll amount field is available to the application exactly as entered.

The first dynamic area on a panel that specifies SCROLL=ON or SCROLL=CMDLINE (with a valid SCROLLVAR attribute) controls the creation of the scroll amount field. The specification of the SCROLL attribute on subsequent DA tags is ignored.

**USERMOD=usermod-code | %varname**

This attribute specifies a single-character or a 2-position hexadecimal value to be substituted for attribute characters in a dynamic area variable following user interaction. You can define this attribute as a variable name preceded by a "%".

**DATAMOD=datamod-code | %varname**

This attribute specifies a single-character or a 2-position hexadecimal value to be substituted for attribute characters in a dynamic area following user interaction. You can define this attribute as a variable name preceded by a "%".

**DEPTH=n | \***

This attribute specifies the number of lines reserved for the dynamic area definition.

If the DA tag is to be formatted in the panel )BODY section, that is, the tag is not within a scrollable area:

- The maximum DEPTH value is the DEPTH value specified on the PANEL tag, reduced by the number of divider lines (if the DIV attribute is specified) and any other lines previously used by text or interactive fields.
- If the DEPTH value is specified as an asterisk (\*), the conversion utility will reserve the remaining available panel depth for the dynamic area.

If the DA tag is defined within a scrollable area (see "AREA (Area)" on page 217), \* cannot be specified as the depth value. The maximum DEPTH value is limited by the ISPF run-time environment.

**WIDTH=n**

This attribute specifies the number of columns reserved in the panel )BODY section for the dynamic area definition. If the dynamic area width is less than the PANEL width, the conversion utility adds an attribute byte immediately following the right dynamic area boundary. The minimum width for a dynamic area is the length of *varname* plus two (2) positions. The maximum value is the remaining panel width.

**SHADOW=shadow-name**

This attribute provides a name for a shadow variable name which is used to define character level attributes within the dynamic area string. The *shadow-name* must follow the standard naming convention described in "Rules for Variable Names" on page 205.

**DIV=NONE | BLANK | SOLID | DASH | TEXT**

This attribute specifies the type of divider line to be placed before and after the

dynamic area. If this attribute is not specified or has the value NONE, no divider line is generated. The value BLANK produces a blank line. You must specify SOLID, DASH, or TEXT to produce a visible divider line. When the GRAPHIC invocation option is specified, SOLID produces a solid line for host display and DASH produces a dashed line. When NOGRAPHIC is specified or the panel is displayed in GUI mode, both SOLID and DASH produce a dashed line. A visible divider line formats with a non-displayable attribute byte on each end of the line.

**FORMAT=START | CENTER | END**

This attribute specifies the position of the *divider-text* within the divider line. You must specify both the FORMAT attribute and the TEXT attribute to create a divider line containing text.

**TEXT=divider-text**

This attribute specifies the text to be placed on the divider line. You must specify both the FORMAT attribute and the TEXT attribute to create a divider line containing text.

**SCROLLVAR=scroll-variable**

This attribute specifies the name of a variable that the application uses to obtain scrolling information. The *scroll-variable* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

**SCRVHELP=NO | YES | scroll-help-panel-name | \*scroll-help-message-id | %varname | \*%varname**

This attribute specifies the help action taken when the user requests help for the field specified with the SCROLLVAR attribute.

When SCRHELP=YES, control is returned to the application. You can specify either a help panel or a message identifier. If a message identifier is used, it must be prefixed with an asterisk (\*).

The help attribute value can be specified as a variable name. When %varname is coded, a panel variable name is created. When \*%varname is coded, a message variable name is created.

If the user requests help on a choice and no help is defined, the extended help panel is displayed. If an extended help panel is not defined for the panel, the application or ISPF tutorial is invoked.

The *scroll-help-panel-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

See “HELP (Help Panel)” on page 335 for information about creating help panels. For information about creating messages, see “MSG (Message)” on page 390.

**SCROLLTAB=NO | YES**

If you specify SCROLLTAB=YES, the cursor moves to the next input field when the user enters the last character in the scroll amount field. If there is no other input field on the panel, the cursor moves to the beginning of the command line. The ISPF SKIP keyword is not supported in GUI mode.

**SCRCAPS=OFF | ON**

When SCRCAPS=ON, the data in the scroll field is displayed in uppercase characters.

**INITATTR=NT | CT | ET | WT | WASL**

This attribute specifies the last attribute found before the start of the dynamic

area. This allows the developer control of the initial color for the area. The conversion utility will replace the last attribute found before the dynamic area with the attribute specified.

**HELP=**NO | YES | **help-panel-name** | \***help-message-id** | %**varname** | \*%**varname**

This attribute specifies whether help is available for the dynamic area.

When HELP=YES, requesting help when the cursor is within the dynamic area causes control to return to the application. It is the application's responsibility to process the help request. You can specify either a help panel or a message identifier. If a message identifier is used, it must be prefixed with an asterisk (\*).

The help attribute value can be specified as a variable name. When %**varname** is coded, a panel variable name is created. When \*%**varname** is coded, a message variable name is created.

If the user requests help in a dynamic area and no help is defined, the extended help panel is displayed. If an extended help panel is not defined for the panel, the application or ISPF tutorial is invoked.

The *help-panel-name* must follow the standard naming convention described in "Rules for Variable Names" on page 205.

See "HELP (Help Panel)" on page 335 for information about creating help panels. For information about creating messages, see "MSG (Message)" on page 390.

## Description

The DA tag defines a dynamic area in the panel )BODY or )AREA sections.

If you specify the CMDAREA tag within your DTL source file, it must appear before the DA tag when DEPTH=\* is specified. The DA tag DEPTH may have to be adjusted to allow for additional lines which result from tags present within the panel definition following the end DA tag.

Refer to the *ISPF Dialog Developer's Guide and Reference* for a discussion of dynamic areas.

## Conditions

- You must code the DA tag within a PANEL, AREA, or REGION tag. If found anywhere else, an error is logged and the output panel is not saved.
- If NAME is not valid or not specified, an error is logged and the output panel is not saved.
- You can use the EXTEND=ON attribute only once within a panel, and EXTEND=ON cannot be specified on a DA tag coded within a scrollable area. If EXTEND is already active, either from a DA tag, or from an AREA, GA, SELFLD or REGION tag, a warning message is logged and the EXTEND attribute is ignored.
- You can use the SCROLLVAR attribute only once within a panel.
- If you specify the SCROLLVAR attribute, you must also specify the attribute SCROLL=ON or SCROLL=CMDLINE.
- The resulting scroll entry on the command line must leave at least eight positions for the command entry field.

- If you specify the SCRHELP attribute, you must also specify the SCROLLVAR attribute.
- When a “%varname” notation is found on any of the attributes that allow a variable name, the “%varname” entry must follow the standard naming convention described in “Rules for “%variable” Names” on page 205.

## Nested Tags

You can code the following tags within a DA definition:

Tag	Name	Usage	Page	Required
ATTR	Attribute	Multiple	228	No
COMMENT	Comment	Multiple	275	No
SOURCE	Source	Multiple	482	No

## Example

```
<!DOCTYPE DM SYSTEM(
  <!entity sampvar1 system>
  <!entity sampabc system>)>
&sampvar1;

<PANEL NAME=da KEYLIST=keyl xmp>Library Card Registration
<AB>
&sampabc;
</AB>
<TOPINST> Type in patron's name and card number (if applicable)
<AREA>
  <DTACOL PMTWIDTH=12 ENTWIDTH=25 DESWIDTH=25 SELWIDTH=25>
  <DTAFLD DATAVAR=curdate USAGE=out ENTWIDTH=8>Date
  <DTAFLD DATAVAR=cardno ENTWIDTH=7>Card No.
    <DTAFLDD>(A 7-digit number)
  <DTAFLD DATAVAR=name>Name
    <DTAFLDD>(Last, First, M.I.)
  <DTAFLD DATAVAR=address>Address
  </DTACOL>
<DIVIDER>
  <DA NAME=darea DIV=solid DEPTH=6 SHADOW=shadwvar>
    <ATTR ATTRCHAR=# TYPE=datain PADC='_' COLOR=BLUE>
    <ATTR ATTRCHAR=| TYPE=dataout COLOR=green>
    <ATTR ATTRCHAR=$ TYPE=char COLOR=red>
  </DA>
</AREA>
<CMDAREA>Enter a command
</PANEL>
```

---

## DD (Definition Description)

The DD tag defines the description of a term in a definition list.

```
—<DD>—
  └── definition-description ─┘ └──</DD>—
```

### definition-description

This is the text for the description of a definition list term.

## Description

The DD tag defines the description of a term in a definition list.

## Conditions

- You must code the DD tag within a DL definition. See “DL (Definition List)” on page 292 for a complete description of this tag.
- Each DD tag must follow an associated DT tag within the definition list. You can code only one DD tag for each DT tag.

## Nested Tags

You can code the following tags within a DD definition:

Tag	Name	Usage	Page	Required
DL	Definition list	Multiple	292	No
FIG	Figure	Multiple	324	No
HP	Highlighted phrase	Multiple	348	No
LINES	Lines	Multiple	360	No
NOTE	Note	Multiple	396	No
NOTEL	Note List	Multiple	399	No
NT	Note	Multiple	402	No
OL	Ordered list	Multiple	404	No
P	Paragraph	Multiple	406	No
PARML	Parameter list	Multiple	424	No
PS	Point-and-Shoot	Multiple	438	No
RP	Reference phrase	Multiple	454	No
SL	Simple list	Multiple	480	No
UL	Unordered list	Multiple	491	No
XMP	Example	Multiple	508	No

## Example

The following help panel markup contains a definition list with three definition descriptions. Figure 104 on page 287 shows the formatted result.



## Description

The DDHD tag defines the heading for the description column of a definition list. You can code multiple DDHD tags within a definition list.

The conversion utility inserts a blank line between the header and the list items unless the COMPACT attribute is specified on the DL tag.

## Conditions

- You must code the DDHD tag within a DL definition. See “DL (Definition List)” on page 292 for a complete description of this tag.
- Each DDHD tag must be paired with and follow a DTHD tag. See “DTHD (Definition Term Header)” on page 319 for a complete description of this tag.

## Nested Tags

You can code the following tags within a DDHD definition:

Tag	Name	Usage	Page	Required
HP	Highlighted phrase	Multiple	348	No
PS	Point-and-Shoot	Multiple	438	No
RP	Reference phrase	Multiple	454	No

## Example

The following help panel markup contains a definition description header with the text “Meaning”. Figure 105 shows the formatted result.

```
<!DOCTYPE DM SYSTEM>


<HELP NAME=ddhd DEPTH=18>Prefix Help
<AREA>
<INFO>
  <P>The following list defines each of the valid prefixes.
  <DL TSIZE=12>
    <DTHD>Prefix
    <DDHD>Meaning
    <DT>AU
    <DD>Automotive
    <DT>HB
    <DD>Health and beauty
    <DT>LG
    <DD>Lawn and garden
    <DT>SG
    <DD>Sporting goods
  </DL>
</INFO>
</AREA>
</HELP>
```

Prefix Help		
The following list defines each of the valid prefixes.		
Prefix	Meaning	
AU	Automotive	
HB	Health and beauty	
LG	Lawn and garden	
SG	Sporting goods	
F1=Help	F3=Exit	F5=Exhelp
F6=Keyshelp	F7=PrvTopic	F8=NxtTopic
F10=PrvPage	F11=NxtPage	F12=Cancel

Figure 105. Definition Description Header

## DIVIDER (Area Divider)

The DIVIDER tag creates a blank or visible divider within the text portion of an application panel.



### TYPE=NONE | SOLID | DASH | TEXT

This attribute specifies the type of divider line. The line width is one character.

The default value is NONE, which produces a blank line. You must specify SOLID, DASH, or TEXT to produce a visible divider line. When the GRAPHIC invocation option is specified, SOLID produces a solid line for host display and DASH produces a dashed line. When NOGRAPHIC is specified or the panel is displayed in GUI mode, both SOLID and DASH produce a dashed line.

### GAP=YES | NO

When GAP=NO, the divider line completely crosses from one side of the text area to the other. When GAP=YES, a 1-character gap remains at each end of the divider line. However, GAP=YES is ignored and set to NO for dividers coded within horizontal regions.

### GUTTER=1 | n

This attribute specifies the total width of the divider. If the GUTTER value is an even number, the conversion utility increases the number by 1 so that the divider is centered within the defined width.

The minimum GUTTER value is 1. If GUTTER=1 on a DIVIDER within a horizontal region, then the TYPE value must be NONE.

## DIVIDER

The default GUTTER value for a DIVIDER within a vertical region is 1. The default GUTTER value for dividers within horizontal regions is 3 to allow for an attribute byte on each side of the divider character.

### NOENDATTR

This attribute is valid only when the DIVIDER tag is coded within a horizontal region. It specifies that no ending attribute character will be placed after the divider character.

**Note:** The minimum divider space that can be specified for a horizontal region is 1.

When the GUTTER value is 1, the divider character is set to blank.

When the GUTTER value is 2, a solid divider may be specified. The divider character is placed in the second position of the 2-character GUTTER space.

### FORMAT=START | CENTER | END

This attribute specifies the position of the divider text within the width of the divider line.

### divider-text

This is the text of the area divider line.

## Description

The DIVIDER tag creates a blank or solid divider within the text portion of an application panel. A horizontally formatted visible divider is created when you specify the TYPE attribute value as SOLID or DASH. When the GRAPHIC invocation option is specified, SOLID produces a solid line for host display and DASH produces a dashed line. When NOGRAPHIC is specified or the panel is displayed in GUI mode, both SOLID and DASH produce a dashed line. A vertically formatted SOLID or DASH divider is the “|” character which is obtained from the ISPF literals table. The direction of the divider is determined by the tag definition it is coded within. Formatting for dividers are as follows:

- Dividers coded within an AREA, HELP, or PANEL tag definition format horizontally.
- Dividers coded within a vertical region format horizontally.
- Dividers coded within a horizontal region format vertically.

The divider line can be formatted with descriptive text. When this feature is used, the FORMAT attribute must be specified. If FORMAT is not specified, the tag text is ignored. You control the text padding with the TYPE attribute. If TYPE=TEXT, the *divider-text* is padded with blanks. When TYPE=SOLID or TYPE=DASH, the *divider-text* is padded with the specified character.

## Conditions

- You must code the DIVIDER tag within an AREA, DTACOL, HELP, PANEL, or REGION definition. See “AREA (Area)” on page 217, “DTACOL (Data Column)” on page 300, “HELP (Help Panel)” on page 335, “PANEL (Panel)” on page 413, and “REGION (Region)” on page 446 for descriptions of these tags.

## Nested Tags

You can code the following tags within a DIVIDER definition:

Tag	Name	Usage	Page	Required
HP	Highlighted phrase	Multiple	348	No

## Example

The following application panel markup contains four DIVIDER definitions. The first divider is blank. The second divider is solid with a gutter size of 2 and a GAP=NO value. The third and fourth dividers are solid. Figure 106 on page 292 shows the formatted result.

```
<!DOCTYPE DM SYSTEM(
  <!entity sampvar3 system>)>
&sampvar3;

<PANEL NAME=divider DEPTH=22 WIDTH=70>Print a Document
<AREA>
  <DTACOL PMTWIDTH=20 ENTWIDTH=8 SELWIDTH=40 DESWIDTH=35>
    <DTAFLD DATAVAR=file>File name
      <DTAFLDD>Name of the document to be printed
        <DIVIDER TYPE=none>
          <SELFLD NAME=type PMTLOC=before>Type style for printing
            <CHOICE>Prestige Elite (12 pitch)
            <CHOICE>Courier (10 pitch)
            <CHOICE>Essay Standard (proportional)
            <CHOICE>Essay Bold (proportional)
          </SELFLD>
        </DTACOL>
        <DIVIDER TYPE=solid GUTTER=2 GAP=no>
        <DTACOL PMTWIDTH=20 ENTWIDTH=2 DESWIDTH=35>
          <DTAFLD DATAVAR=marg>Left margin
            <DTAFLDD>Number of spaces in the left margin
              <DIVIDER TYPE=solid>
                <DTAFLD DATAVAR=copy>Copies
                  <DTAFLDD>Number of copies
                    <DIVIDER TYPE=solid>
                      <DTAFLD DATAVAR=dupl x ENTWIDTH=1>Duplex
                        <DTAFLDD>1 = Yes (Print both sides of paper)
                        <DTAFLDD>2 = No (Print one side only)
                      </DTACOL>
                    </AREA>
                  </PANEL>
```

Print a Document

File name . . . . . \_\_\_\_\_ Name of the document to be printed

Type style for  
printing . . . . . \_ 1. Prestige Elite (12 pitch)  
2. Courier (10 pitch)  
3. Essay Standard (proportional)  
4. Essay Bold (proportional)

-----

Left margin . . . . . \_ Number of spaces in the left margin

-----

Copies . . . . . \_ Number of copies

-----


Duplex . . . . . \_ 1 = Yes (Print both sides of paper)  
2 = No (Print one side only)

F1=Hel p    F3=Exi t    F12=Cancel

Figure 106. Area Dividers

## DL (Definition List)

The DL tag defines a list of terms and their corresponding definitions within an information region.



### **TSIZE=10 | 's1 s2... sn'**

This attribute specifies the space to be allocated for the definition term. The default value is 10 characters. The minimum TSIZE value is 0 and the maximum is 40. When multiple TSIZE values are specified, a DT tag must be coded for each value. The sizes are applied to the DT tags in the order the tags are encountered in the DTL source file.

### **BREAK=NONE | FIT | ALL**

This attribute controls the formatting of the definition terms and descriptions. If BREAK=NONE, the term is on the same line as the description, spilling into the description area if the length exceeds TSIZE. If BREAK=FIT, the description is on the line below the term if the term exceeds the TSIZE value. If BREAK=ALL, every definition is on the line below the term.

### **COMPACT**

This attribute causes the list to format without a blank line between the items

in the list. If you code DDHD and DTHD tags in a compact definition list, the list formats without a blank line between the headers and list items.

**NOSKIP**

This attribute causes the list to format without creating a blank line before the first line of the list.

**INDENT=n**

This attribute specifies that the definition list is to be indented from the current left margin.

**FORMAT=START | CENTER | END**

This attribute specifies the placement of the DT tag text within the space specified by TSIZE. The DL tag FORMAT setting applies to all of the DT tags within the definition list.

**DIVEND=NO | YES**

This attribute specifies a divider character will be formatted following the DDHD and DD tag text. When DIVEND=YES the formatting width of the DDHD and DD text is reduced to allow space for the divider character.

**SPLIT=NO | YES**

This attribute controls the format of the last DT tag in a multiple DT tag group. It is used only when BREAK=ALL or when BREAK=FIT and the DT tag text length exceeds the TSIZE value. When SPLIT=YES, the text following the last DT tag in the DT group (typically one or two dashes) is placed in front of the first line of the formatted DD tag text. The DL tag SPLIT setting applies to all of the DT tag groups within the definition list.

## Description

The DL tag defines a list of terms and their corresponding definitions within an information region. You use the DT and DD tags to identify the terms that you are defining and their descriptions, respectively. You use the DTHD and the DDHD tags to define headings for the term and description columns in definition lists.

The conversion utility inserts a blank line before the definition list unless NOSKIP is specified.

If you do not specify a TSIZE value, the space allocated for the term size is 10 characters. If any term is longer than 10 characters and BREAK=NONE (the default) is specified, the term will extend into the description line. If the term is still too long to fit, it will wrap to the next line.

The definition description is an implied paragraph, and can contain any text items. For example, you can insert additional paragraphs in a definition description by using the paragraph (P) tag following the description paragraph. Other tags that you want to nest within the definition list (such as OL, SL, or UL) must follow the DD tag within the list.

## Conditions

- The DL tag requires an end tag.
- You must code the DL tag within an INFO definition. See “INFO (Information Region)” on page 350 for a complete description of this tag.
- If you code DDHD and DTHD tags within the definition list, they must precede the first DT tag.

## Nested Tags

You can code the following tags within a DL definition:

Tag	Name	Usage	Page	Required
DD	Definition description	Multiple	285	No
DDHD	Definition description header	Multiple	287	No
DLDIV	Definition List Divider	Multiple	296	No
DT	Definition term	Multiple	298	No
DTDIV	Definition Term Divider	Multiple	318	No
DTHD	Definition term header	Multiple	319	No
DTHDIV	Definition Term Header Divider	Multiple	321	No

## Example

The following help panel markup contains a definition list that uses the default BREAK value of NONE, which formats the definition descriptions on the same line as the associated terms. Definition term and description headers are also included. Figure 107 on page 295 shows the formatted result of the markup. Figure 108 on page 295 shows how the same definition list would format with a BREAK value of FIT. Figure 109 on page 296 shows how the same definition list would format with a BREAK value of ALL.

```
<!DOCTYPE DM SYSTEM>

<HELP NAME=dl DEPTH=22 WIDTH=60>Employee Code Help
  <AREA>
  <INFO>
  <P>The following list defines the valid employee codes.
  <DL TSIZE=11>
  <DTHD>Code
  <DDHD>Meaning
  <DT>Full-time
  <DD>Indicates that the employee works a
  regular schedule of 40 hours or more weekly.
  <DT>Part-time
  <DD>Indicates that the employee works a regular
  schedule of 20 to 40 hours weekly.
  <DT>Supplemental
  <DD>Indicates that the employee works less than
  20 hours weekly.
  No regular schedule is in place.
  </DL>
  </INFO>
  </AREA>
</HELP>
```

Employee Code Help			
The following list defines the valid employee codes.			
Code	Meaning		
Full-time	Indicates that the employee works a regular schedule of 40 hours or more weekly.		
Part-time	Indicates that the employee works a regular schedule of 20 to 40 hours weekly.		
Supplemental	Indicates that the employee works less than 20 hours weekly. No regular schedule is in place.		
F1=Help	F3=Exit	F5=Exhelp	F6=Keyshelp
F7=PrvTopic	F8=NxtTopic	F10=PrvPage	F11=NxtPage
F12=Cancel			

Figure 107. Definition List (BREAK=NONE)

Employee Code Help			
The following list defines the valid employee codes.			
Code	Meaning		
Full-time	Indicates that the employee works a regular schedule of 40 hours or more weekly.		
Part-time	Indicates that the employee works a regular schedule of 20 to 40 hours weekly.		
Supplemental	Indicates that the employee works less than 20 hours weekly. No regular schedule is in place.		
F1=Help	F3=Exit	F5=Exhelp	F6=Keyshelp
F7=PrvTopic	F8=NxtTopic	F10=PrvPage	F11=NxtPage
F12=Cancel			

Figure 108. Definition List (BREAK=FIT)





Figure 109. Definition List (BREAK=ALL)

## DLDIV (Definition List Divider)

The DLDIV tag creates a blank or visible divider within the text portion of an application panel.



### TYPE=NONE | SOLID | DASH | TEXT

This attribute specifies the type of divider line. The line width is one character.

The default value is NONE, which produces a blank line. You must specify SOLID, DASH, or TEXT to produce a visible divider line. When the GRAPHIC invocation option is specified, SOLID produces a solid line for host display and DASH produces a dashed line. When NOGRAPHIC is specified or the panel is displayed in GUI mode, both SOLID and DASH produce a dashed line.

### GAP=YES | NO

When GAP=NO, the divider line completely crosses from one side of the text area to the other. When GAP=YES, a 1-character gap remains at each end of the divider line.

### GUTTER=1 | n

This attribute specifies the total width of the divider. If the GUTTER value is an even number, the conversion utility increases the number by 1 so that the divider is centered within the defined width.

The minimum GUTTER value, and the default, is 1.

#### FORMAT=START | CENTER | END

This attribute specifies the position of the divider text within the width of the divider line.

#### divider-text

This is the text of the area divider line.

## Description

The DLDIV tag creates a blank or solid divider within the text portion of an application panel. A horizontally formatted visible divider is created when you specify the TYPE attribute value as SOLID or DASH. When the GRAPHIC invocation option is specified, SOLID produces a solid line for host display and DASH produces a dashed line. When NOGRAPHIC is specified or the panel is displayed in GUI mode, both SOLID and DASH produce a dashed line.

The divider line can be formatted with descriptive text. When this feature is used, the FORMAT attribute must be specified. If FORMAT is not specified, the tag text is ignored. You control the text padding with the TYPE attribute. If TYPE=TEXT, the *divider-text* is padded with blanks. When TYPE=SOLID or TYPE=DASH, the *divider-text* is padded with the specified character.

## Conditions

- You must code the DLDIV tag within a DL tag.

## Nested Tags

You can code the following tags within a DLDIV definition:

Tag	Name	Usage	Page	Required
HP	Highlighted phrase	Multiple	348	No

## Example

The following example illustrates the use of the DLDIV tag in combination with the multiple DT tag function and the DIVEND attribute of the DL tag. Figure 110 on page 298 shows the formatted result.

## DLDIV

```
<!DOCTYPE DM SYSTEM>

<HELP NAME=dldiv DEPTH=22 WIDTH=60>Employee Code Help
  <AREA>
  <INFO>
  <P>The following list defines the valid employee codes.
  <DL TSIZE=14 BREAK=none>
    <DLDIV TYPE=SOLID>
    <DTHD>Code
    <DDHD>Meaning
    <DLDIV TYPE=SOLID>
    <DT NOSKIP>Full-time
    <DD>Indicates that the employee works a
    regular schedule of 40 hours or more weekly.
    <DT>Part-time
    <DD>Indicates that the employee works a regular
    schedule of 20 to 40 hours weekly.
    <DT>Supplemental
    <DD>Indicates that the employee works less than
    20 hours weekly.
    No regular schedule is in place.
  </DL>
</INFO>
</AREA>
</HELP>
```

Code	Meaning
Full-time	Indicates that the employee works a regular schedule of 40 hours or more weekly.
Part-time	Indicates that the employee works a regular schedule of 20 to 40 hours weekly.
Supplemental	Indicates that the employee works less than 20 hours weekly. No regular schedule is in place.

Figure 110. Definition List Dividers

## DT (Definition Term)

The DT tag defines a term in a definition list.

```
--<DT>
  |
  |---[FORMAT=]---[START]---[NOSKIP]---[SPLIT=]---[NO]
  |               |         |         |         |
  |               |         |         |         |
  |               |---[CENTER]---[YES]
  |               |         |
  |               |---[END]---
```

```
-> [definition-term] [ </DT> ]
```

### **FORMAT=START | CENTER | END**

This attribute specifies the placement of the DT tag text within the space specified by TSIZE. The DT tag FORMAT setting overrides the FORMAT specified in the enclosing DL tag.

### **NOSKIP**

This attribute causes the definition term to be formatted without a blank line before the term. It is used to control the formatting of the definition term when COMPACT has not been specified on the enclosing DL tag. When the DL tag TSIZE attribute specifies that multiple DT tags are to be formatted for each DD tag, NOSKIP should be coded on the first DT tag. It is ignored for the second and subsequent DT tags.

### **SPLIT**

This attribute controls the format of the last DT tag in a multiple DT tag group. It is used only when BREAK=ALL or when BREAK=FIT and the DT tag text length exceeds the TSIZE value. When SPLIT=YES, the text following the last DT tag in the DT group (typically one or two dashes) is placed in front of the first line of the formatted DD tag text. The DT tag SPLIT setting overrides the SPLIT specified in the enclosing DL tag.

### **definition-term**

This is the text of the definition term.

## **Description**

The DT tag defines a term in a definition list.

## **Conditions**

- You must code the DT tag within a DL definition. See “DL (Definition List)” on page 292 for a complete description of this tag.
- Each DT tag must be paired with and precede a DD tag.

## **Nested Tags**

You can code the following tags within a DT definition:

Tag	Name	Usage	Page	Required
DTSEG	Definition term segment	Multiple	322	No
HP	Highlighted phrase	Multiple	348	No
PS	Point-and-Shoot	Multiple	438	No
RP	Reference phrase	Multiple	454	No

## **Example**

The following help panel markup contains a definition list with three definition terms. Each definition term is paired with an associated definition description. Figure 111 on page 300 shows the formatted result.

```

<!DOCTYPE DM SYSTEM>

<HELP NAME=dt DEPTH=22 WIDTH=64>Help for Markup
<AREA>
<INFO>
  <P>Here are some definitions:
  <DL TSIZE=2 BREAK=all>
    <DT>markup
    <DD>Text that is added to document data in order to
    convey information about it.
    There are three types of markup the DTL uses: tags, references,
    and markup declarations.
    <DT>markup declaration
    <DD>Markup that controls how other markup of a document
    is to be interpreted, for example document type and entity declarations.
    <DT>markup language
    <DD>A set of characters, conventions, and rules to control
    the interpretation of document data.
    The Dialog Tag Language is a markup language.
  </DL>
</INFO>
</AREA>
</HELP>

```





Figure 111. Definition Terms

## DTACOL (Data Column)

The DTACOL tag defines default values for data fields (DTAFLD) and selection fields (SELFLD) that are coded within a DTACOL definition.



**PMTWIDTH=*n* | \* | \*\***

This attribute specifies the number of bytes reserved for prompts for data fields and selection fields coded within the data column. The minimum width is 0 and the maximum is the remaining available panel width. When you specify PMTWIDTH=\*, the conversion utility uses the length of the prompt text as the prompt width. When you specify PMTWIDTH=\*\*, the conversion utility uses the maximum available space as the prompt width. If PMTFMT=CUA is specified (or defaulted) and the prompt text has fewer characters than the field allows, leader dots fill the remaining spaces. For output-only data fields, a colon is also added as the last character in the prompt width space. If any prompt contains more characters than the width you specify, the prompt is word-wrapped to fit on multiple lines.

**Note:** Any field within the data column defining a prompt width overrides the DTACOL PMTWIDTH value.

**ENTWIDTH=*n***

This attribute specifies the number of bytes reserved for data fields coded within the data column. The minimum width is 1 and the maximum is the remaining available panel (or region) width.

**Note:** Any data field within the data column defining an entry width overrides the DTACOL ENTWIDTH value.

**DESWIDTH=*n* | \***

This attribute specifies the number of bytes reserved for the description text of the enclosed DTAFLDD tags. The minimum width is 0. When you specify DESWIDTH=\*, the conversion utility uses the length of the description text as

the description width. If the text is longer than the width you specify, the text is word-wrapped to fit on multiple lines.

**Note:** Any data field within the data column defining a description width overrides the DTACOL DESWIDTH value.

**SELWIDTH=n | \***

This attribute specifies the number of bytes reserved for choices in selection fields coded within the data column. The minimum width value is 1 and the maximum is the remaining available panel width. If the width required by the *choice-text* and its entry field exceeds the specified SELWIDTH value, the text is wrapped to multiple conversion utility will use the remaining available panel (or region) width.

**Note:** Any selection field within the data column defining a selection width overrides the DTACOL SELWIDTH value.

**FLDSPACE=n**

This attribute specifies the number of bytes reserved for the data field. The minimum width is 2 and the maximum is the remaining available panel (or region) width. The FLDSPACE value should include the actual entry width plus the number of entry field attributes. If the value specified by ENTWIDTH (plus attributes) is less than the specified FLDSPACE value, the entry field is padded with blanks to the FLDSPACE value. This will create blank space between the entry field and description text provided by the DTAFLDD tag and allows you to align description text from successive DTAFLD definitions.

**Note:** Any data field within the data column defining field space overrides the DTACOL FLDSPACE value.

**PAD=NULLS | USER | char | %varname**

This attribute specifies the pad character for initializing the field. You can define this attribute as a variable name preceded by a "%".

**Note:** Any data field within the data column defining PAD overrides the DTACOL PAD value.

**PADC=NULLS | USER | char | %varname**

This attribute specifies the conditional padding character to be used for initializing the field. You can define this attribute as a variable name preceded by a "%".

**Note:** Any data field within the data column defining PADC overrides the DTACOL PADC value.

**OUTLINE=NONE | L | R | O | U | BOX | %varname**

This attribute provides for displaying lines around the field on a DBCS terminal. You can define this attribute as a variable name preceded by a "%".

**Note:** Any data field within the data column defining OUTLINE overrides the DTACOL OUTLINE value.

**PMTFMT=CUA | ISPF | NONE | END**

This attribute controls the generation of prompt leader characters. The default is to create CUA leader dots. When ISPF is specified, and at least 4 bytes of prompt text space remain following the prompt text, the "====>" character string is placed in the rightmost 4 positions of the prompt text space. When

NONE is specified, no leader characters are added to the prompt text. When END is specified, the prompt text is right justified within the prompt text space.

**Note:** Any data field within the data column defining PMTFMT overrides the DTACOL PMTFMT value.

#### **AUTOTAB=NO | YES**

When AUTOTAB=YES, the cursor moves to the next field capable of input when the user enters the last character in this field. If no other field capable of user input exists on the panel, the cursor returns to the beginning of this field. The ISPF SKIP keyword is not supported when running in GUI mode.

**Note:** Any data field within the data column defining AUTOTAB overrides the DTACOL AUTOTAB value.

#### **ATTRCHANGE=NO | YES | NEW**

When ATTRCHANGE=YES or ATTRCHANGE=NEW, the conversion utility formats an additional entry in the panel )ATTR section (that can apply to multiple data fields) instead of creating a unique “.ATTR(field-name)” entry in the )INIT section for each field. With this option, multiple DTAFLD tags with the same characteristics require fewer panel logic statements. ATTRCHANGE=NEW creates a new entry. ATTRCHANGE=YES uses an existing attribute, if possible.

**Note:** Any data field within the data column defining ATTRCHANGE overrides the DTACOL ATTRCHANGE value.

#### **PMTLOC=BEFORE | ABOVE**

This attribute defines the prompt location for the enclosed DTAFLD and SELFLD tags.

**Note:** Any data field or selection field within the data column defining PMTLOC overrides the DTACOL PMTLOC value.

#### **DBALIGN=YES | NO | PROMPT | FIELD | FORCE**

This attribute defines the DBALIGN value for the enclosed DTAFLD tags.

**Note:** Any data field within the data column defining DBALIGN overrides the DTACOL DBALIGN value.

#### **VARCLASS=variable-class-name**

This attribute defines the name of the variable class for enclosed CHOFLD and DTAFLD tags.

**Note:** Any data field within the data column defining VARCLASS overrides the DTACOL VARCLASS value.

#### **REQUIRED=NO | YES**

This attribute defines whether the fields for enclosed CHOFLD and DTAFLD tags *require* input.

**Note:** Any data field within the data column defining REQUIRED overrides the DTACOL REQUIRED value.

#### **CAPS=OFF | ON**

This attribute defines whether the fields for enclosed CHOFLD and DTAFLD tags are displayed in uppercase characters.

**Note:** Any data field within the data column defining CAPS overrides the DTACOL CAPS value.

**VARDCL=YES | NO**

When VARDCL=NO the data field name is not checked to the declared variable information provided with the VARCLASS and VARDCL tags for enclosed CHOFLD and DTAFLD tags.

**Note:** Any data field within the data column defining VARDCL overrides the DTACOL VARDCL value.

**Description**

The DTACOL tag defines default attribute values for data fields (DTAFLD), choice data fields (CHOFLD), and selection fields (SELFLD) that are coded within a DTACOL definition. This allows you to define common values for fields coded within the data column within a single tag definition.

The xxxWIDTH attributes are convenient for aligning fields on an application panel. Fields are laid out within the data column along boundaries established by the values specified on the DTACOL tag. The following example shows those boundaries:




Figure 112. PMTWIDTH, ENTWIDTH, FLDSpace, and DESWIDTH attributes

The prompt width (PMTWIDTH) is valid for data fields and selection fields coded within the data column description. The entry width (ENTWIDTH), field space (FLDSpace), and description width (DESWIDTH) are only used by enclosed DTAFLD tags. The selection width (SELWIDTH) is used only by enclosed SELFLD tags. All of the previous cases stated are true only when the enclosed DTAFLD or SELFLD tags do not specify values that override the DTACOL values.

**Note:** The SELFLD tag does not use the ENTWIDTH, DESWIDTH, FLDSpace, PAD, PADC, OUTLINE, AUTOTAB, ATTRCHANGE, DBALIGN, VARCLASS, REQUIRED, or CAPS attributes of the DTACOL tag.

If the combined PMTWIDTH, ENTWIDTH, and DESWIDTH values exceed the remaining available panel (or region) width, the conversion utility issues a warning message and attempts to fit the data in the available width by wrapping the text.

For data fields, first priority is given to the entry field. Second and third priorities are given to the prompt and description fields, respectively. These fields use the available width remaining after the width of the entry field is determined.

**Note:** Word wrapping can result in word truncation if insufficient width is available for the text.

**Conditions**

- The DTACOL tag requires an end tag.

- You must code the DTACOL tag within an AREA, PANEL, or REGION definition. You can code a DTACOL definition anywhere within these tags, but the start and end tags must enclose any DTAFLD or SELFLD tags to which it applies. See “AREA (Area)” on page 217, “PANEL (Panel)” on page 413, and “REGION (Region)” on page 446 for descriptions of these tags.
- If both PAD and PADC have been specified, PAD is ignored and PADC is used.
- When a “%varname” notation is found on any of the attributes that allow a variable name, the “%varname” entry must follow the standard naming convention described in “Rules for “%variable” Names” on page 205.

## Nested Tags

You can code the following tags within a DTACOL definition:

Tag	Name	Usage	Page	Required
COMMENT	Comment	Multiple	275	No
DIVIDER	Area divider	Multiple	289	No
DTAFLD	Data field	Multiple	306	No
GRPHDR	Group header	Multiple	332	No
SELFLD	Selection field	Multiple	464	No
SOURCE	Source	Multiple	482	No

## Example

The following application panel markup contains a data column that provides default width values for the enclosed data fields and data field descriptions. The ENTWIDTH value specified on the first and second data fields override the ENTWIDTH value specified on the DTACOL tag. Figure 113 on page 306 shows the formatted result.

```
<!DOCTYPE DM SYSTEM(
  <!entity sampvar1 system>
  <!entity sampabc system>)>
&sampvar1;

<PANEL NAME=dtacol2 KEYLIST=keyl xmp>Library Card Registration
<AB>
&sampabc;
</AB>
<TOPINST> Type in patron's name and card number (if applicable)
<TOPINST> Then select an action bar choice.
<AREA>
  <DTACOL PMTWIDTH=12 ENTWIDTH=25 DESWIDTH=25 SELWIDTH=25
    <DTAFLD DATAVAR=curdate USAGE=out ENTWIDTH=8>Date
    <DTAFLD DATAVAR=cardno ENTWIDTH=7>Card No.
      <DTAFLDD>(A 7-digit number)
    <DTAFLD DATAVAR=name>Name
      <DTAFLDD>(Last, First, M.I.)
    <DTAFLD DATAVAR=address>Address
  </DTACOL>
  <DIVIDER>
  <REGION DIR=horiz>
  <SELFLD NAME=cardsel PMTWIDTH=30 SELWIDTH=38>Choose
  one of the following
    <CHOICE CHECKVAR=card MATCH=new>New
    <CHOICE CHECKVAR=card MATCH=renew>Renewal
    <CHOICE CHECKVAR=card MATCH=replace>Replacement
  </SELFLD>
  <SELFLD TYPE=multi PMTWIDTH=30 SELWIDTH=25>Check valid branches
```

```

<CHOICE NAME=north HELP=nthlp CHECKVAR=nth>North Branch
<CHOICE NAME=south HELP=sthhlp CHECKVAR=sth>South Branch
<CHOICE NAME=east HELP=esthlp CHECKVAR=est>East Branch
<CHOICE NAME=west HELP=wsthlp CHECKVAR=wst>West Branch
</SELFLD>
</REGION>
</AREA>
<CMDAREA>Enter a command
</PANEL>

```

File Search Help

---

Library Card Registration

Type in patron's name and card number if applicable.

Then select an action bar choice.

Date . . . : 08/29/90

Card No. . . \_\_\_\_\_ (A 7-digit number)

Name . . . \_\_\_\_\_ (Last, First, M.I.)

Address . . \_\_\_\_\_

Choose one of the following

<p>1. New</p> <p>2. Renewal</p> <p>3. Replacement</p>	<p>Check valid branches</p> <p>— North Branch</p> <p>— South Branch</p> <p>— East Branch</p> <p>— West Branch</p>
---	---

Enter a command ===> \_\_\_\_\_


F1=Help    F2=Split    F3=Exit    F6=KEYSHELP    F9=Swap



F12=Cancel

Figure 113. Data Column

## DTAFLD (Data Field)

The DTAFLD tag defines an input field, an output field, or an input/output field on an application panel.



**IMAP Group:****NAME=field-name**

This attribute specifies the name of the field. The *field-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

The *field-name* can be used by:

- The PANEL tag to position the cursor

- The ISPF DISPLAY or TBDISPL services to position the cursor
- The ISPF ADDPOP service to position a pop-up.

**DATAVAR=field-data**

This attribute specifies the variable name for the data in the field. The value coded must be a variable-name without the leading % notation. The conversion utility considers NAME and DATAVAR to be synonymous. However, the value you assign DATAVAR has precedence. For example, if you specify different values for the DATAVAR and NAME attributes, the conversion utility uses the DATAVAR value as the name of the field on the panel.

**Compatibility Considerations**

DATAVAR is a required attribute for the DTAFLD tag. For compatibility between releases, you can code either the NAME or the DATAVAR attributes, or both.

**VARCLASS=variable-class-name**

This attribute specifies the name of the variable class, defined using a VARCLASS tag, that overrides the default variable class referred to by the VARDCL that declared the data variable for this field.

**HELP=NO | YES | help-panel-name | \*help-message-id | %varname | \*%varname**

This attribute specifies the help action taken when the user requests help for this data field. This is field-level help.

When HELP=YES, control is returned to the application. You can specify either a help panel or a message identifier. If a message identifier is used, it must be prefixed with an asterisk (\*).

The help attribute value can be specified as a variable name. When %varname is coded, a panel variable name is created. When \*%varname is coded, a message variable name is created.

If the user requests help for the data field and no help is defined, the extended help panel is displayed. If an extended help panel is not defined for the panel, the application or ISPF tutorial is invoked.

The *help-panel-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

See “HELP (Help Panel)” on page 335 for information about creating help panels. For information about creating messages, see “MSG (Message)” on page 390.

**USAGE=BOTH | IN | OUT**

This attribute indicates whether the field is for input only, output only, or both.

For USAGE=OUT, the conversion utility inserts a colon as the last character of the data field prompt to indicate to the user that it is an output-only field.

**REQUIRED=NO | YES**

This attribute indicates if the field requires input. This attribute is valid only when USAGE=IN or BOTH.

If REQUIRED=YES is coded, a VER(variable,NONBLANK) statement will be built by the conversion utility and placed in the )PROC section of the ISPF panel generated.

**MSG=message-identifier**

This attribute specifies the message that is displayed when the user does not complete a required entry (defined with the REQUIRED attribute). If you do not specify a *message-identifier*, ISPF displays a default message.

If you specify the MSG attribute and REQUIRED=YES, a VER(variable, NONBLANK, MSG=message-identifier) statement is built by the conversion utility and placed in the )PROC section of the ISPF panel generated. If you specify the MSG attribute and REQUIRED=NO (the default), the conversion utility issues a warning message.

See “MSG (Message)” on page 390 for information about creating messages.

**Note:** You can specify messages pertaining to other validations using XLATL and CHECKL tags within a VARCLASS definition. See the descriptions of these tags for additional information.

**AUTOTAB=NO | YES**

When AUTOTAB=YES, the cursor moves to the next field capable of input when the user enters the last character in this field. If no other field capable of user input exists on the panel, the cursor returns to the beginning of this field. The ISPF SKIP keyword is not supported when running in GUI mode.

AUTOTAB=YES is valid only when the value for USAGE is either BOTH or IN. If specified, this attribute overrides the AUTOTAB value of the DTACOL tag.

**ENTWIDTH=n**

This attribute specifies the number of bytes used for the data field. The minimum width is 1 and the maximum is the remaining available panel width less the required amount of space for field attributes. If ENTWIDTH is not provided on either the DTAFLD tag or the enclosing DTACOL tag, the conversion utility will use the width determined by the TYPE value of the associated VARCLASS.

If specified, this attribute overrides the ENTWIDTH value of the DTACOL tag.

**PMTWIDTH=n | \* | \*\***

This attribute specifies the number of bytes used for the data field *prompt-text*. The minimum width is 0 and the maximum is the remaining available panel (or region) width less the required amount of space for field attributes. When you specify PMTWIDTH=\*, the conversion utility uses the length of the prompt text as the prompt width. When you specify PMTWIDTH=\*\*, the conversion utility uses the maximum available space as the prompt width. If PMTFMT=CUA is specified (or defaulted) and the *prompt-text* has fewer characters than the field allows, leader dots fill the remaining spaces. If any prompt contains more characters than the width you specify, the prompt is word-wrapped to fit on multiple lines. If PMTWIDTH is not specified and *prompt-text* is present, the PMTWIDTH value will be defaulted to the length of the *prompt-text*.

If specified, this attribute overrides the PMTWIDTH value of the DTACOL tag.

**DESWIDTH=n | \***

This attribute specifies the number of bytes used for the description text of enclosed DTAFLDD tags. The minimum width is 0. When you specify DESWIDTH=\*, the conversion utility uses the length of the description text as the description width. If the text is longer than the width you specify, the text is word-wrapped to fit on multiple lines.

If specified, this attribute overrides the DESWIDTH value of the DTACOL tag.

**FLDSPACE=*n***

This attribute specifies the number of bytes reserved for the data fields coded within the data column. The minimum width is 2 and the maximum is the remaining available panel (or region) width. The FLDSPACE value should include the actual entry width plus the number of entry field attributes. If the value specified by ENTWIDTH is less than the specified FLDSPACE value, the entry field is padded with blanks to the FLDSPACE value. This will create blank space between the entry field and description text provided by the DTAFLDD tag and allows you to align description text from successive DTAFLD definitions.

If specified, this attribute overrides the FLDSPACE value of the DTACOL tag.

**ALIGN=START | CENTER | END**

This attribute specifies the alignment of data within the display field after all translations have been performed. Use this attribute to align the data with the start, the end, or the center of the display field.

This is accomplished in the conversion utility by using an attribute character for the field that specifies JUST(LEFT) if ALIGN=START or JUST(RIGHT) if ALIGN=END. ALIGN=CENTER will use an attribute character for the field that specifies JUST(ASIS).

Alignment occurs if the transformed value of the dialog variable is shorter than the display width of the field. When ALIGN=END, there is no underscore padding performed—blanks are used.

**PMTLOC=BEFORE | ABOVE**

This attribute specifies whether the *prompt-text* of the data field appears above or in front of the data field.

**DISPLAY=YES | NO**

This attribute specifies whether data will display on the screen when the user types it in. If you specify NO, the data will not display. This attribute is useful when creating fields for passwords or other information which you do not want to appear on the screen.

**NOENDATTR**

This attribute, which is valid only when WINDOW=NO is specified on the PANEL tag or DIR=HORIZ is specified on the REGION tag, specifies that no ending attribute will be placed after the data field. NOENDATTR is ignored for the last field on each panel line unless WINDOW=NO has been specified on the PANEL tag. NOENDATTR is valid only when the DTAFLD tag is followed by a DTAFLD, DTAFLDD, DIVIDER, or SELFLD tag.

**PAD=NULLS | USER | char | %varname**

This attribute specifies the pad character for initializing the field. You can define this attribute as a variable name preceded by a "%".

If specified, this attribute overrides the PAD value of the DTACOL tag.

**PADC= NULLS | USER | char | %varname**

This attribute specifies the conditional padding character to be used for initializing the field. You can define this attribute as a variable name preceded by a "%".

If specified, this attribute overrides the PADC value of the DTACOL tag.

**OUTLINE=NONE | L | R | O | U | BOX | %varname**

This attribute provides for displaying lines around the field on a DBCS terminal. You can define this attribute as a variable name preceded by a "%".

If specified, this attribute overrides the OUTLINE value of the DTACOL tag.

**PMTFMT=CUA | ISPF | NONE | END**

This attribute controls the generation of prompt leader characters. The default is to create CUA leader dots. When ISPF is specified, and at least 4 bytes of prompt text space remain following the prompt text, the "====>" character string is placed in the rightmost 4 positions of the prompt text space. When NONE is specified, no leader characters are added to the prompt text. When END is specified, the prompt text is right justified within the prompt text space.

If specified, this attribute overrides the PMTFMT value of the DTACOL tag.

**PSVAR=point-and-shoot-variable | %varname**

This attribute provides the name of a variable that is to be set when a DTAFLD is clicked on for point-and-shoot selection. You can define this attribute as a variable name preceded by a "%".

The *point-and-shoot-variable* must follow the standard naming convention described in "Rules for Variable Names" on page 205.

**PSVAL=point-and-shoot-value | %varname**

This attribute provides the value to be placed in the field specified by the PSVAR attribute. You can define this attribute as a variable name preceded by a "%". To specify a blank value, the "' ' " (quotation mark, apostrophe, blank, apostrophe, quotation mark) coding notation should be used.

**PAS=%varname**

This attribute can be used to provide a variable name to specify ON or OFF for point-and-shoot. When PSVAR and PSVAL have been specified without the PAS attribute, the point-and-shoot field will be automatically enabled.

**CSRGRP=NO | YES | N**

When CSRGRP=YES, the conversion utility generates a cursor group number to be used for this data field. When CSRGRP=n, the number provided is used for this field. The PAS attribute must be specified as %varname.

The CSRGRP attribute is accepted for all data fields. It is used at run-time for output fields only.

**EXPAND**

The EXPAND attribute, used in combination with EXPAND=xy on the PANEL definition, causes the expand characters to be added to the DTAFLD definition, effectively allowing ENTWIDTH to expand. The ENTWIDTH value must be specified as 4 or greater for the EXPAND function to operate.

**Note:** If the PANEL tag attribute EXPAND is defined with no value specified, the DTAFLD tag EXPAND attribute is not used.

**FLDWIDTH=n**

The FLDWIDTH attribute, used in combination with WINDOW=NO on the PANEL definition, provides the width of a DTAFLD which spans multiple lines.

FLDWIDTH cannot be used within any horizontal region.

**ATTRCHANGE=NO | YES | NEW**

When ATTRCHANGE=YES or ATTRCHANGE=NEW, the conversion utility

formats an additional entry in the panel )ATTR section (that can apply to multiple data fields) instead of creating a unique “.ATTR(field-name)” entry in the )INIT section for this field. With this option, multiple DTAFLD tags with the same characteristics require fewer panel logic statements.

ATTRCHANGE=NEW creates a new entry. ATTRCHANGE=YES uses an existing entry, if possible.

**INIT=initial-value**

When the INIT attribute is specified, the conversion utility adds a statement to the panel )INIT section to initialize the field to the *initial-value*.

**DEPTH=n | %varname**

This attribute defines the depth reserved for the field. When the panel is displayed in GUI mode, a field specified as point-and-shoot results in a push button displayed with the specified DEPTH. You use this attribute in combination with the IMAPNAME attribute to provide space for the image. The minimum value is 1 and the maximum value is the remaining panel depth.

**IMAPNAME=image-name | %varname**

This attribute specifies the name of an image to be placed on the point-and-shoot push button when it is displayed in GUI mode. The *image-name* is not used when the panel is displayed in host mode.

The *image-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

**IMAPNAMEP=image-namep | %varname**

This attribute specifies the name of an image to be placed on the point-and-shoot push button after it has been pushed when it is displayed in GUI mode. The *image-namep* is not used when the panel is displayed in host mode.

The *image-namep* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

**PLACE=ABOVE | BELOW | LEFT | RIGHT**

This attribute specifies the position of the image relative to the text within the point-and-shoot push button.

**DBALIGN=YES | NO | PROMPT | FIELD | FORCE**

This attribute defines the DBALIGN value. DBALIGN is used only for DBCS language conversions when PMTLOC=ABOVE and the DBALIGN invocation option is specified.

When DBALIGN=PROMPT, the start position of the prompt-text is shifted 1 position to the right.

When DBALIGN=FIELD, the start position of the data field is shifted 1 position to the right.

When DBALIGN=YES, and the prompt-text starts with a DBCS character, the data field is shifted. If DBALIGN=YES and the prompt text starts with an SBCS character or the prompt text is not provided, no shifting is done.

When DBALIGN=FORCE, both the prompt-text and the data field are shifted. DBALIGN=YES and DBALIGN=FORCE are useful to align a DTAFLD with another DTAFLD or SELFLD tag.

When DBALIGN=NO, no alignment adjustment is made.

**PMTSKIP=NO | YES**

This attribute is used for horizontal formatting of input fields. When

PMTSKIP=YES, and the previous DTAFLD definition includes the NOENDATTR attribute, the cursor moves past the prompt text to the input field when the user enters the last character in the previous field. If there is no other input field on the panel, the cursor returns to the first input field on the panel. The ISPF SKIP keyword is not supported in GUI mode.

#### **DESSKIP=NO | YES**

This attribute is used for horizontal formatting of input fields. When DESSKIP=YES, and the current DTAFLD definition includes the NOENDATTR attribute, the cursor skips over the description text provided by the DTAFLDD tag to the next input field when the user enters the last character in the current field. If there is no other input field on the panel, the cursor returns to the first input field on the panel. The ISPF SKIP keyword is not supported in GUI mode.

#### **FLDTYPE=CUA | ISPF**

This attribute defines the attribute type to be applied to the field. TYPE=CUA, the default, causes the field to display using the standard CUA attribute. When FLDTYPE=ISPF, a non-CUA attribute entry is generated for the )ATTR section, and you can specify the color, intensity, and highlighting of the attribute. See the COLOR, INTENS, and HILITE attributes that follow for more information. These attributes are not valid when FLDTYPE=CUA.

**Note:** IF DISPLAY=NO is specified, an .ATTR(...) is created to override this field.

#### **COLOR=WHITE | RED | BLUE | GREEN | PINK | YELLOW | TURQ | %varname**

This attribute specifies the color of the field. You can define this attribute as a variable name preceded by a percent (%) sign.

#### **INTENS=HIGH | LOW | NON | %varname**

This attribute defines the intensity of the field. You can define this attribute as a variable name preceded by a percent (%) sign.

#### **HILITE=USCORE | BLINK | REVERSE | %varname**

This attribute specifies the extended highlighting attribute of the field. You can define this attribute as a variable name preceded by a percent (%) sign.

#### **ATTRCHAR=code**

This attribute can be a single character or a two-position entry of valid hex digits. If you enter an incorrect value, a warning message is issued and the value is set to null. Hex entries are converted to character. Hex values '00'-'2F' are reserved for use by the conversion utility.

#### **CAPS=OFF | ON**

When CAPS=ON, the data in the field is displayed in uppercase characters.

#### **NOJUMP=OFF | ON**

When NOJUMP=ON, the JUMP function is disabled for the field.

#### **AUTOTYPE=PROJECT | GROUP1 | GROUP2 | GROUP3 | GROUP4 | TYPE | MEMBER | DSN**

This attribute specifies that ISPF panel logic be added to support the AUTOTYPE function.

AUTOTYPE=DSN is specified for data set name fields.

The other attribute values are used for ISPF- format project, group, type, and member name fields.

Multiple data fields can be specified with AUTOTYPE=DSN. Only one field can be specified with each of the other listed attribute values.

**AUTOVOL = volser name**

This attribute specifies an associated panel field for volume name when AUTOTYPE=DSN.

**AUTODMEM = YES | NO**

This attribute specifies whether a member name is part of the data set name when AUTOTYPE=DSN.

**VARDCL = YES | NO**

When VARDCL=NO the field name is not checked to the declared variable information provided with the VARCLASS and VARDCL tags.

**prompt-text**

This is the prompt text for the data field. The *prompt-text* appears in front of or above the field, depending on the setting of the PMTLOC attribute. If you do not specify prompt text, no text appears for the field.

If the *prompt-text* exceeds the width defined for a prompt, it is word-wrapped to multiple lines.

## Description

The DTAFLD tag defines an input field, an output field, or an input/output field on an application panel.

The formatted width of the field is 2 positions more than the ENTWIDTH value to provide for an attribute byte both before and after the field.

If PMTLOC=ABOVE, an attribute is placed both before and after the prompt text reserved space. If PMTLOC=BEFORE (or PMTLOC is not specified), and the DTAFLD is being formatted in a horizontal region, then an additional byte is used for the field prompt attribute when the field prompt is not at the left edge of the panel.

The DTAFLDD tag can be used to provide the description text for the data field.

## Conditions

- You must code the DTAFLD tag within an AREA, DTACOL, PANEL, or REGION definition. See “AREA (Area)” on page 217, “DTACOL (Data Column)” on page 300, “PANEL (Panel)” on page 413, and “REGION (Region)” on page 446 for descriptions of these tags.
- The variable name specified in the DATAVAR attribute should have an associated VARDCL definition. See “VARDCL (Variable Declaration)” on page 497 for a complete description of this tag.
- If both PAD and PADC have been specified, PAD is ignored and PADC is used.
- When a “%varname” notation is found on any of the attributes that allow a variable name, the “%varname” entry must follow the standard naming convention described in “Rules for “%variable” Names” on page 205.

## Nested Tags

You can code the following tags within a DTAFLD definition:

Tag	Name	Usage	Page	Required
ASSIGNL	Assignment list	Multiple	225	No

Tag	Name	Usage	Page	Required
COMMENT	Comment	Multiple	275	No
DTAFLDD	Data field description	Multiple	316	No
HP	Highlighted phrase	Multiple	348	No
PS	Point-and-Shoot	Multiple	438	No
RP	Reference phrase	Multiple	454	No
SCRFLD	Scrollable field	Single	456	No
SOURCE	Source	Multiple	482	No

## Example

The following source file markup contains an application panel with three data fields and the variable declarations and classes associated with the data fields. The **Date** field is an output-only field that displays the current date. The **Name** and **Password** fields are input/output fields. The **Password** field is defined as a required field, and specifies DISPLAY=NO, so the user input for this field will not be displayed. A data column specifying a default prompt width for the data fields is also defined. Figure 114 on page 316 shows the formatted result.

```
<!DOCTYPE DM SYSTEM>

<VARCLASS NAME=date TYPE=' char 8' >
<VARCLASS NAME=name TYPE=' char 25' >
<VARCLASS NAME=password TYPE=' char 8' >

<VARLIST>
  <VARDCL NAME=curdate VARCLASS=date>
  <VARDCL NAME=namevar VARCLASS=name>
  <VARDCL NAME=passvar VARCLASS=password>
</VARLIST>

<PANEL NAME=dtafld1 HELP=loghelp>System Logon
<TOPINST>Complete the following fields, then press Enter.
<AREA>
  <DTACOL PMTWIDTH=12>
    <DIVIDER>
      <DTAFLD DATAVAR=curdate USAGE=out ENTWIDTH=8 FLDSpace=27>Date
    <DTAFLDD>(Current Date)
    <DIVIDER>
      <DTAFLD DATAVAR=namevar ENTWIDTH=25 DESWIDTH=25>Name
      <DTAFLDD>(Last, First)
    <DIVIDER>
      <DTAFLD DATAVAR=passvar REQUIRED=yes ENTWIDTH=8 DISPLAY=no>Password
    </DTACOL>
  </AREA>
</PANEL>
```

System Logon

Complete the following fields, then press Enter.

Date . . . : 08/29/90 (Current Date)

Name . . . . \_\_\_\_\_ (Last, First)

Password . .

F1=Hel p    F3=Exi t    F12=Cancel

Figure 114. Data Fields

## DTAFLDD (Data Field Description)

The DTAFLDD tag defines descriptive text associated with a data field.

```

-<DTAFLDD>
└── description ─┘ └──</DTAFLDD>┘
  
```

### description

This is the descriptive text associated with the data field.

## Description

The DTAFLDD tag defines descriptive text associated with a data field. For example, it could explain what the application user can type into the field.

The text appears in the area defined by the DESWIDTH attribute of the DTAFLD or DTACOL tag.

You can specify more than one DTAFLDD tag for a given field. Each data field description starts a new line.

## Conditions

- You must code the DTAFLDD tag within the DTAFLD definition it is associated with. See “DTAFLD (Data Field)” on page 306 for a complete description of this tag.

## Nested Tags

You can code the following tags within a DTAFLDD definition:

Tag	Name	Usage	Page	Required
HP	Highlighted phrase	Multiple	348	No
PS	Point-and-Shoot	Multiple	438	No





```

<DD>Indicates that the employee works less than
20 hours weekly.
No regular schedule is in place.
<DLDIV TYPE=solid>
</DL>
</INFO>
</AREA>
</HELP>

```

Employee Code Help		
The following list defines the valid employee codes.		
Code	Flag	Meaning
Full-time	F	Indicates that the employee works a regular schedule of 40 hours or more weekly.
Part-time	P	Indicates that the employee works a regular schedule of 20 to 40 hours weekly.
Supplemental	S	Indicates that the employee works less than 20 hours weekly. No regular schedule is in place.

Figure 116. Definition Term Divider

## DTHD (Definition Term Header)

The DTHD tag defines the heading for the term column of a definition list.

```

—<DTHD>—definition-term-header—
└─</DTHD>─┘

```

### definition-term-header

This is the text of the definition term header. The length of the text for the definition term header should be less than the specified TSIZE value in the DL tag. A warning message is issued if the length of the text exceeds the limit.

## Description

The DTHD tag defines the heading for the term column of a definition list. You can code multiple DTHD tags within a definition list.

The conversion utility inserts a blank line between the header and the list items unless the COMPACT attribute is specified on the DL tag.

## Conditions

- You must code the DTHD tag within a DL definition. See “DL (Definition List)” on page 292 for a complete description of this tag.
- Each DTHD tag must be paired with and precede a definition description header (DDHD) tag.

## Nested Tags

You can code the following tags within a DTHD definition:

Tag	Name	Usage	Page	Required
HP	Highlighted phrase	Multiple	348	No
PS	Point-and-Shoot	Multiple	438	No
RP	Reference phrase	Multiple	454	No

## Example

The following help panel markup contains a definition term header with the text "Prefix". Figure 117 shows the formatted result.

```
<!DOCTYPE DM SYSTEM>

<HELP NAME=dthd DEPTH=18>Prefix Help
<AREA>
<INFO>
  <P>The following list defines each of the valid prefixes.
  <DL TSIZE=12>
    <DTHD>Prefix
    <DDHD>Meaning
    <DT>AU
    <DD>Automotive
    <DT>HB
    <DD>Health and beauty
    <DT>LG
    <DD>Lawn and garden
    <DT>SG
    <DD>Sporting goods
  </DL>
</INFO>
</AREA>
</HELP>
```

Prefix Help		
The following list defines each of the valid prefixes.		
Prefix	Meaning	
AU	Automotive	
HB	Health and beauty	
LG	Lawn and garden	
SG	Sporting goods	
F1=Help	F3=Exit	F5=Exhelp
F6=Keyshelp	F7=PrvTopic	F8=NxtTopic
F10=PrvPage	F11=NxtPage	F12=Cancel

Figure 117. Definition Term Header

## DTHDIV (Definition Term Header Divider)

The DTHDIV tag defines a visible vertical divider (|) between multiple DTHD tags.

```
—<DTHDIV>|</DTHDIV>—
```

### Description

The DTHDIV tag can be used to create a visual separation between the definition term headings. Each DTHDIV tag adds a vertical bar (plus display control attributes) to the Definition Term Header text.

### Conditions

The DTHDIV tag can be coded before the first DTHD tag, between DTHD tags, or following the last DTHD tag (before the DDHD tag definition).

### Nested Tags

None.

### Example

The following example illustrates the use of the DTHDIV tag in combination with the multiple DT tag function and the DIVEND attribute of the DL tag. Figure 118 on page 322 shows the formatted result.

```
<!DOCTYPE DM SYSTEM>

<HELP NAME=dthdiv DEPTH=22 WIDTH=66>Employee Code Hel p
  <AREA depth=1 extend=on>
  <INFO width=*>
    <P>The following list defines the valid employee codes.
    <DL TSIZE='14 4' BREAK=none COMPACT DIVEND=yes>
      <DLDIV TYPE=solid>
        <DTHDIV>
        <DTHD>Code
        <DTHDIV>
        <DTHD>Flag
        <DTHDIV>
        <DDHD>Meaning
        <DLDIV TYPE=solid>
        <DTDIV>
        <DT NOSKIP>Full-time
        <DTDIV>
        <DT FORMAT=center>F
        <DTDIV>
        <DD>Indicates that the employee works a
        regular schedule of 40 hours or more weekly.
        <DLDIV TYPE=solid>
        <DTDIV>
        <DT>Part-time
        <DTDIV>
        <DT FORMAT=center>P
        <DTDIV>
        <DD>Indicates that the employee works a regular
        schedule of 20 to 40 hours weekly.
        <DLDIV TYPE=solid>
        <DTDIV>
        <DT>Supplemental
        <DTDIV>
```

```

<DT FORMAT=center>S
<DTDIV>
<DD>Indicates that the employee works less than
20 hours weekly.
No regular schedule is in place.
<DLDIV TYPE=solid>
  </DL>
</INFO>
</AREA>
</HELP>

```

Employee Code Help		
The following list defines the valid employee codes.		
Code	Flag	Meaning
Full-time	F	Indicates that the employee works a regular schedule of 40 hours or more weekly.
Part-time	P	Indicates that the employee works a regular schedule of 20 to 40 hours weekly.
Supplemental	S	Indicates that the employee works less than 20 hours weekly. No regular schedule is in place.

Figure 118. Definition Term Header Divider

## DTSEG (Definition Term Segment)

The DTSEG tag defines a segment of the definition term. It is used to provide vertical separation of the DT tag text.

```

--<DTSEG>
└─</DTSEG>─┘

```

### Description

The DTSEG tag is used to create a vertical separation within the definition term. The text following the DTSEG tag is formatted directly under any previous definition term tag text. Multiple DTSEG tags create additional DT text lines.

Use of the DTSEG tag affects the DL tag BREAK attribute. The first (or only) line of DT tag text is processed according to the BREAK attribute of the DL tag. For additional lines, when TSIZE is large enough to accommodate the text segments, the DTSEG text is formatted in front of the associated DD tag text. When TSIZE is not large enough to accommodate the largest segment, all of the DT and DTSEG text is formatted above the associated DD tag text.

### Conditions

- The DTSEG tag can be coded within the text following a DT tag.
- When a DTSEG tag is coded, then all remaining DT tag text for the current DT tag set must follow a DTSEG tag.

- The DT nested tags RP and PS are not supported within DT tag text following any DTSEG tag in a DT/DD tag set.

## Nested Tags

You can code the following tag within a DTSEG definition:

Tag	Name	Usage	Page	Required
HP	Highlighted phrase	Multiple	348	No

## Example

The following example illustrates the use of the DTSEG tag in combination with a multiple DT tag set. The last DT tag includes the SPLIT=yes attribute to format the dash in front of the DD tag text. Figure 119 on page 324 shows the formatted result.

```
<!DOCTYPE DM SYSTEM(>

<PANEL NAME=dtseg KEYLIST=ISRHELP APPLID=ISR WINDOW=no PADC=user
      TUTOR ZUP=ISP7R000>Traces - Primary Commands

<CMDAREA CAPS=on>
<AREA DEPTH=1 EXTEND=on>

  <INFO WIDTH=*>
    <P>
      Enter a <hp>Primary Command</hp> in the command input field.
      It is processed after all row modifications and all line commands
      are processed. The following primary commands are valid for the
      Traces options:

    <DL TSIZE="8 1" BREAK=fit INDENT=2>
      <DT>
        LOCATE
        function-name
        (Function Traces) or variable name (Variable Traces)
        <DTSEG>
        LOC or
        <DTSEG>
        L
      <DT SPLIT=yes>-
      <DD>The LOCATE command positions the scrollable display at the
        first (or next) row containing the function name (Function
        Traces option) or the variable name (Variable Traces option).
    </DL>
  </INFO>
</AREA>
</PANEL>
```



A figure can also contain a figure caption, defined with the FIGCAP tag (see “FIGCAP (Figure Caption)” on page 326).

## Conditions

- The FIG tag requires an end tag.
- You must code the FIG tag within an INFO definition. See “INFO (Information Region)” on page 350 for a complete description of this tag.

## Nested Tags

You can code the following tags within a FIG definition:

Tag	Name	Usage	Page	Required
DL	Definition list	Multiple	292	No
FIGCAP	Figure caption	Single	326	No
HP	Highlighted phrase	Multiple	348	No
NOTE	Note	Multiple	396	No
NOTEL	Note List	Multiple	399	No
NT	Note	Multiple	402	No
OL	Ordered list	Multiple	404	No
P	Paragraph	Multiple	406	No
PARML	Parameter list	Multiple	424	No
PS	Point-and-Shoot	Multiple	438	No
RP	Reference phrase	Multiple	454	No
SL	Simple list	Multiple	480	No
UL	Unordered list	Multiple	491	No
XMP	Example	Multiple	508	No

## Example

The following help panel markup contains a figure definition with a ruled frame. The output of the text within the figure definition is identical to the *figure-content*. Figure 120 on page 326 shows the formatted result.

```
<!DOCTYPE DM SYSTEM>

<HELP NAME=fig DEPTH=20>ShellBrowse Help
<AREA>
<INFO>
  <FIG>

    We're your local library...

    CHECK US OUT!

  </FIG>
</INFO>
</AREA>
</HELP>
```

## FIGCAP



Figure 120. Figure

---

## FIGCAP (Figure Caption)

The FIGCAP tag defines a caption for a figure defined with the FIG tag.

```
--<FIGCAP>-----  
|figure-caption-text| |</FIGCAP>|
```

### figure-caption-text

This is the text of the figure caption.

## Description

The FIGCAP tag defines a caption for a figure defined with the FIG tag. The figure caption is formatted below the frame of the figure when FRAME=RULE is specified on the FIG tag.

The conversion utility does not add any blank lines before or after the figure caption.

## Conditions

- You must code the FIGCAP tag within a FIG definition. See “FIG (Figure)” on page 324 for a complete description of this tag.
- You can code only one FIGCAP within a FIG definition. Code the FIGCAP tag following the content of the figure, before the FIG end tag.

## Nested Tags

You can code the following tags within a FIGCAP definition:

Tag	Name	Usage	Page	Required
HP	Highlighted phrase	Multiple	348	No
PS	Point-and-Shoot	Multiple	438	No
RP	Reference phrase	Multiple	454	No

## Example

The following help panel markup contains a figure definition with an enclosed figure caption. Figure 121 shows the formatted result.

```
<!DOCTYPE DM SYSTEM>

<HELP NAME=figcap DEPTH=20>ShellBrowse Help
<AREA>
<INFO>
  <FIG>

    We're your local library...

    CHECK US OUT!

  <FIGCAP>Our Motto
  </FIG>
</INFO>
</AREA>
</HELP>
```





Figure 121. Figure Caption

## GA (Graphic Area)

The GA tag allows the creation of graphic areas on ISPF panels.

```
—<GA NAME=graphic-area-name
  EXTEND= [ OFF ]
           [ ON ]
           [ FORCE ]
  DEPTH= [ n ]
         [ * ]
```

**DIV Options:****NAME=graphic-area-name**

This attribute defines the name of the graphic area. This name is the dialog variable specified by the application that provides the data for the graphic area.

The NAME attribute must follow the standard naming convention described in “Rules for Variable Names” on page 205.

**EXTEND=OFF | ON | FORCE**

This attribute defines the run-time display size of the graphic area. If EXTEND=ON is specified, the graphic area definition is expanded to the size of the logical screen. If you intend to display the panel in a pop-up window, use EXTEND=OFF (which is the default).

If EXTEND=FORCE is specified within a horizontal area or region, the EXTEND(ON) keyword is added to the graphic area attribute statement in the )ATTR panel section. The conversion utility issues a message to advise of a potential display error if other panel fields are formatted on or after the last defined line of the graphic area.

**DEPTH=n | \***

This attribute specifies the number of lines reserved for the graphic area definition. The DEPTH attribute value reserves space within the panel )BODY section. The minimum depth is one line. will reserve the remaining available panel depth for the graphic area.

**WIDTH=n**

This attribute specifies the number of columns reserved for the graphic area definition. The minimum width is the number of positions in the graphic area name plus 4 and the maximum is 2 positions less than the panel width. The conversion utility places attribute bytes on both sides of the graphic area.

**DIV=NONE | BLANK | SOLID | DASH | TEXT**

This attribute specifies the type of divider line to be placed before and/or after the graphic area. If this attribute is not specified or has the value NONE, no divider line is generated. The value BLANK produces a blank line. You must specify SOLID, DASH, or TEXT to produce a visible divider line. When the GRAPHIC invocation option is specified, SOLID produces a solid line for host display and DASH produces a dashed line. When NOGRAPHIC is specified or the panel is displayed in GUI mode, both SOLID and DASH produce a dashed line. A visible divider line formats with a non-displayable attribute byte on each end of the line.

**FORMAT=START | CENTER | END**

This attribute specifies the position of the *divider-text* within the divider line. You must specify both the FORMAT attribute and the TEXT attribute to create a divider line containing text.

**TEXT=divider-text**

This attribute specifies the text to be placed on the divider line. You must specify both the FORMAT attribute and the TEXT attribute to create a divider line containing text.

**LVLIN=variable-name**

This attribute allows you to specify the name of a variable which contains the result of the ISPF function LVLIN.

The LVLIN attribute must follow the standard naming convention described in “Rules for Variable Names” on page 205.

## Description

The GA tag defines a graphic area in the panel )BODY section.

If you specify the CMDAREA tag within your DTL source file, it must appear before the GA tag when DEPTH=\* is specified. The GA tag DEPTH may have to be adjusted to allow for additional lines which result from tags present within the panel definition following the end GA tag.

Refer to the *ISPF User's Guide* for a discussion of the graphic area in ISPF panels.

## Conditions

- You must code the GA tag within a PANEL, AREA, or REGION tag. If found anywhere else, an error is logged and the output panel is not saved.
- If NAME is not valid or not specified, an error is logged and the output panel is not saved.
- You can use the EXTEND=ON attribute only once within a panel. If EXTEND is already active, from another GA tag, or from an AREA, DA, SELFLD, or REGION tag, a warning message is logged and the EXTEND attribute is ignored.
- You can code only one GA tag within a PANEL definition.
- You cannot code the GA tag within a scrollable area.

## Nested Tags

None.

## Example

```

<!DOCTYPE DM SYSTEM(
  <!entity sampvar1 system>
  <!entity sampabc system>)>
&sampvar1;


<PANEL NAME=ga KEYLIST=keyl xmp>Library Card Registration
<AB>
&sampabc;
</AB>
<TOPINST> Type in patron's name and card number (if applicable)
<AREA>
  <DTACOL PMTWIDTH=12 ENTWIDTH=25 DESWIDTH=25 SELWIDTH=25>
  <DTAFLD DATAVAR=curdate USAGE=out ENTWIDTH=8>Date
  <DTAFLD DATAVAR=cardno ENTWIDTH=7>Card No.
  <DTAFLDD>(A 7-digit number)
  <DTAFLD DATAVAR=name>Name
  <DTAFLDD>(Last, First, M.I.)
  <DTAFLD DATAVAR=address>Address
</DTACOL>
<DIVIDER>
  <GA NAME=garea DIV=solid DEPTH=6 WIDTH=40>
  </GA>
</AREA>
<CMDAREA>Enter a command
</PANEL>

```

---

## GENERATE (Generate)

The GENERATE tag provides direct formatting for )BODY and )AREA panel sections.



### SUBSTITUTE=NO | YES

The SUBSTITUTE attribute specifies whether variable substitution is attempted within the pre-formatted panel text.

## Description

The GENERATE tag is used to add pre-formatted displayable panel contents into the )BODY or )AREA panel sections. These contents can contain any valid displayable information. It is the panel developer's responsibility to provide valid displayable data.

The pre-formatted information is coded within a nested SOURCE tag. The SOURCE tag TYPE attribute is automatically determined based on the position of the GENERATE tag within the DTL source file. When panel attributes are required, the ATTR tag can be used to define the necessary )ATTR section entries.

## Conditions

- The GENERATE tag requires an end tag.
- You must code the GENERATE tag within an AREA, HELP or PANEL tag definition.

## Nested Tags

You can code the following tags within a GENERATE definition:

Tag	Name	Usage	Page	Required
ATTR	Attribute	Multiple	228	No
COMMENT	Comment	Multiple	275	No
SOURCE	Source	Multiple	482	No

## Example

The following markup shows contains a GENERATE tag with nested ATTR and SOURCE tags. Figure 122 on page 332 shows the generated panel file.

```
<!DOCTYPE DM SYSTEM>
<PANEL NAME=* KEYLIST=keyl xmp applid=isr window=no>
    Generate Tag Example

<CMDAREA>
<pnlinst compact>
    Sample panel source to illustrate the GENERATE tag.

<divider type=solid gap=no>

<generate>
    <attr attrchar=! type=FP>
    <attr attrchar=_ type=NEF>
    <attr attrchar=+ type=NT>

<source>
! Project ==>_PROJECT !
! Group  ==>_GROUP1 !==>_GROUP2 !==>_GROUP3 !==>_GROUP4 +
! Type   ==>_TYPE   !
! Member ==>_MEMBER !

! DS Name ==>_OTHERDSN +
! Volume  ==>_VOLUME+
</source>
</generate>

</panel >
```

```

)PANEL KEYLIST(KEYLXMP,ISR)
)ATTR DEFAULT('') FORMAT(MIX)
05 TYPE(PT)
06 TYPE(PIN)
09 TYPE(FP)
0A TYPE(NT)
13 TYPE(NEF)
22 TYPE(WASL) SKIP(ON) GE(ON)
! TYPE(FP)
_ TYPE(NEF)
+ TYPE(NT)
)BODY CMD(ZCMD)

```

Generate Tag Example

Command ==> Z

Sample panel source to illustrate the GENERATE tag.

```


-----
! Project ==>_PROJECT !
! Group  ==>_GROUP1 !==>_GROUP2 !==>_GROUP3 !==>_GROUP4 +
! Type   ==>_TYPE   !
! Member ==>_MEMBER !
! DS Name ==>_OTHERDSN +
! Volume ==>_VOLUME+
)INIT
.ZVARS = '(ZCMD)'
&ZCMD = ' '
)PROC
)END

```

Figure 122. Generated Panel

## GRPHDR (Group Header)

The GRPHDR tag allows the creation of group headers on ISPF panels.



### FORMAT=START | CENTER | END | NONE

This attribute specifies the type of group header formatting.

When FORMAT=NONE, the lines of *group-heading-text* are placed in the panel )BODY section without alteration. The processing is similar to the LINES tag.

When the values START, CENTER, or END are specified, the data is processed in a manner similar to the P tag. The *group-heading-text* is read and flowed to fit within the width limit specified by FMTWIDTH. Multiple lines may be added to the panel, depending on the length of the *group-heading-text*.

**WIDTH=n**

This attribute specifies the number of columns reserved for the group heading. The minimum width for a group heading is 4. The maximum value is the remaining panel width. If WIDTH is not specified, the default value is set to the remaining panel width. The conversion utility uses 2 positions from the specified or default WIDTH for attributes.

**FMTWIDTH=n**

This attribute specifies the number of columns to use for formatting the *group-heading-text*. The minimum formatting width is 2. The maximum value is the value specified or defaulted for WIDTH. If FMTWIDTH is not specified, the default value is set to the value of WIDTH.

**INDENT=n**

This attribute specifies that the group heading is to be indented from the current position.

**HEADLINE=NO | YES**

This attribute specifies whether dashes are added to span the width of the group heading not occupied by text. This allows a visual indication of the width of the group heading.

**DIV=NONE | BLANK | SOLID | DASH**

This attribute specifies the type of divider line to be placed before and after the group heading. If this attribute is not specified or has the value NONE, no divider line is generated. The value BLANK produces a blank line. You must specify SOLID or DASH to produce a visible divider line. When the GRAPHIC invocation option is specified, SOLID produces a solid line for host display and DASH produces a dashed line. When NOGRAPHIC is specified or the panel is displayed in GUI mode, both SOLID and DASH produce a dashed line.

**DIVLOC=AFTER | BEFORE | BOTH**

This attribute specifies whether divider line is to be added after the group heading, before the group heading or both before and after the group heading.

**COMPACT**

This attribute causes the group heading to format without a blank before the heading.

**STRIP**

This attribute causes leading and trailing blanks to be removed from the heading.

**group-heading-text**

This is the text of the group header. If no *group-heading-text* is provided, a blank line is added to the panel unless the COMPACT attribute is also specified.

## Description

The GRPHDR tag defines a group heading in the panel )BODY section.

The FMTWIDTH and HEADLINE attributes are not valid in combination with FORMAT=NONE. The DIVLOC attribute is not valid in combination with DIV=NONE.

You use the FMTWIDTH attribute to control the width of flowed text within the number of columns specified by WIDTH. The FORMAT attribute controls the

## GRPHDR

placement of the resulting lines within the heading WIDTH. The FMTWIDTH attribute has no effect if the length of the *group-heading-text* is less than the value specified.

Because the group heading is formatted as text, a blank line is placed at the beginning of each group heading unless the COMPACT attribute has been specified. However, when the group heading is the first item in a scrollable region the blank line is not generated.

## Conditions

- You must code the GRPHDR tag within a PANEL, AREA, DTACOL, or REGION tag. If found anywhere else, an error is logged and the output panel is not saved.

## Nested Tags

You can code the following tags within a GRPHDR tag:

Tag	Name	Usage	Page	Required
HP	Highlighted phrase	Multiple	348	No
PS	Point-and-Shoot	Multiple	438	No
RP	Reference phrase	Multiple	454	No

## Example

```
<!DOCTYPE DM SYSTEM>
  <!entity sampvar1 system>
  <!entity sampabc system>>
&sampvar1;

<PANEL NAME=grphdr KEYLIST=keyl xmp>Library Card Registration
<AB>
&sampabc;
</AB>
<TOPINST> Type in patron's name and card number (if applicable)
<AREA>
  <GRPHDR FORMAT=center WIDTH=50 FMTWIDTH=30 DIV=solid COMPACT>
    Data Field Group Heading
  </GRPHDR>
  <DTACOL PMTWIDTH=12 ENTWIDTH=25 DESWIDTH=25 SELWIDTH=25>
    <DTAFLD DATAVAR=curdate USAGE=out ENTWIDTH=8>Date
    <DTAFLD DATAVAR=cardno ENTWIDTH=7>Card No.
      <DTAFLDD>(A 7-digit number)
    <DTAFLD DATAVAR=name>Name
      <DTAFLDD>(Last, First, M.I.)
    <DTAFLD DATAVAR=address>Address
  </DTACOL>
</AREA>
<CMDAREA>Enter a command
</PANEL>
```

```

File Search Help
-----
Library Card Registration

Type in patron's name and card number (if applicable)

Data Field Group Heading
-----
Date . . . : _____
Card No. . . : _____ (A 7-digit number)
Name . . . : _____ (Last, First, M.I.)
Address . . : _____

Enter a command ==>> _____
F1=Help      F3=Exit      F5=Display      F6=Keyshelp      F10=Actions
F12=Cancel

```

Figure 123. Group Heading

## HELP (Help Panel)

The HELP tag defines a help panel.

```


--<HELP--NAME=hel p-panel -name
    |HELP=|hhel p-panel -name
    |%varname
-----
|HELPDEF=hel pdef-id|
|WIDTH=|50|
|         |n|
|         |FIT|
|DEPTH=|10|
|         |n|
|         |FIT|
|CCSID=n|
-----
|TUTOR|
|KEYLIST=key-list-name| KEYLIST Options |
|EXPAND=xy|
-----
|WINTITLE=window-title|
|APPTITLE=application-title|
-----
|MERGESAREA=|NO|
|             |YES|
|MSGLINE=|YES|
|         |NO|
-----
|IMAPNAME=|image-name|
|          |%varname|
|IMAP Group|
|ZUP=zup-id|
-----
|ZCONT=zcont-id|
|>hel p-panel -title</HELP>

```

**KEYLIST Options:**



**IMAP Group:**



**NAME=help-panel-name**

This attribute specifies the name of the help panel. The *help-panel-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

In addition, the *help-panel-name* is limited to 7 characters when the DTL source you are converting causes the conversion utility to build multiple panels. If you have specified an 8-position help name and multiple panels are required, the help name will be truncated to 7 positions. If you are not creating a scrollable help panel, this allows additional panels to be built if the help text exceeds the limits of the original help panel. Up to 36 additional help panels will be built to contain additional help text.

If the number of generated panels required exceeds 37, a warning message is issued and all help text after the 37th panel is discarded. The additional panel names are generated from the original *help-panel-name* by the following rules:

- The character ‘X’ will be used to pad the *help-panel-name* to 8 characters in length if the original *help-panel-name* is less than 8 characters.
- The eighth character of the generated panel name will be incremented from 0–9 and A–Z depending on the number of panels required to be generated. For example, if the original *help-panel-name* is ‘HELP1’ and the help text extends beyond the original panel, the second generated panel name would be ‘HELP1XX0’, and the third would be ‘HELP1XX1’.

If you specify NAME=\*, the *help-panel-name* is set to the input DTL source member name. If multiple dialog element definitions have been combined within a single source file, then this notation should be used for only one dialog element definition within the file. See “Dialog Elements” on page 5 for a description of dialog element types created by the conversion utility.

The *help-panel-name* is used to build the help panel output file name in which the conversion utility stores the converted help panel. The default name is “userid.PANELS(*help-panel-name*)”.

The output panel file name can be specified on the invocation panel for the conversion utility. You can specify the panel library of your choice. If the SCRIPT option was specified, the *help-panel-name* is also used to build the file name in which the conversion utility stores the image of the help panel. The default name is “userid.SCRIPT( *help-panel-name*)”.

See Chapter 10, “Using the Conversion Utility,” on page 171 for complete information on invocation syntax.

The ISPF tutorial facility displays help panels. The user can scroll forward by pressing Enter or the RIGHT (F11) key, or scroll backward by pressing the LEFT (F10) key. The scrolling indicators “More: +”, “More: -”, and “More: - +” are added to the displayed panel to indicate more help is available.

#### **HELP=hhelp-panel-name | %varname**

This attribute specifies the name of a defined help for help panel. It identifies the help text that is associated with help processing.

The *hhelp-panel-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

Specification of the HELP attribute will cause ISPDTLC to generate “.HHELP=*hhelp-panel-name*” (or “.HHELP=&varname”) in the )INIT section during help panel generation.

If no value is provided for the HELP attribute, the conversion utility will add the default “.HHELP = ISP00006” to the generated panel.

ISPF displays this panel when the application user requests help and the cursor is not on a panel field that is defined as a reference phrase.

#### **HELPDEF=helpdef-id**

This attribute specifies a defined help default. The *helpdef-id* value is the identifier specified on the HELPDEF tag. You can override any of the defaults from this HELPDEF tag by specifying that attribute on the HELP tag. See the description of the HELPDEF tag for information on defining help defaults.

#### **WIDTH=50 | n | FIT**

This attribute specifies the width of the help panel. The default width is 50. When you specify this attribute, it should be greater than or equal to the minimum width of 16 characters. The maximum is 156. Because there are set margins of 1 character on each side of the panel text to allow for 3270 attribute bytes, the effective width for text for a help panel defined as WIDTH=50 is 48 characters.

If you have specified WIDTH=FIT, The conversion utility will format the panel using the maximum available width. When formatting is completed the WIDTH value will be reset to the minimum width used or to 16 if the formatted panel is less than 16 characters wide.

If the specified WIDTH exceeds the maximum minus 4 allowed by the display device, ISPF issues an error message at run time.

#### **DEPTH=10 | n | FIT**

This attribute specifies the depth of the HELP panel. The maximum depth is 60 and the minimum depth is 6. When the panel body does not end with a scrollable area, four lines at the bottom of each help panel are reserved for the function key area. Two lines are reserved at the top of the help panel for the *help-panel-title* and a separator line. You must include provisions for these 6 lines in the depth you specify.

The default help panel depth of 10 is used when the DEPTH attribute provided cannot be used or the DEPTH attribute is not specified.

If you have specified DEPTH=FIT, The conversion utility will format the panel using a depth of 22. When formatting is completed the DEPTH value will be reset to the minimum depth used or to 6 if the formatted panel contains less than 6 lines.

If the specified DEPTH exceeds the maximum, minus 2, allowed by the display device, ISPF issues an error message at run time.

### **CCSID=n**

CCSID specifies the coded-character-set identifier as defined by the Character Data Representation Architecture. CCSID should be entered as a five-position numeric value. For more information on using the CCSID attribute, refer to the *ISPF Dialog Developer's Guide and Reference*.

### **TUTOR**

This attribute specifies that the panel title be formatted with the word *Tutorial* (or its translated equivalent) on each end of the title line, similar to ISPF tutorial panels.

### **KEYLIST=key-list-name**

KEYLIST is an ISPF extension to the Dialog Tag Language. This attribute specifies the name of the key mapping list associated with the help panel. If you do not specify a *key-list-name* in a HELP definition, the ISPF-provided key list (ISPHELP) will be used. For information about defining key mapping list, see "KEYL (Key List)" on page 355. For information about the ISPF-provided key list, refer to the *ISPF User's Guide*.

### **KEYLTYPE= PRIVATE | SHARED**

This attribute is used to add the SHARED keyword to the KEYLIST parameter of the )PANEL statement. For information about the )PANEL statement, refer to the *ISPF Dialog Developer's Guide and Reference*. The KEYLTYPE attribute is ignored if you have not provided the KEYLIST attribute as part of the HELP tag definition or as part of an associated HELPDEF tag definition.

### **APPLID=application-id**

This attribute is used to add the application ID to the )PANEL statement. The *application-id* overrides the KEYLAPPL invocation option value. The APPLID attribute is ignored if you have not provided the KEYLIST attribute as part of the HELP tag definition or as part of an associated HELPDEF tag definition.

### **EXPAND=xy**

This attribute adds the EXPAND(xy) attribute to the )BODY section of the panel. If only one character is present, the second character will be set to the same value. If the EXPAND attribute is present with no value specified, the conversion utility will use a character from the range of low-order hex values available for panel attributes. This removes an available character from possible use as a panel attribute and may cause panel formatting errors.

### **WINTITLE=window-title**

This attribute is used to add a title on the pop-up window border. The attribute value is placed in the ISPF ZWINTTL variable. The maximum length of the *window-title* text is the panel width minus 1.

### **APTITLE=application-title**

This attribute is used to add a title on the GUI window border. The attribute value is placed in the ISPF ZAPTTL variable. The maximum length of the *application-title* text is the panel width minus 1.

### **MERGESAREA= NO | YES**

This attribute controls an additional formatting step for panels with a single scrollable area. If the entire contents of the scrollable area will fit within a standard 24-line panel (allowing 4 lines for the function keys display), the scrollable area content is moved into the panel body.

**MSGLINE=YES | NO**

This attribute controls the provision for a long message line in the generated panel. When MSGLINE=NO, the blank line for the long message is not added to the panel )BODY section. It is the panel designer's responsibility to ensure that critical panel areas are positioned so that the long message will not inhibit use of the resulting panel.

**IMAPNAME=image-name | %varname**

This attribute specifies the name of an image to be placed on the panel when it is displayed in GUI mode. The *image-name* is not used when the panel is displayed in host mode.

The *image-name* must follow the standard naming convention described in "Rules for Variable Names" on page 205.

**IMAPROW=n | %varname**

This attribute specifies the row number for positioning the image. Image position uses an origin based on 0. Therefore, the minimum row value is 0 and the maximum is 59, relating to the above description for the DEPTH attribute. If a variable name is used, the application must set the variable to a valid value before the panel is displayed. The value specified should be within the actual panel depth for the image to be visible when the panel is displayed.

**IMAPCOL=n | %varname**

This attribute specifies the column number for positioning the image. Image position uses an origin based on 0. Therefore, the minimum column value is 0 and the maximum is 155, relating to the above description for the WIDTH attribute. If a variable name is used, the application must set the variable to a valid value before the panel is displayed. The value specified should be within the actual panel width for the image to be visible when the panel is displayed.

**ZUP=zup-id**

This attribute provides the name of the Tutorial panel to be assigned to the ZUP variable. It is valid only when the TUTOR attribute has also been specified.

**ZCONT=zcont-id**

This attribute provides the name of the Tutorial panel to be assigned to the ZCONT variable. It is valid only when the TUTOR attribute has also been specified.

**help-panel-title**

This specifies the title that appears on the help panel.

The *help-panel-title* is centered within the specified help panel width in accordance to CUA rules. If the title text is wider than the WIDTH specified, the title will be truncated with an ellipses (...) appended. Two lines are reserved for the title and a separator which can include the scrolling indicator if there are more panels.

## Description

The HELP tag defines a help panel. A help panel can contain multiple information areas, which you use the INFO tag to define (see "INFO (Information Region)" on page 350).

ISPF always displays help panels defined with DTL in a pop-up window with a border. Therefore, the maximum value you can specify for the WIDTH attribute is

## HELP

4 less than the maximum allowed by the display device. This allows for the left and right borders and their 3270 attribute characters. The maximum value for the DEPTH attribute is 2 less than the maximum allowed by the display device to allow for the top and bottom borders. Borders are added to the formatted help panel at run time.

If you are not creating a scrollable help panel and the text to be included in the )BODY section of the ISPF panel exceeds the specified DEPTH value, up to 36 additional panels are generated to contain the additional text. If the help text extends beyond the original help panel and 36 additional help panels, an error message will be issued and the excess text will be truncated. If the error occurs, and the DEPTH and WIDTH attributes are not set to their maximum values, the values should be increased or the amount of text to be included in the help panel should be reduced.

For nonscrollable HELP panels or for scrollable HELP panels which end with a nonscrollable section, a function key area of four lines is reserved at the bottom of the panel. The four lines are taken from the value specified for the DEPTH attribute.

If you do not specify the KEYLIST attribute, ISPF automatically associates the ISPF-provided key list "ISPHELP" with all DTL help panels.

The following table shows the "ISPHELP" key list and assignments:

*Table 4. ISPHELP keylist and assignments*

Key	Command	Key Label	Format
F1	HELP	Help	Short
F2	SPLIT	Split	Long
F3	EXIT	Exit	Short
F4	RESIZE	Resize	Long
F5	EXHELP	Exhelp	Short
F6	KEYSHELP	Keyshelp	Short
F7	UP	PrvTopic	Short
F8	DOWN	NxtTopic	Short
F9	SWAP	Swap	Long
F10	LEFT	PrvPage	Short
F11	RIGHT	NxtPage	Short
F12	CANCEL	Cancel	Short

All ISPHELP function keys are active when the cursor is in the help panel. Display of keys in the function key area is controlled by the user through the ISPF FKA command.

Because help panels are displayed by the ISPF tutorial processor, the commands assigned to the keys are those supported by the ISPF tutorial. For more information on the ISPF tutorial, refer to the *ISPF User's Guide*.

Since ISPD TLC generated panels are not normally used in a full Tutorial, the default ISPHELP keylist may result in confusion in the use of the F7 and F8 keys for scrolling. An alternate approach is the ISPHLP2 keylist as defined below. To use

this keylist, add the KEYLIST=ISPHLP2 attribute to your help panel definition.

Table 5. ISPHLP2 keylist and assignments

Key	Command	Key Label	Format
F1	HELP	Help	Short
F2	SPLIT	Split	Long
F3	EXIT	Exit	Short
F4	RESIZE	Resize	Long
F5	EXHELP	Exhelp	Short
F6	KEYSHELP	Keyshelp	Short
F7	LEFT	PrvPage	Short
F8	RIGHT	NxtPage	Short
F9	SWAP	Swap	Long
F10	LEFT	PrvPage	Long
F11	RIGHT	NxtPage	Long
F12	CANCEL	Cancel	Short

## Conditions

- The HELP tag requires an end tag.
- You cannot code the HELP tag within any other tag definition.
- If the help panel does not have a panel body, the conversion utility issues an error message. The help panel must contain at least one INFO (information region) definition to qualify as a panel body. See “INFO (Information Region)” on page 350 for a complete description of this tag.
- When a “%varname” notation is found on any of the attributes that allow a variable name, the “%varname” entry must follow the standard naming convention described in “Rules for “%variable” Names” on page 205.

## Nested Tags

You can code the following tags within a HELP definition:

Tag	Name	Usage	Page	Required
AREA	Area	Multiple	217	No
COMMENT	Comment	Multiple	275	No
DIVIDER	Divider	Multiple	289	No
GENERATE	Generate	Multiple	330	No
HP	Highlighted phrase	Multiple	348	Yes
INFO	Information region	Multiple	350	Yes
REGION	Region	Multiple	446	No
SOURCE	Source	Multiple	482	No
TEXTLINE	Text Line	Single	485	No

## Example

The following help panel markup contains an information region that contains a paragraph, a definition list, and two unordered lists nested within the definition

## HELP

list. Because all of the data does not fit in one help panel, the conversion utility created three panels HELP, HELPXXX0, and HELPXXX1. The panels are scrollable. Figures 124, 125, and 126 show the formatted results with the function key area displayed in its short form.

```
<!DOCTYPE DM SYSTEM>
```

```
<HELP NAME=help WIDTH=46 DEPTH=16>Shel fBrowse for Kids
<AREA>
  <INFO>
    <P>Shel fBrowse can help you
    find any kind of book you are looking for.
    The two main categories for books are:
    <DL TSIZE=12>
      <DTHD>Book
      <DDHD>Description
      <DT>Fiction
      <DD>Fiction books are stories
      that never really happened.
      The writer made them up.
      For example:
      <UL>
        <LI>Fai ry Tales
        <LI>Mysteri es
        <LI>Sci ence fi cti on stories
      </UL>
      <DT>Nonfi cti on
      <DD>Nonfi cti on books are about
      thi ngs that really exist.
      For example:
      <UL>
        <LI>Hi story books
        <LI>Refe rence books
        <LI>Ho w to books
      </UL>
    </DL>
  </INFO>
</AREA>
</HELP>
```




Figure 124. Help Panel (Example 1 of 3)




Figure 125. Help Panel (Example 2 of 3)




Figure 126. Help Panel (Example 3 of 3)


## HELPDEF (Help default)

The HELPDEF tag defines default values for help panels.

```

--<HELPDEF--ID=hel pdef- i d
    HELP=hhel p- panel -name
         %varname
    WIDTH= n
         FIT
    DEPTH= n
         FIT
    CCSID= n
    KEYLIST=key- l ist- name
    KEYLIST Options
    EXPAND=xy
    WINTITLE=wi ndow- ti tle
    APPTITLE=appl i cati on- ti tle
  
```

## HELPDEF



### KEYLIST Options:



### ID=helpdef-id

This is the ID of the help panel default definition. The ID is used as the identifier of this set of default definitions on the HELP tag.

The *helpdef-id* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

### HELP=hhelp-panel-name | %varname

This attribute specifies the default name of a defined help for help panel. It identifies the help text that is associated with help processing.

The *hhelp-panel-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

### WIDTH=n | FIT

This attribute specifies a default width value for a help panel that refers to this help default.

### DEPTH=n | FIT

This attribute specifies a default depth value for a help panel that refers to this help default.

### CCSID=n

CCSID specifies the coded-character-set identifier as defined by the Character Data Representation Architecture. CCSID should be entered as a five-position numeric value. For more information on using the CCSID attribute, refer to the *ISPF Dialog Developer's Guide and Reference*.

### KEYLIST=key-list-name

This attribute specifies the name of the key mapping list associated with the help panel. If you do not specify a *key-list-name* in a HELP definition, the ISPF-provided key list (ISPHelp) will be used. For information about defining key mapping list, see “KEYL (Key List)” on page 355. For information on the ISPF-provided key list, refer to the *ISPF User's Guide*.

### KEYLTYPE=PRIVATE | SHARED

This attribute is used to add the SHARED keyword to the KEYLIST parameter of the )PANEL statement. For information about the )PANEL statement, refer to the *ISPF Dialog Developer's Guide and Reference*.

### APPLID=application-id

This attribute is used to add the application ID to the )PANEL statement. The *application-id* overrides the KEYLAPPL invocation option value.

### EXPAND=xy

This attribute adds the EXPAND(xy) attribute to the )BODY section of the

panel. If only one character is provided, the second character is set to the same value. If the EXPAND attribute is present with no value specified, the conversion utility will use a character from the range of low-order hex values available for panel attributes. This removes an available character from possible use as a panel attribute and may cause panel formatting errors.

**WINTITLE=window-title**

This attribute is used to add a title on the pop-up window border. The attribute value is placed in the ISPF ZWINTTL variable. The maximum length of the *window-title* is the panel width minus 1.

**APTITLE=application-title**

This attribute is used to add a title on the GUI window border. The attribute value is placed in the ISPF ZAPPTTL variable. The maximum length of the *application-title* text is the panel width minus 1.

**MERGESAREA= NO | YES**

This attribute controls an additional formatting step for panels with a single scrollable area. If the entire contents of the scrollable area will fit within a standard 24-line panel (allowing 4 lines for the function keys display), the scrollable area content is moved into the panel body.

**IMAPNAME=image-name | %varname**

This attribute specifies the name of an image to be placed on the panel when it is displayed in GUI mode. The *image-name* is not used when the panel is displayed in host mode.

The *image-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

**IMAPROW=n | %varname**

This attribute specifies the row number for positioning the image. Image position uses an origin based on 0. Therefore, the minimum row value is 0 and the maximum is 59, relating to the description for the DEPTH attribute on the HELP tag. If a variable name is used, the application must set the variable to a valid value before the panel is displayed. The value specified should be within the actual panel depth for the image to be visible when the panel is displayed.

**IMAPCOL=n | %varname**

This attribute specifies the column number for positioning the image. Image position uses an origin based on 0. Therefore, the minimum column value is 0 and the maximum is 155, relating to the description for the WIDTH attribute on the HELP tag. If a variable name is used, the application must set the variable to a valid value before the panel is displayed. The value specified should be within the actual panel width for the image to be visible when the panel is displayed.

## Description

The HELPDEF tag defines default values for help panels. When a HELP panel tag refers to a help panel default, the values specified by the associated HELPDEF tag are used for the help panel unless overridden by values specified in the HELP tag definition.

The HELP tag can override any of the HELPDEF values by specifying that value within its own definition. Therefore, it is possible for a HELP tag to select certain default values from the help panel default and override others.

See “HELP (Help Panel)” on page 335 for more information.

## HELPDEF

You can code multiple HELPDEF definitions in a single application. Each help default must have a unique *helpdef-id*.

### Portability Considerations

In ISPF Version 3 Release 1, the Conversion Utility supported the HELPDEF tag. In this release, the HELPDEF tag is supported to ease portability between releases.

## Conditions

- You cannot code the HELPDEF tag within any other tag definition.
- You must code the HELPDEF tag before you code any HELP tag that refers to it.

## Nested Tags

None.

## Example

In the following source file example, the HELPDEF definition defines default DEPTH and WIDTH values. The help panels “help15” and “help16” both reference the help default—“help15” uses both default values and “help16” uses only the default WIDTH value, and overrides the default DEPTH value by specifying its own DEPTH value. The help panel “help17” does not reference the help default, and defines its own DEPTH and WIDTH values.

```
<!DOCTYPE DM SYSTEM>

<HELPDEF ID=helpdef1 DEPTH=10 WIDTH=40>

<HELP NAME=help15 HELPDEF=helpdef1>Help for This
:
:
</HELP>

<HELP NAME=help16 HELPDEF=helpdef1 DEPTH=15>Help for That
:
:
</HELP>

<HELP NAME=help17 DEPTH=15 WIDTH=25>Help for the Other
:
:
</HELP>
```

---

## Hn (Heading)

The heading tags define main topics and subtopics of information within an information region.

```
—<Hn—>
  |   |   |
  | COMPACT | heading-text | </Hn> |
```

### COMPACT

This attribute causes the heading-text to be formatted without creating a blank line before the heading.

### heading-text

This is the text of the heading.

## Description

The heading tags define main topics and subtopics of information within an information region. You can define up to four heading levels. The  $n$  in H $n$  indicates the heading level. The heading levels are formatted as follows:

**H1** Identifies a main topic of information. The text is centered on the panel.

**H2, H3, H4** The text is formatted against the left margin of the panel body.

Headings are formatted with one blank line before them.

## Conditions

- The H $n$  tag must be coded within an INFO definition. See “INFO (Information Region)” on page 350 for a complete description of this tag.

## Nested Tags

You can code the following tags only within an H2, H3, or H4 tag:

Tag	Name	Usage	Page	Required
HP	Highlighted phrase	Multiple	348	No
PS	Point-and-Shoot	Multiple	438	No
RP	Reference phrase	Multiple	454	No

## Example

The following help panel markup contains two levels of headings. Figure 127 on page 348 shows the formatted result.

```
<!DOCTYPE DM SYSTEM>

<HELP NAME=hn DEPTH=22>Department Descriptions Help
<AREA>
<INFO>
  <H1>Departments
  <H2>Entertainment
  <P>Our entertainment department carries the
  finest in home entertainment components.
  <H2>Exotic Pets
  <P>You can order from a wide variety of exotic
  pets and pet supplies in this department.
  <H2>Toys
  <P>Your kids will love our wide selection of
  toys, games, and play equipment.
</INFO>
</AREA>
</HELP>
```





Figure 127. Headings

## HP (Highlighted Phrase)

The HP tag identifies text to be displayed with highlighted emphasis.



**TYPE=** ET | CH | CT | FP | LEF | LI | NT | PT | SAC | TEXT | WASL | WT

This attribute defines the attribute type to be applied to the *phrase-to-be-highlighted*. Using a CUA attribute causes the text to appear in the associated color.

When TYPE=TEXT, a non-CUA attribute is generated and you can specify the color, intensity, and highlighting with the COLOR, INTENS, and HILITE attributes. These attributes are not valid for CUA types.

**COLOR= WHITE | RED | BLUE | GREEN | PINK | YELLOW | TURQ | %varname**

This attribute specifies the color of the field. You can define this attribute as a variable name preceded by a percent (%) sign.

**INTENS= HIGH | LOW | NON | %varname**

This attribute defines the intensity of a field. You can define this attribute as a variable name preceded by a percent (%) sign.

**HILITE= USCORE | BLINK | REVERSE | %varname**

This attribute specifies the extended highlighting attribute of a field. You can define this attribute as a variable name preceded by a percent (%) sign.

**INTENSE=varname**

This attribute supplies a variable name that must contain a valid value for the INTENS keyword. The entire phrase is controlled by this value. For example, if the variable contains the value NON, the phrase will not be visible.

**phrase-to-be-highlighted**

This text displays with highlighted emphasis.

## Description

The HP identifies text to be displayed with highlighted emphasis by ISPF. The HP end tag restores normal text.

## Conditions

- You can code the HP tag wherever the RP tag is valid.
- You can code the HP tag within the text following the CHDIV, CMDAREA, HELP, and PANEL tags.
- The HP tag requires an end tag.

## Nested Tags

None.

## Example

The following markup shows the formatted result in Figure 128 on page 350.

```
<!DOCTYPE DM SYSTEM(
  <!entity sampvar1 system>
  <!entity sampabc system>)>
&sampvar1;

<PANEL NAME=hp KEYLIST=keyl xmp>Library Card Registration
<AB>
&sampabc;
</AB>
<TOPINST> Type in <HP>patron's name</HP> and <HP>card number</HP>
          (if applicable)
<TOPINST> Then select an action bar choice.
<AREA>
  <DTACOL PMTWIDTH=12 ENTWIDTH=25 DESWIDTH=25 SELWIDTH=25>
  <DTAFLD DATAVAR=curdate USAGE=out ENTWIDTH=8>Date
  <DTAFLD DATAVAR=cardno ENTWIDTH=7>Card No.
    <DTAFLDD>(A 7-digit number)
  <DTAFLD DATAVAR=name>Name
    <DTAFLDD>(Last, First, M.I.)
```

```

    <DTAFLD DATAVAR=address>Address
    </DTACOL>
<DIVIDER>
<REGION DIR=horiz>
<SELFLD NAME=cardsel PMTWIDTH=30 SELWIDTH=38>Choose
one of the following
    <CHOICE CHECKVAR=card MATCH=new>New
    <CHOICE CHECKVAR=card MATCH=renew>Renewal
    <CHOICE CHECKVAR=card MATCH=replace>Replacement
</SELFLD>
<SELFLD TYPE=multi PMTWIDTH=30 SELWIDTH=25>Check valid branches
    <CHOICE NAME=north HELP=nthlp CHECKVAR=nth>North Branch
    <CHOICE NAME=south HELP=sthhlp CHECKVAR=sth>South Branch
    <CHOICE NAME=east HELP=esthlp CHECKVAR=est>East Branch
    <CHOICE NAME=west HELP=wsthlp CHECKVAR=wst>West Branch
</SELFLD>
</REGION>
</AREA>
<CMDAREA>Enter a command
</PANEL>

```




Figure 128. HP (Highlighted Phrase)

## INFO (Information Region)

The INFO tag defines an information region for a panel.



### WIDTH=format-width | \*

This attribute determines the width the conversion utility uses to format the text in the ISPF )BODY section of the panel. If WIDTH is not the value is set to the remaining available panel (or region) width. If specified, the WIDTH value cannot be larger than the defined width of the panel (or region) minus 2 characters. For example, a WIDTH value of 58 is acceptable for an information region within a panel with a defined width of 60.

**Note:** You should code the WIDTH attribute if the information region is part of an application panel definition that uses horizontal region capability. The actual width used in a horizontal region is 2 characters longer than the WIDTH attribute value to provide for attribute bytes that delimit the region.

#### INDENT=n

This attribute defines the number of columns to indent the current information region from the current left boundary.

## Description

The INFO tag defines an information region for a panel. The information region is used to display text such as paragraphs, lists, notes, examples, and figures. A typical use of the INFO tag is for the definition of text within help panels.

## Conditions

- The INFO tag requires an end tag.
- You must code the INFO tag within an AREA, HELP, or PANEL definition. See “AREA (Area)” on page 217, “HELP (Help Panel)” on page 335, and “PANEL (Panel)” on page 413 for descriptions of these tags.

## Nested Tags

You can code the following tags within an INFO definition:

Tag	Name	Usage	Page	Required
DIVIDER	Divider	Multiple	289	No
DL	Definition list	Multiple	292	No
FIG	Figure	Multiple	324	No
Hn	Heading	Multiple	346	No
LINES	Lines	Multiple	360	No
NOTE	Note	Multiple	396	No
NOTEL	Note List	Multiple	399	No
NT	Note	Multiple	402	No
OL	Ordered list	Multiple	404	No
P	Paragraph	Multiple	406	No
PARML	Parameter list	Multiple	424	No
SL	Simple list	Multiple	480	No
SOURCE	Source	Multiple	482	No
UL	Unordered list	Multiple	491	No
XMP	Example	Multiple	508	No

## Example

The following help panel markup contains an information region. The text of the information region is defined using two P (paragraph) tags and an unordered list (UL) tag with three LI (list item) tags. Figure 129 on page 352 shows the formatted result.

## INFO

```
<!DOCTYPE DM SYSTEM>

<HELP NAME=info WIDTH=60 DEPTH=22>Shel fBrowse Hel p
<AREA>
<INFO WIDTH=42>
  <P>When Shel fBrowse finds your book, it displays this
  information:
  <UL>
    <LI>Reference information about the book.
    <LI>The location of the book.
    <LI>If the book is in stock.
  </UL>
  <P>If the book is not in stock, see the librarian.
</INFO>
</AREA>
</HELP>
```





Figure 129. Information Region

## KEYI (Key Item)

The KEYI tag defines a key assignment within a key mapping list.



### KEY=virtual-key

This attribute specifies the name of the key to assign to the command. The conversion utility supports F1–F24 only.

**CMD=internal-command-name**

This attribute specifies the command that ISPF runs when the user presses the key.

The *internal-command-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

As an extension to the Dialog Tag Language, the conversion utility supports special ISPF command syntax for *internal-command-name*. In this case, the *internal-command-name* must have the following characteristics:

- 2–9 single-byte characters in length
- The first character must be a '>', ':', or '%'.

To code the > character you must use the *&gt;sym* predefined entity. See “Predefined Entities” on page 25 for more information.

- The second character must be A–Z, a–z, @, #, or \$.
- Remaining characters, if any, must be A–Z, a–z, @, #, \$, or 0–9.

Lowercase characters are translated to their uppercase equivalents by default.

**CASE=UPPER | MIXED**

This attribute specifies that the *internal-command-name* will be converted to uppercase characters or stored as entered in the tag definition.

**FKA=NO | YES | LONG | SHORT**

This attribute specifies whether the key assignment is to appear in the function key area of an application panel. The default value NO indicates that the key is not to appear. You must specify FKA=YES, FKA=LONG, or FKA=SHORT if you want the key to be displayed in the function key area.

When FKA=NO is specified, the key is active even if it is not displayed.

**Compatibility Considerations**

In ISPF Version 3.1, the conversion utility supported the values NO, SHORT, and LONG for the FKA attribute. The FKA attribute values have been changed to YES and NO. FKA=YES is converted to FKA=SHORT. If you want keys to appear only when the user chooses LONG form, you must code FKA=LONG.

For compatibility between releases, the conversion utility allows SHORT or LONG.

**PARM=parm-string**

This attribute allows a parameter to be added to the command specified by the CMD attribute. The combined length of the command and the parameter is limited to 40 bytes. When the combined length exceeds 40 bytes, truncation of the PARM occurs at the end of the last complete word in the *parm-string*, for a *parm-string* containing multiple words. A *parm-string* which is a single word is truncated at position 40.

**FKA-text**

This is the text for the key which is to appear in the function key area of the panels that refer to the key list. This text is appended to the string “Fn=” (with no intervening space) to create the displayed format. You should use initial caps for the *FKA-text* value.

If not specified, the *FKA-text* defaults to the *internal-command-name* specified for the key.

## KEYI

The function key area is formatted at run time based on the panel size. The maximum number of bytes allowed for *FKA-text* is 64. If the text exceeds 64 bytes, it is truncated and a warning message is issued. The conversion utility removes excess blanks from *FKA-text*. The first 8 bytes of the resulting text are used by ISPF.

### Description

The KEYI tag defines a key assignment within a key mapping list. Key assignments provide a means of associating commands with keys.

KEYI tags with the same assignment cause the conversion utility to issue a warning message and retain only the first occurrence.

### Conditions

- You must code the KEYI tag within a KEYL definition. See “KEYL (Key List)” on page 355 for a complete description of this tag.
- Each KEYI definition can only have one command assigned to it. Additionally, CUA requires the following conventions when assigning commands to certain keys:
  - If KEY=F1 or F13, then CMD must be HELP.
  - If KEY=F3 or F15, then CMD must be EXIT.
  - If KEY=F12 or F24, then CMD must be CANCEL.

ISPF will allow you to provide the name of your own command on these keys.

If you code the command HELP, EXIT, or CANCEL as part of your KEYI definition, then HELP must be assigned to key F1 or F13, EXIT must be assigned to F3 or F15, and CANCEL must be assigned to F12 or F24.

### Nested Tags

None.

### Example

The following source file markup contains a key mapping list and an application panel that refers to the key mapping list. The F7 and F8 keys do not appear on the panel because they both have an FKA value of NO. Figure 130 on page 355 shows the formatted application panel with the displayed keys.

```

<!DOCTYPE DM SYSTEM(
  <!entity sampvar1 system>
  <!entity sampabc system>
  <!entity sampbody system>)>
&sampvar1;

<KEYL NAME=keyl xmp>
  <KEYI KEY=f1  CMD=help   FKA=yes>Hel p
  <KEYI KEY=f2  CMD=split  FKA=yes>Spli t
  <KEYI KEY=f3  CMD=exit   FKA=yes>Exi t
  <KEYI KEY=f5  CMD=search  FKA=no>Di spl ay
  <KEYI KEY=f6  CMD=keyhlp  FKA=yes>Keyshel p
  <KEYI KEY=f7  CMD=backward FKA=no>Backward
  <KEYI KEY=f8  CMD=forward FKA=no>Forward
  <KEYI KEY=f9  CMD=swap    FKA=yes>Swap
  <KEYI KEY=f10 CMD=actions FKA=no>Acti ons
  <KEYI KEY=f12 CMD=cancel  FKA=yes>Cancel
</KEYL>

<PANEL NAME=keyi KEYLIST=keyl xmp>Library Card Registration
<AB>
&sampabc;
</AB>
&sampbody;
</PANEL>

```

File Search Help

---

Library Card Registration

Type in patron's name and card number if applicable.

Then select an action bar choice.

Date . . . :

Card No. . . . \_\_\_\_\_ (A 7-digit number)

Name . . . . \_\_\_\_\_ (Last, First, M.I.)

Address . . \_\_\_\_\_

Choose one of the following	Check valid branches
— 1. New	— North Branch
— 2. Renewal	— South Branch
— 3. Replacement	— East Branch
	— West Branch

Enter a command ===> \_\_\_\_\_

F1=Help      F2=Split      F3=Exit      F6=KEYSHELP      F9=Swap

F12=Cancel

Figure 130. Key Items

## KEYL (Key List)

The KEYL tag defines a key mapping list where keys can be mapped to commands.

```

—<KEYL—NAME=key-l i s t -name—
                                |HELP=hel p-panel -name|

```

**NAME=key-list-name**

This attribute specifies a name for a key list. The HELP, HELPDEF, PANEL, and PANDEF tag refer to the *key-list-name*.

The *key-list-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

The name of the keylist table is xxxxKEYS where xxxx represents the application identifier provided to ISPDTLC with the KEYLAPPL keyword when invoked, in the “Keylist Application ID” field on the invocation panel, or with the APPLID attribute of this tag.

The *key-list-name* is used to identify the entry in the keylist table. For example, if NAME=CONVLIST and KEYLAPPL=XYZ, then CONVLIST will be written as a table entry to member XYZKEYS in the table library partitioned data set.

Keylists are updated using ISPF table services. Input is obtained from the ISPTLIB DDname allocation and output is written to the ISPTABL DDname allocation. Refer to the description of how to allocate libraries before starting ISPF in the *ISPF User’s Guide* for more information about the use of ISPTLIB and ISPTABL.

See Chapter 10, “Using the Conversion Utility,” on page 171 for more information on invocation parameters for the conversion utility.

**HELP=help-panel-name**

This attribute names a help panel that displays when the user requests help on a keylist display.

If a user requests help for a keylist and no help has been defined by the KEYL tag, the ZKEYHELP variable is checked for a help panel name. If the application has not set ZKEYHELP, a message that keyshelp is not available is displayed.

The *help-panel-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

See “HELP (Help Panel)” on page 335 for information about creating help panels.

**ACTION=UPDATE | DELETE**

This attribute specifies the type of action requested for the keylist specified by *key-list-name*.

When ACTION=DELETE is specified, it is not necessary to nest any KEYI tags within the KEYL tag definition.

**APPLID=application-id**

This attribute provides the application ID used to build the keylist name. The *application-id* overrides the KEYLAPPL invocation option value.

**Description**

The KEYL tag defines a key mapping list where keys can be mapped to commands.

To display these keys on a panel requires that the PANEL or PANDEF tag refer to the *key-list-name*. ISPF uses the specified key mapping list when building the

display dependent on the user's setting by the FKA command. For more information about displaying and formatting of the function key area, refer to the appropriate section in the *ISPF User's Guide*.

## Conditions

- The KEYL tag requires an end tag.
- The KEYL tag cannot be nested within any other tag definition.
- When ACTION=UPDATE is specified (or defaulted), at least one KEYI tag must be included in the keylist definition.

## Nested Tags

You can code the following tag within a KEYL definition:

Tag	Name	Usage	Page	Required
KEYI	Key item	Multiple	352	No

## Example

The following source file markup contains a key mapping list and an application panel that refers to the key mapping list. Figure 131 on page 358 shows the formatted application panel with the displayed keys.

```
<!DOCTYPE DM SYSTEM(
  <!entity sampvar1 system>
  <!entity sampabc system>
  <!entity sampbody system>)>
&sampvar1;

<KEYL NAME=key1tb1>
  <KEYI KEY=f1  CMD=hel p    FKA=yes>Hel p
  <KEYI KEY=f2  CMD=spl i t  FKA=yes>Spl i t
  <KEYI KEY=f3  CMD=exi t    FKA=yes>Exi t
  <KEYI KEY=f5  CMD=search   FKA=no>Di spl ay
  <KEYI KEY=f6  CMD=keyhl p  FKA=no>Keyshel p
  <KEYI KEY=f7  CMD=backward FKA=yes>Backward
  <KEYI KEY=f8  CMD=forward  FKA=yes>Forward
  <KEYI KEY=f9  CMD=swap     FKA=yes>Swap
  <KEYI KEY=f10 CMD=actions  FKA=no>Acti ons
  <KEYI KEY=f12 CMD=cancel   FKA=yes>Cancel
</KEYL>


<PANEL NAME=keyl KEYLIST=key1xmp>Library Card Registration
<AB>
&sampabc;
</AB>
&sampbody;
</PANEL>
```

File	Search	Help
-----		
Library Card Registration		
Type in patron's name and card number if applicable.		
Then select an action bar choice.		
Date . . . . :		
Card No. . . . :	_____ (A 7-digit number)	
Name . . . . :	_____ (Last, First, M.I.)	
Address . . . :	_____	
Choose one of the following		Check valid branches
— 1. New		— North Branch
— 2. Renewal		— South Branch
— 3. Replacement		— East Branch
		— West Branch
Enter a command ==>> _____		
F1=Help	F2=Split	F3=Exit
F12=Cancel		F6=KEYSHELP
		F9=Swap

Figure 131. Function Keys

## LI (List Item)

The LI tag defines a list item within a note list, ordered list, unordered list, or simple list.



### SPACE=NO | YES

The `SPACE` attribute controls the indentation space for the list item. When the `SPACE` attribute is not specified on the LI tag, the `SPACE` attribute from the enclosing list tag is used to set the indentation space for the *item-text*.

When `SPACE=YES`, the indentation is set to 3 spaces. When `SPACE=NO` (or `SPACE` is not specified), the indentation is set to 4 spaces.

The `SPACE` attribute can be used to control the alignment of list items when the first word of some list items is a DBCS word preceded by a shift-out character and the first word of other list items is a SBCS word.

### NOSKIP

This attribute causes the list item to format without creating a blank line before the item.

### item-text

This is the text of the list item.

## Description

The LI tag defines a list item within a note list, ordered list, unordered list, or simple list.

The formatting of the LI tag is dependent on the type of list you use it within and the level of nesting.

**List Formatting**

**Note** Formats with a 3-space or 4-space indentation (depending on the SPACE attribute) and is preceded by sequential numbers.

**Ordered**

Formats with a 3-space or 4-space indentation (depending on the SPACE attribute) within the level of the list in which it is defined and is preceded by sequential numbers or letters.

**Simple**

Formats with a 3-space or 4-space indentation (depending on the SPACE attribute) within the level of the list it is defined within.

**Unordered**

Formats with a 3-space or 4-space indentation (depending on the SPACE attribute) within the level of the list in which it is defined and is preceded by bullets or dashes.

The next list item implicitly ends the previous list item as do the NOTEL, OL, SL, and UL end tags.

If you do not specify text for a list item, a blank line is displayed for that item.

**Conditions**

- You must code the LI tag within a NOTEL, OL, SL, or UL definition. See “NOTEL (Note List)” on page 399, “OL (Ordered List)” on page 404, “SL (Simple List)” on page 480, and “UL (Unordered List)” on page 491 for descriptions of these tags.

**Nested Tags**

You can code the following tags within an LI definition:

Tag	Name	Usage	Page	Required
ATTENTION	Attention	Single	226	No
CAUTION	Caution	Single	234	No
DL	Definition list	Multiple	292	No
FIG	Figure	Multiple	324	No
HP	Highlighted phrase	Multiple	348	No
LINES	Lines	Multiple	360	No
NOTE	Note	Multiple	396	No
NOTEL	Note List	Multiple	399	No
NT	Note	Multiple	402	No
OL	Ordered list	Multiple	404	No
P	Paragraph	Multiple	406	No
PARML	Parameter list	Multiple	424	No
PS	Point-and-Shoot	Multiple	438	No
RP	Reference phrase	Multiple	454	No
SL	Simple list	Multiple	480	No
UL	Unordered list	Multiple	491	No
WARNING	Warning	Single	502	No

Tag	Name	Usage	Page	Required
XMP	Example	Multiple	508	No

## Example

The following help panel markup contains an unordered list with three list items. The last list item contains an additional paragraph of text. Figure 132 shows the formatted result.

```
<!DOCTYPE DM SYSTEM>

<HELP NAME=li DEPTH=20>Shel fBrowse Hel p
<AREA>
<INFO>
  <P>When Shel fBrowse finds your book,
  it displays this information:
  <UL>
    <LI>Reference information about the book.
    <LI>The location of the book.
    <LI>If the book is in stock.
    <P>If the book is not in stock, see the librarian.
  </UL>
  <P>Thank you for using Shel fBrowse.
</INFO>
</AREA>
</HELP>
```




Figure 132. List Items

## LINES (Lines)

The LINES tag defines unformatted text within an information region.

```
—<—LINES—>—
      |NOSKIP| |text|
```

### NOSKIP

This attribute causes the blank line normally placed before the lines to be skipped.

**text**

This is the unformatted text.

## Description

The LINES tag defines unformatted text within an information region. Tags that normally cause word-wrapping (such as the P, LI, or CAUTION) do not cause wrapping when nested within a LINES definition.

If the source text on any line is too long to fit in the remaining available formatting width, the conversion utility truncates that line. The conversion utility issues a warning message the first time that truncation occurs.

The formatting of the LINES tag is similar to that of the FIG tag, except that there is no border or caption capability.

## Conditions

- The LINES tag requires an end tag.
- You must code the LINES tag within an INFO definition. See “INFO (Information Region)” on page 350 for a complete description of this tag.

## Nested Tags

You can code the following tags within a LINES definition:

Tag	Name	Usage	Page	Required
DL	Definition list	Multiple	292	No
HP	Highlighted phrase	Multiple	348	No
NOTE	Note	Multiple	396	No
NOTEL	Note List	Multiple	399	No
NT	Note	Multiple	402	No
OL	Ordered list	Multiple	404	No
P	Paragraph	Multiple	406	No
PARML	Parameter list	Multiple	424	No
PS	Point-and-Shoot	Multiple	438	No
RP	Reference phrase	Multiple	454	No
SL	Simple list	Multiple	480	No
UL	Unordered list	Multiple	491	No
XMP	Example	Multiple	508	No

## Example

The following application panel markup contains a LINES definition. The formatted output of the LINES definition is identical to the input markup. Figure 133 on page 362 shows the formatted results.

## LINES

```
<!DOCTYPE DM SYSTEM>

<PANEL NAME=lines DEPTH=22 WIDTH=40>Lines Tag Example
<AREA>
<INFO WIDTH=38>
<P>The following area shows how the LINES tag formats.
<LINES>
First line, just at it was entered.
  Second line, ditto.

Notice we skipped a line here?

  You
    can
      even
        do
          this.
</LINES>
<P>The LINES tag formatting ends immediately above.
</INFO>
</AREA>
</PANEL>
```




Figure 133. LINES

---

## LIT (Literal)

The LIT tag defines a string where all blanks are significant and included in the value.

```
—<LIT>—l i t e r a l - d i s p l a y - v a l u e—</LIT>—
```

### literal-display-value

This attribute specifies a string with all blanks preserved.

## Description

The LIT tag defines a string where all blanks are significant and included in the value. No stripping of leading, trailing, or embedded blanks is performed.

This is the only way to specify trailing blanks or a value of all blanks in the XLATI *displayed-value*.

The LIT start and end tags must be on the same line as the *literal-display-value* to preserve the original spacing of the value.

## Conditions

- The LIT tag requires an end tag.
- You must code the LIT tag only within an XLATI definition. See “XLATI (Translate Item)” on page 504 for a complete description of this tag.
- Multiple LIT tags may be coded within a single XLATI definition, as long as they are not nested within each other. However, a better approach is to include the whole XLATI *displayed-value* within the LIT tag.

## Nested Tags

None.

## Example

The following markup contains a variable class definition with two translate lists. The last four translate items in the second list contain LIT definitions that preserve trailing blanks in the displayed value of their respective translate items.

## LP

```
<!DOCTYPE DM SYSTEM>

<VARCLASS NAME=aa TYPE=' char 2' >
<VARCLASS NAME=bb TYPE=' char 9' >
<VARCLASS NAME=cc TYPE=' char 9' >
  <XLATL FORMAT=upper>
  </XLATL>
  <XLATL>
    <XLATI VALUE=1>BIGCHARGE
    <XLATI VALUE=2><LIT>V I S T A</LIT>
    <XLATI VALUE=3><LIT>EZCARD </LIT>
    <XLATI VALUE=4><LIT>CHECK </LIT>
    <XLATI VALUE=5><LIT> CASH</LIT>
  </XLATL>

<VARLIST>
  <VARDCL NAME=di spva VARCLASS=cc>
  <VARDCL NAME=inptva VARCLASS=bb>
  <VARDCL NAME=chckva VARCLASS=aa>
</VARLIST>

<PANEL NAME=lit>LIT translation
  <TOPINST>You can display this panel with ISPF option 7.2
  <TOPINST>For this example, enter the word 'BIGCHARGE', 'V I S T A',
  'EZCARD', 'CHECK', or ' CASH' in the "literal value"
  field (no quotes).
  <TOPINST>The literal will be translated to the corresponding number
  defined in the XLATL tag, and will be displayed in the
  "translated value" field.
  <TOPINST>The literal you enter will be displayed (left justified) in
  the "original value" field.
  <DTACOL>
  <:-- assign "literal value" to "original value" -->
  <SOURCE>
  &inptva = &di spva
  </SOURCE>
  <DTAFLD DATAVAR=di spva ENTWIDTH=9 PMTWIDTH=20 ALIGN=center>Li teral value
  <DTAFLD DATAVAR=chckva ENTWIDTH=2 PMTWIDTH=20 USAGE=out>Translated value
  <DTAFLD DATAVAR=inptva ENTWIDTH=9 PMTWIDTH=20 USAGE=out>Original value
  <:-- assign translated "literal value" to "translated value" -->
  <SOURCE>
  &chckva = &di spva
  </SOURCE>
  </DTACOL>
  <CMDAREA>
</PANEL>
```

---

## LP (List Part)

The LP tag defines a comment or explanation within a note list, ordered list, unordered list, or simple list.

```
--<LP-->
  |_____|
  |_NOSKIP_|
  |_____|
  |_implied-paragraph_|
  |_____|
  |_</LP>_|
```

### NOSKIP

This attribute causes the list part to format without creating a line before the list part.

### implied-paragraph

This is the text of the list part.

## Description

The LP tag defines a comment or explanation within an ordered list, unordered list, or simple list. You can code the LP tag anywhere within a list.

The text of the list part starts at the left margin of the current level of the list. It is not numbered or lettered. When you use it within a NOTEL or OL definition, LP does not interrupt or increment the sequence.

The next list item or the end of the list implicitly ends the list part.

## Conditions

- You must code the LP tag within a NOTEL, OL, SL, or UL definition. See “NOTEL (Note List)” on page 399, “OL (Ordered List)” on page 404, “SL (Simple List)” on page 480, and “UL (Unordered List)” on page 491 for descriptions of these tags.

## Nested Tags

You can code the following tags within an LP definition:

Tag	Name	Usage	Page	Required
ATTENTION	Attention	Single	226	No
CAUTION	Caution	Single	234	No
DL	Definition list	Multiple	292	No
FIG	Figure	Multiple	324	No
HP	Highlighted phrase	Multiple	348	No
LINES	Lines	Multiple	360	No
NOTE	Note	Multiple	396	No
NOTEL	Note List	Multiple	399	No
NT	Note	Multiple	402	No
OL	Ordered list	Multiple	404	No
P	Paragraph	Multiple	406	No
PARML	Parameter list	Multiple	424	No
PS	Point-and-Shoot	Multiple	438	No
RP	Reference phrase	Multiple	454	No
SL	Simple list	Multiple	480	No
UL	Unordered list	Multiple	491	No
WARNING	Warning	Single	502	No
XMP	Example	Multiple	508	No

## Example

The following help panel markup contains an ordered list with a nested list part tag. WARNING and P tags are nested within the list part definition. Figure 134 on page 366 shows the formatted result.

```

<!DOCTYPE DM SYSTEM>

<HELP NAME=lp WIDTH=50 DEPTH=20>Help For Changing a File
<AREA>
<INFO>
<OL>
  <LI>Type over the existing data
    in the entry fields with the new data.
    <LP>
      <WARNING>
        Performing the next step will save all changes
        and delete the existing data.
      <P>To quit this function without
        deleting the existing data, press F12=Cancel.
      </WARNING>
    <LI>Press Enter to save the
      updated data.
</OL>
</INFO>
</AREA>
</HELP>

```




Figure 134. List Part


## LSTCOL (List Column)


The LSTCOL tag defines a column of data from an ISPF table displayed in the ISPF table display area of a panel.

```

---<LSTCOL---DATAVAR=column-data-----
                                     |VARCLASS=variable-class-name|

```



**DATAVAR=column-data**

This is the data which will occupy the column. The *column-data* value must be an ISPF table variable name (without a leading % sign).

**VARCLASS=variable-class-name**

This is the name of a variable class, defined with a VARCLASS tag, that overrides the default variable class referred to by the VARDCL tag that declares the data variable for the list column.

**HELP=NO | YES | help-panel-name | \*help-message-id | %varname | \*%varname**

This attribute specifies the help action taken when the user requests help for this list column. This is field-level help.

When HELP=YES, control is returned to the application. You can specify either a help panel or a message identifier. If a message identifier is used, it must be prefixed with an asterisk (\*).

The help attribute value can be specified as a variable name. When %varname is coded, a panel variable name is created. When \*%varname is coded, a message variable name is created.

If the user requests help for a list column and no help is defined, the extended help panel is displayed. If an extended help panel is not defined for the panel, the application or ISPF tutorial is invoked.

The *help-panel-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

See “HELP (Help Panel)” on page 335 for information about creating help panels. For information about creating messages, see “MSG (Message)” on page 390.

**USAGE=BOTH | IN | OUT**

This attribute indicates if this column is for input, output, or both.

**REQUIRED=NO | YES**

This attribute indicates if this column is required to have input for each modified row. The default is NO. This attribute is valid only when USAGE=IN or BOTH.

If you specify REQUIRED=YES, a conditional VER(variable, NONBLANK) statement will be built by the conversion utility and placed in the )PROC section of the ISPF panel generated. This results in the column variable being verified only when the row is selected or modified.

**MSG=message-id**

This attribute specifies the message that is displayed when the user does not complete a required entry (defined with the REQUIRED attribute). If you do not specify a *message-id*, ISPF displays a default message.

If you specify the MSG attribute and REQUIRED=YES, a VER(variable, NONBLANK, MSG=message-identifier) statement is built by the conversion utility and placed in the )PROC section of the ISPF panel generated. If you specify the MSG attribute and REQUIRED=NO (the default), the conversion utility issues a warning message.

See “MSG (Message)” on page 390 for information about creating messages.

**Note:** You can specify messages pertaining to other validations using XLATL and CHECKL tags within a VARCLASS definition. See the descriptions of these tags for additional information.

#### **COLWIDTH=data-width**

This attribute determines the data width to be used by the column. If you do not specify this attribute, the data width and column formatting width are determined by the actual length of the *column-heading*. If the width of the *column-heading* text is greater than the COLWIDTH, it will be used as the column formatting width. The minimum width is 1 and the maximum is the remaining available panel (or region) width. If the *column-heading* and the COLWIDTH attribute are omitted, the data width and column formatting width are determined by the TYPE value of the associated VARCLASS. If a VARCLASS TYPE value is not available, the size of the column variable name (specified by the DATAVAR attribute) determines the width.

You should code the COLWIDTH attribute with a value equal to the length of the table data variable.

#### **ALIGN=START | CENTER | END**

This attribute specifies how the data value is to be displayed in the data field.

An attribute character is used for the field that specifies JUST(LEFT) if ALIGN=START, JUST(ASIS) if ALIGN=CENTER or JUST(RIGHT) if ALIGN=END. When ALIGN=END, no underscore padding is performed; blanks are used.

#### **AUTOTAB=NO | YES**

When AUTOTAB=YES, the cursor moves to the next field capable of input when the user enters the last character in the list column field.

AUTOTAB=YES is valid only when the value for USAGE is either BOTH or IN.

The ISPF SKIP keyword is not supported when running in GUI mode.

#### **LINE=n**

This attribute provides the ability to place LSTCOL fields on different model lines. ISPF defines the range of lines as 1 to 8. The default is 1. Column headings are generated on multiple lines to match the LSTCOL field placement.

#### **CLEAR**

This attribute adds a CLEAR (variable, ...) statement to the )MODEL line. CLEAR should be specified for table extension variables.

For more information about the )MODEL line, refer to the *ISPF User's Guide*.

#### **POSITION=n**

This attribute specifies the starting position of the data column and related text or the column heading, if the heading is longer than the data column. If this attribute is not specified or is not valid, the conversion utility formats the column immediately to the right of the previous column on the specified or

default model line. This attribute allows you to position fields on different model lines with vertical alignment. Column position is location of the attribute byte preceding the data column.

**FORMAT=**START | CENTER | END

This attribute specifies how the data column and its column heading are formatted. If you do not specify this attribute, or if you specify the attribute value *START*, then the column formats as in ISPF Version 3.1 and ISPF Version 3.2.

Formatting of the data in the column takes place within the column width, which is determined as described in the COLWIDTH attribute section.

When you specify the attribute value *CENTER*, the conversion utility centers a column heading that is shorter than the column width. If the column heading is longer than the column width, then the data column is centered under the column heading. When either the heading or the data column is centered, blank characters are added before and after the column heading or data column. The total amount of space to be added is divided by 2 and the resulting whole number is the number of blanks added in front of the column heading or data column. The difference between the total amount of space and the amount placed in front of the column heading or data column is used at the end.

When you specify the attribute value *END*, a column heading that is shorter than the column width is right-justified so it aligns with the end of the displayed data. If the column heading is longer than the column width, the data column is right-justified so that the displayed data and the column heading end at the same position.

If there is insufficient space available to format the column heading as requested, the conversion utility issues a message that the *FORMAT* attribute is ignored.

The *FORMAT* attribute does not affect the display of the field contents within the data column, which is determined by the *ALIGN* attribute.

**TEXT=***descriptive-text*

This attribute specifies a short description of the data column. It can be placed before or after the data column. Text containing special characters or embedded blanks must be enclosed in quotes.

**TEXTLOC=**BEFORE | AFTER

This attribute specifies the location of the *TEXT* relative to the data column. Text can be placed on either side of the data column.

**TEXTFMT=**START | CENTER | END

This attribute specifies the format of the text within the length of the text area. The text can be left-justified, centered, right-justified.

**TEXTLEN=***n*

This attribute specifies the amount of space to reserve for formatting the descriptive text. This attribute helps you line up text on different model lines, and if the space reserved is longer than the descriptive text, it permits formatting within the reserved space with the *TEXTFMT* attribute. If the descriptive text is longer than the space reserved by the *TEXTLEN* attribute, the descriptive text is not formatted and a warning message is issued.

**TEXTSKIP=**NO | YES

This attribute provides for skipping past the *descriptive text* when either the *TEXTLOC=BEFORE* and the previous *LSTCOL* tag includes the *NOENDATTR*

attribute, or TEXTLOC=AFTER and the current LSTCOL tag includes the NOENDATTR attribute. If there is no other input field on the panel, the cursor moves to the first input field. The ISPF SKIP keyword is not supported in GUI mode.

#### **NOENDATTR**

This attribute specifies that no ending attribute character will be placed after the data column. NOENDATTR is ignored for the last data column on each model line.

#### **PAD=NULLS | USER | char | %varname**

This attribute specifies the pad character for initializing the field. You can define this attribute as a variable name preceded by a "%".

#### **PADC=NULLS | USER | char | %varname**

This attribute specifies the conditional padding character to be used for initializing the field. You can define this attribute as a variable name preceded by a "%".

#### **OUTLINE=NONE | L | R | O | U | BOX | %varname**

This attribute provides for displaying lines around the field on a DBCS terminal. You can define this attribute as a variable name preceded by a "%".

#### **PAS=OFF | ON | %varname**

This attribute controls the availability of the point-and-shoot function for this table field. You can define this attribute as a variable name preceded by "%"

#### **CSRGRP=NO | YES | n**

When CSRGRP=YES, the conversion utility generates a cursor group number to be used for this table column. When CSRGRP=n, the number provided is used for this field. The PAS attribute must be specified as ON or %varname.

The conversion utility accepts the CSRGRP attribute for any table field definition. The CSRGRP attribute is used at run-time for output fields only.

#### **ATTRCHANGE=NO | YES | NEW**

When ATTRCHANGE=YES or ATTRCHANGE=NEW, the conversion utility formats an additional entry in the panel )ATTR section (that can apply to multiple list columns) instead of creating a unique ".ATTR(field-name)" entry in the )INIT section for this field. With this option, multiple LSTCOL tags with the same characteristic require fewer panel logic statements.

ATTRCHANGE=NEW creates a new entry. ATTRCHANGE=YES uses an existing entry, if possible.

#### **COLSPACE=n**

The COLSPACE attribute specifies the total number of bytes for the column width, including the leading and trailing attributes, and any trailing blank following an input field. The use of the COLSPACE attribute causes column heading text longer than the COLSPACE value (minus the attribute bytes) to be flowed into multiple lines.

#### **COLTYPE=CUA | ISPF | EE | VOI | LID**

This attribute defines the attribute type to be applied to the table field. TYPE=CUA, the default, causes the field to display using the standard CUA attribute.

VOI and LID are valid only when USAGE=OUT.

EE is valid when USAGE=IN or USAGE=BOTH.

Using a CUA attribute causes the field to appear in the associated color.

When COLTYPE=ISPF, a non-CUA attribute is generated and you can specify the color, intensity, and highlighting of the field using the COLOR, INTENS, and HILITE attributes. These attributes are not valid for CUA types.

**COLOR=WHITE | RED | BLUE | GREEN | PINK | YELLOW | TURQ | %varname**

This attribute specifies the color of the field. You can define this attribute as a variable name preceded by a percent (%) sign.

**INTENS=HIGH | LOW | NON | %varname**

This attribute defines the intensity of the field. You can define this attribute as a variable name preceded by a percent (%) sign.

**HILITE=USCORE | BLINK | REVERSE | %varname**

This attribute specifies the extended highlighting attribute of the field. You can define this attribute as a variable name preceded by a percent (%) sign.

**CAPS=OFF | ON**

When CAPS=ON, the data in the field is displayed in uppercase characters.

**DISPLAY=YES | NO**

This attribute specifies whether the data for the field will be visible when the panel is displayed. This attribute is used to allow fields to contain information you do not want to appear on the screen.

**VARDCI=YES | NO**

When VARDCI=NO the list column name is not checked to the declared variable information provided with the VARCLASS and VARDCI tags.

**column-heading**

This is the text of the list column heading. If the length of the *column-heading* and the COLWIDTH values are not equal, the greater of the two is used to determine column formatting width. If the column-heading and the COLWIDTH attributes are omitted, the column formatting width is determined by the TYPE value of the associated VARCLASS. If a VARCLASS TYPE value is not available, the size of the column variable name (specified by the DATAVAR attribute) determines the width.

The *column-heading* text placement over the column is determined by the FORMAT attribute value.

## Description

In conjunction with the LSTFLD tag, LSTCOL tags provide a means of defining a vertically scrollable list display area that is made up of columns of data coming from ISPF table data. One or more ISPF )MODEL section statements will be built to display the fields defined by the LSTCOL tags. The use of LSTCOL tags requires the use of the TBDISPL service in the application program.

If the ISPF panel width is smaller than the total width of the group of columns, columns that exceed the panel width will be clipped from the right. A warning message is issued if this condition occurs.

You can use the LINE attribute to format your table to display on multiple lines.

If NOENDATTR is not specified, the conversion utility generates a beginning and ending attribute for each column of the table display )MODEL line. An additional blank is also inserted for fields with USAGE=IN or BOTH if AUTOTAB=NO. This characteristic results in the following conditions:

- When USAGE=OUT, 2 extra spaces are added to the defined column formatting width.
- When AUTOTAB=YES and USAGE=IN or BOTH, 2 extra spaces are added to the defined column formatting width.
- When AUTOTAB=NO (the default) and USAGE=IN or BOTH, 3 extra spaces are added to the defined column formatting width.

It is important that you allow for this extra space when designing your panel. The extra space is added to the width value for the field as defined in the description of the COLWIDTH attribute.

## Conditions

- You must code the LSTCOL tag within a LSTFLD or LSTGRP tag. See “LSTFLD (List Field)” on page 377 for a complete description of this tag.
- Each LSTCOL definition should have a VARDCL definition associated with the variable value specified with the DATAVAR attribute. See “VARDCL (Variable Declaration)” on page 497 for a complete description of this tag.
- Only MODEL lines that actually are formatted with fields are written in the panel body. Thus, if some LSTCOL entries specify LINE=1 and others specify LINE=3, but there are no LSTCOL entries for LINE 2, only two MODEL lines are created.
- If both PAD and PADC have been specified, PAD is ignored and PADC is used.
- When a “%varname” notation is found on any of the attributes that allow a variable name, the “%varname” entry must follow the standard naming convention described in “Rules for “%variable” Names” on page 205.

## Nested Tags

You can code the following tags within a LSTCOL definition:

Tag	Name	Usage	Page	Required
COMMENT	Comment	Multiple	275	No
HP	Highlighted phrase	Multiple	348	No
PS	Point-and-Shoot	Multiple	438	No
RP	Reference phrase	Multiple	454	No
SCRFLD	Scrollable field	Single	456	No
SOURCE	Source	Multiple	482	No

## Examples

In the following source file markup, the application panel contains a list field with five list columns. The first three columns are defined as output-only, and are coded within the Subscriber Name list group. The Number column is an input/output column, and it is coded within the Phone list group. The last column is input-only, and it is coded within the Approved list group. This column requires input, so if it is not filled in, the error message MSGG886 will be displayed. The variable declarations and classes associated with the list columns are also shown. Figure 135 on page 375 shows the formatted result of the application panel.

## LSTCOL

```
<!DOCTYPE DM SYSTEM>

<VARCLASS NAME=namecls TYPE='char 15'>
<VARCLASS NAME=mi dcls TYPE='char 1'>
<VARCLASS NAME=phoncls TYPE='char 12'>
<VARCLASS NAME=apcls TYPE='char 1'>
  <XLATL FORMAT=upper>
  </XLATL>
  <CHECKL>
    <CHECKI TYPE=values PARM1=EQ PARM2='Y N'>
  </CHECKL>

<VARLIST>
  <VARDCL NAME=xfname VARCLASS=namecls>
  <VARDCL NAME=xlname VARCLASS=namecls>
  <VARDCL NAME=xmid VARCLASS=mi dcls>
  <VARDCL NAME=xphone VARCLASS=phoncls>
  <VARDCL NAME=xapp VARCLASS=apcls>
</VARLIST>

<PANEL NAME=lstcola KEYLIST=keyltbl>Subscriber List
<TOPINST>Enter phone number, if missing,
(format - nnn-xxx-nxxx) and approved
indicator (y or n) for each person.
<AREA>
  <LSTFLD>
    <LSTGRP HEADLINE=yes>Subscriber Name
      <LSTCOL DATAVAR=xfname USAGE=out COLWIDTH=15>First Name
      <LSTCOL DATAVAR=xlname USAGE=out COLWIDTH=15>Last Name
      <LSTCOL DATAVAR=xmid USAGE=out COLWIDTH=1>MI
    </LSTGRP>
    <LSTGRP>Phone
      <LSTCOL DATAVAR=xphone COLWIDTH=12>Number
    </LSTGRP>
    <LSTGRP>Approved
      <LSTCOL DATAVAR=xapp USAGE=in REQUIRED=yes
        COLWIDTH=1 MSG=msgg886>(Y or N)
    </LSTGRP>
  </LSTFLD>
</AREA>
<CMDAREA>
</PANEL>
```

Subscriber List				ROW 1 TO 3 OF 3
Enter phone number, if missing, (format - nnn-xxx-nnnn) and approved indicator (y or n) for each person.				
----- Subscriber Name -----		Phone	Approved	
First Name	Last Name	MI	Number	(Y or N)
Pete	Moss	P	919-888-4444	-
Sally	Forth	N	_____	-
Melba	Toast	T	919-444-8888	-
***** BOTTOM OF DATA *****				
Command ==>				
F1=Help	F2=Split	F3=Exit	F7=Backward	F8=Forward
F9=Swap	F12=Cancel			

Figure 135. List Columns

To display the same table in a different format, we can change the LSTCOL tags for name to include the LINE attribute. The DTL changes are reflected in the following example.

## LSTCOL

```
<!DOCTYPE DM SYSTEM>

<VARCLASS NAME=namecls TYPE='char 15'>
<VARCLASS NAME=mi dcls TYPE='char 1'>
<VARCLASS NAME=phoncls TYPE='char 12'>
<VARCLASS NAME=appcls TYPE='char 1'>
  <XLATL FORMAT=upper>
  </XLATL>
  <CHECKL>
    <CHECKI TYPE=values PARM1=EQ PARM2='Y N'>
  </CHECKL>

<VARLIST>
  <VARDCL NAME=xfname VARCLASS=namecls>
  <VARDCL NAME=xlname VARCLASS=namecls>
  <VARDCL NAME=xmid VARCLASS=mi dcls>
  <VARDCL NAME=xphone VARCLASS=phoncls>
  <VARDCL NAME=xapp VARCLASS=appcls>
</VARLIST>

<PANEL NAME=lstcolb KEYLIST=keyl tbl>Subscriber List
<TOPINST>Enter phone number, if missing,
(format - nnn- nnn- nnnn) and approved
indicator (y or n) for each person.
<AREA>
  <LSTFLD DIV=solid>
    <LSTGRP HEADLINE=yes>Subscriber Name
      <LSTCOL DATAVAR=xfname USAGE=out LINE=1 COLWIDTH=15>First Name
      <LSTCOL DATAVAR=xlname USAGE=out LINE=2 COLWIDTH=15>Last Name
      <LSTCOL DATAVAR=xmid USAGE=out LINE=3 COLWIDTH=1>MI
    </LSTGRP>
    <LSTGRP>Phone
      <LSTCOL DATAVAR=xphone COLWIDTH=12>Number
    </LSTGRP>
    <LSTGRP>Approved
      <LSTCOL DATAVAR=xapp USAGE=in REQUIRED=yes
        COLWIDTH=1 MSG=msgg886>(Y or N)
    </LSTGRP>
  </LSTFLD>
</AREA>
<CMDAREA>
</PANEL>
```


Figure 136 on page 377 shows the formatted result of the application panel.

Subscriber List		ROW 1 TO 3 OF 3
Enter phone number, if missing, (format - nnn-xxx-nxxx) and approved indicator (y or n) for each person.		
Subscriber Name	Phone	Approved
First Name	Number	(Y or N)
Last Name		
MI		
Pete	919-888-4444	_
Moss		
P		
-----		
Sally		
Forth		
N		
-----		
Melba	919-444-8888	_
Toast		
Command ==>>		
F1=Help	F2=Split	F3=Exit
F9=Swap	F12=Cancel	F7=Backward
		F8=Forward

Figure 136. List Columns

## LSTFLD (List Field)

The LSTFLD tag defines an ISPF table display area that is made up of columns of data coming from ISPF tables.



### RULES=NONE | HORIZ | VERT | BOTH

This attribute specifies the type of interior rules that will be drawn in the table display being defined within the LSTFLD tag. This applies to all the list columns within the context of this tag.

This attribute is supported by using the ISPF outline (L|R|O|U|Box|None) statement on panel definition statements. However, the lines around fields will only be visible on double-byte character support terminals.

**Note:** Any list column field within the list field defining OUTLINE overrides the LSTFLD RULES value.

**ROWS=NOSCAN | SCAN | %varname**

This attribute provides support by TDISPL of rows previously selected by the TBSARG service. If you specify ROWS=SCAN, the conversion utility adds ROWS(SCAN) to the )MODEL line statement in the generated ISPF panel.

If you specify ROWS=%varname, ROWS(&varname) is added to the )MODEL line. The application must set the variable name to ALL or SCAN before the panel is displayed.

**DIV=NONE | BLANK | SOLID | DASH | char**

This attribute specifies the type of divider line to be added as the last line of a model set. If this attribute is omitted or specified as NONE, the divider line is not generated. If this attribute is specified as BLANK, a blank divider line is generated. You may specify either SOLID or DASH to produce a visible divider line. When the GRAPHIC invocation option is specified, SOLID produces a solid line for host display and DASH produces a dashed line. When NOGRAPHIC is specified or the panel is displayed in GUI mode, both SOLID and DASH produce a dashed line. Alternately, you can specify a character or a character string of your choice. The character or characters provided are replicated to the available width of the panel (or region) to create the divider line.

If you have defined LSTCOL tags for all 8 of the available model lines, then the conversion utility issues a message and does not generate any divider line.

**SCROLLVAR=scroll-variable**

This attribute specifies the name of a variable that the application uses to obtain scrolling information. The *scroll-variable* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

If the attribute is specified, the conversion utility creates a scroll entry on the command line, providing that the resulting command area allows at least 8 bytes for a command entry.

**SCRVHELP=NO | YES | scroll-help-panel-name | \*scroll-help-message-id | %varname | \*%varname**

This attribute specifies the help action taken when the user requests help for the field specified with the SCROLLVAR attribute.

When SCRHELP=YES, control is returned to the application. You can specify either a help panel or a message identifier. If a message identifier is used, it must be prefixed with an asterisk (\*).

The help attribute value can be specified as a variable name. When %varname is coded, a panel variable name is created. When \*%varname is coded, a message variable name is created.

If the user requests help on a choice and no help is defined, the extended help panel is displayed. If an extended help panel is not defined for the panel, the application or ISPF tutorial is invoked.

The *scroll-help-panel-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

See “HELP (Help Panel)” on page 335 for information about creating help panels. For information about creating messages, see “MSG (Message)” on page 390.

#### SCROLLTAB=NO | YES

When SCROLLTAB=YES, the cursor moves to the next input field when the user enters the last character in the scroll amount field. If there is no other input field on the panel, the cursor moves to the beginning of the command line. The ISPF SKIP keyword is not supported in GUI mode.

#### SCRCAPS=OFF | ON

When SCRCAPS=ON, the data in the scroll field is displayed in uppercase characters.

#### ATTRCHANGE=NO | YES | NEW

When ATTRCHANGE=YES or ATTRCHANGE=NEW, the conversion utility formats an additional entry in the panel )ATTR section (that can apply to multiple list columns) instead of creating a unique “.ATTR(field-name)” entry in the )INIT section for each field. With this option, multiple LSTCOL tags with the same characteristics require fewer panel logic statements.

ATTRCHANGE=NEW creates a new entry. ATTRCHANGE=YES uses an existing entry, if possible.

**Note:** Any list column field within the list field defining ATTRCHANGE overrides the LSTFLD ATTRCHANGE value.

#### VARDCCL=YES | NO

When VARDCCL=NO, the list field name is not checked to the declared variable information provided with the VARCLASS and VARDCCL tags.

**Note:** Any list column field within the list field defining VARDCCL overrides the LSTFLD VARDCCL value.

## Description

The LSTFLD tag defines a scrollable list display area that is made up of columns of data coming from ISPF table data. The conversion utility creates a )MODEL line at the bottom of the )BODY section of the panel the list field is coded within.

The use of the LSTFLD tag causes all other tags that generate panel data and that are coded after the LSTFLD end tag to be moved before the )MODEL statement. This is because ISPF does not allow any panel body definition after the )MODEL statement.

## Conditions

- The LSTFLD tag requires an end tag.
- You must code the LSTFLD tag within an AREA, REGION, or PANEL definition. See “AREA (Area)” on page 217, “REGION (Region)” on page 446, and “PANEL (Panel)” on page 413 for descriptions of these tags.
- You can code only one list field on an application panel.
- You should code a CMDAREA on any panel that contains a LSTFLD definition. If you do not include the CMDAREA tag, the conversion utility inserts one and issues a message, unless the PANEL tag specifies CMDLINE=NO.
- You can use the SCROLLVAR attribute only once within a panel.
- The resulting scroll entry on the command line must leave at least 8 positions for the command entry field.

## LSTFLD

- If you specify the SCRHELP attribute, you must also specify the SCROLLVAR attribute.

### Nested Tags

You can code the following tags within a LSTFLD definition:

Tag	Name	Usage	Page	Required
COMMENT	Comment	Multiple	275	No
LSTCOL	List column	Multiple	366	No
LSTGRP	List group	Multiple	382	No
LSTVAR	List variable	Multiple	385	No
SOURCE	Source	Multiple	482	No

### Example

The application panel in the following source file markup contains a list field with five list columns of data. In addition, three list groups are defined within the list field. The first three list columns are output-only columns. The fourth list column uses the default value *both*, which allows it to handle both input and output data. The last list column is an input-only column, and input by the user is required. Figure 137 on page 382 shows the formatted result.

```

<!DOCTYPE DM SYSTEM>

<VARCLASS NAME=namecls TYPE='char 15'>
<VARCLASS NAME=mi dcls TYPE='char 1'>
<VARCLASS NAME=phoncls TYPE='char 12'>
<VARCLASS NAME=appls TYPE='char 1'>
  <XLATL FORMAT=upper>
  </XLATL>
  <CHECKL>
    <CHECKI TYPE=values PARM1=EQ PARM2='Y N'>
  </CHECKL>

<VARLIST>
  <VARDCL NAME=xfname VARCLASS=namecls>
  <VARDCL NAME=xlname VARCLASS=namecls>
  <VARDCL NAME=xmid VARCLASS=mi dcls>
  <VARDCL NAME=xphone VARCLASS=phoncls>
  <VARDCL NAME=xapp VARCLASS=appls>
</VARLIST>

<PANEL NAME=lstfld3 KEYLIST=keyl tbl>Subscriber List
<TOPINST>Enter phone number, if missing,
(format - nnn- nnn- nnnn) and approved
indicator (y or n) for each person.
<AREA>
  <LSTFLD SCROLLVAR=scr l amt SCRHELP=scr help>
    <LSTGRP HEADLINE=yes>Subscriber Name
      <LSTCOL DATAVAR=xfname USAGE=out COLWIDTH=15>First Name
      <LSTCOL DATAVAR=xlname USAGE=out COLWIDTH=15>Last Name
      <LSTCOL DATAVAR=xmid USAGE=out COLWIDTH=1>MI
    </LSTGRP>
    <LSTGRP>Phone
      <LSTCOL DATAVAR=xphone COLWIDTH=12>Number
    </LSTGRP>
    <LSTGRP>Approved
      <LSTCOL DATAVAR=xapp USAGE=in REQUIRED=yes
        COLWIDTH=1 MSG=msg886>(Y or N)
    </LSTGRP>
  </LSTFLD>
</AREA>
<CMDAREA>
</PANEL>

```





Figure 137. List Field

## LSTGRP (List Group)

The LSTGRP tag defines a heading for a single column or multiple columns within a list field.



### HEADLINE=NO | YES | DASH

This attribute specifies whether the heading text is padded to span the width of the group heading not occupied by the text. This provides a visual indication of the columns that belong to a group heading. You must specify YES or DASH to produce the visible indicator. When the GRAPHIC invocation option is specified, YES produces a solid line for host display and DASH produces a dashed line. When NOGRAPHIC is specified or the panel is displayed in GUI mode, both YES and DASH produce a dashed line.

### ALIGN=CENTER | START | END

This attribute specifies how the list group heading is formatted. If you do not specify this attribute, or if you specify ALIGN=CENTER, then the heading will be centered over multiple columns or a variable model line, or left-justified over a single column.

When ALIGN=START, the list group heading is left-justified. When ALIGN=END, the list group heading is right-justified.

### column-group-heading

The heading is placed above the column group in the nonscrollable part of the list field. The heading must fit on one line above the column or columns in the group. If *column-group-heading* text is longer than the formatted width of the

column or columns in the group, it is truncated. The *column-group-heading* appears on the line immediately above the group of columns.

If you do not specify *column-group-headings* for any of the columns within the group, the conversion utility will reserve the area where the heading would be displayed and fill it with blanks. If the *column-group-heading* is not specified but HEADLINE=YES is specified, the heading will contain only a dashed line.

## Description

The LSTGRP tag defines a heading for a single column or multiple columns within a list field. You can use the LSTGRP tag to group columns in a list field together under a single heading that applies to all of the columns. You create the columns using the LSTCOL or LSTVAR tag.

The list field can contain other columns that do not belong to the list column group. Only the LSTCOL or LSTVAR definitions nested within the LSTGRP tag belong to the group.

There must be at least one LSTCOL tag, nested LSTGRP tag, or LSTVAR tag defined within a column group. The column formatting widths, and the gutters between them, define how much space is allocated for the group heading. If this space is less than the space needed for the group heading, the conversion utility will truncate the heading. If the LSTGRP definition contains only one LSTCOL tag, and the ALIGN attribute is not specified, the group heading is left-justified over the column.

You can use the LSTGRP tag to specify multiple lines of single column headings or multiple lines of multiple column headings.

## Conditions

- The LSTGRP tag requires an end tag.
- You must code the LSTGRP tag within a LSTFLD definition or another LSTGRP definition. See “LSTFLD (List Field)” on page 377 for a complete description of the LSTFLD tag.
- You can code multiple LSTGRP tags within a LSTFLD definition.
- A LSTGRP definition must contain a nested LSTCOL, LSTVAR, or LSTGRP tag, otherwise the conversion utility will issue an error.
- The nested tags LSTCOL definitions must include at least one data column from the first displayable model line.

## Nested Tags

You can code the following tags within the LSTGRP tag:

Tag	Name	Usage	Page	Required
COMMENT	Comment	Multiple	275	No
HP	Highlighted phrase	Multiple	348	No
LSTCOL	List column	Multiple	366	Yes
LSTGRP	List group	Multiple	382	No
LSTVAR	List variable	Multiple	385	No
PS	Point-and-Shoot	Multiple	438	No
RP	Reference phrase	Multiple	454	No

Tag	Name	Usage	Page	Required
SOURCE	Source	Multiple	482	No

## Example

In the following source file markup, the application panel contains a list field with six list columns. The first three columns are placed under a common group, as are the last two columns. Also, for each of the first three columns, a second-level group heading is used in place of list column headings. This technique provides a blank space between the group headings and the data columns. Figure 138 on page 385 shows the formatted result of the application panel.

```
<!DOCTYPE DM SYSTEM>

<VARCLASS NAME=namecls TYPE=' char 12' >
<VARCLASS NAME=mi dcls TYPE=' char 1' >
<VARCLASS NAME=yearcls TYPE=' char 9' >
<VARCLASS NAME=semcls TYPE=' char 2' >

<VARLIST>
  <VARDCL NAME=xfname VARCLASS=namecls>
  <VARDCL NAME=xlname VARCLASS=namecls>
  <VARDCL NAME=xmid VARCLASS=mi dcls>
  <VARDCL NAME=xyear VARCLASS=yearcls>
  <VARDCL NAME=sem1 VARCLASS=semcls>
  <VARDCL NAME=sem2 VARCLASS=semcls>
</VARLIST>

<PANEL NAME=lstgrp WIDTH=66 KEYLIST=keytbl>Class Roster
<AREA>
  <LSTFLD>
    <LSTGRP HEADLINE=yes>Student Name
      <LSTGRP>Last
        <LSTCOL DATAVAR=xlname USAGE=out COLWIDTH=12>
      </LSTGRP>
      <LSTGRP>First
        <LSTCOL DATAVAR=xfname USAGE=out COLWIDTH=12>
      </LSTGRP>
      <LSTGRP>M
        <LSTCOL DATAVAR=xmid USAGE=out COLWIDTH=1>
      </LSTGRP>
      <LSTGRP>Class
      <LSTGRP>Year
        <LSTCOL DATAVAR=xyear USAGE=out COLWIDTH=9>
      </LSTGRP>
      </LSTGRP>
      <LSTGRP HEADLINE=yes>Grade
        <LSTCOL DATAVAR=sem1 COLWIDTH=2>Sem 1
        <LSTCOL DATAVAR=sem2 COLWIDTH=2>Sem 2
      </LSTGRP>
    </LSTFLD>
  </AREA>
</CMDAREA>
</PANEL>
```

Class Roster				ROW 1 TO 6 OF 6	
----- Student Name -----		Class	-- Grade ---		
Last	First	M	Year	Sem 1	Sem 2
Duff	Dean	T	Junior	A	B+
Gillihan	Dana	L	Freshman	B+	B
Rivas	Sergio	J	Post-Grad	D	D
Romero	Maria	C	Post-Grad	A	A
Spencer	Donald	M	Freshman	A	B
Szabo	Imre	B	Senior	C+	B
***** BOTTOM OF DATA *****					

Command ==>

F1=Help	F2=Split	F3=Exit	F7=Backward	F8=Forward
F9=Swap	F12=Cancel			

Figure 138. List Group

## LSTVAR (List Variable)

The LSTVAR tag defines a )MODEL section variable model line displayed in the ISPF table display area of a panel.

```

--<LSTVAR--DATAVAR=variable-model-name
                                     [LINE=n]
                                     [column-heading]
</LSTVAR>

```

### DATAVAR=variable-model-name

This is the data which will occupy the column. The *variable-model-name* value must be a variable model line name (without a leading % sign).

### LINE=n

This attribute provides the application the ability to place a LSTVAR model variable on different model lines. ISPF defines the range of lines as 1 to 8. The default is 1. Headings are generated on multiple lines to match the LSTVAR field placement.

### column-heading

This is the text of the model variable heading.

## Description

In conjunction with the LSTFLD and LSTCOL tags, LSTVAR tags provide a means of defining a vertically scrollable list display area that is made up of data coming from ISPF tables. One or more ISPF )MODEL section statements will be built to display the fields defined by the LSTVAR tags. The use of LSTVAR tags requires the use of the TBDISPL service in the application program.

The application must place valid data in the variable model line before the panel is displayed.

You can use the LINE attribute to format your table to display on multiple lines.

## Conditions

- You must code the LSTVAR tag within a LSTFLD tag. See “LSTFLD (List Field)” on page 377 for a complete description of this tag.
- Only MODEL lines that are not blank fields are written in the panel body. Thus, if one LSTVAR entries specifies LINE=1 and another specifies LINE=3, but there are no entries for LINE 2, only two MODEL lines are created.

## Nested Tags

You can code the following tags within the LSTVAR tag:

Tag	Name	Usage	Page	Required
COMMENT	Comment	Multiple	275	No
HP	Highlighted phrase	Multiple	348	No
PS	Point-and-Shoot	Multiple	438	No
RP	Reference phrase	Multiple	454	No
SOURCE	Source	Multiple	482	No

## Example

In the following source file markup, the application panel contains a list field with five list columns and 2 variable model lines. The first three columns are defined as output-only, and are coded within the **Subscriber Name** list group. The **Number** column is an input/output column, and it is coded within the **Phone** list group. The last column is input-only, and it is coded within the **Approved** list group. This column requires input, so if it is not filled in, the error message *MSGG886* will be displayed. The variable declarations and classes associated with the list columns are also shown.

**Note:** The variable model lines are shown in the formatted output to illustrate the formatting process. The application must provide valid values for these variables before the panel is displayed.

Figure 139 on page 388 shows the formatted result of the application panel.

```

<!DOCTYPE DM SYSTEM>

<VARCLASS NAME=namecls TYPE=' char 15' >
<VARCLASS NAME=mi dcls TYPE=' char 1' >
<VARCLASS NAME=phoncls TYPE=' char 12' >
<VARCLASS NAME=appls TYPE=' char 1' >
  <XLATL FORMAT=upper>
  </XLATL>
<CHECKL>
  <CHECKI TYPE=values PARM1=EQ PARM2=' Y N' >
  </CHECKL>

<VARLIST>
  <VARDCL NAME=xfname VARCLASS=namecls>
  <VARDCL NAME=xlname VARCLASS=namecls>
  <VARDCL NAME=xmid VARCLASS=mi dcls>
  <VARDCL NAME=xphone VARCLASS=phoncls>
  <VARDCL NAME=xapp VARCLASS=appls>
</VARLIST>

<PANEL NAME=lstvar KEYLIST=keyltbl>Subscriber List
<TOPINST>Enter phone number, if missing,
(format - nnn-xxx-xxxx) and approved
indicator (y or n) for each person.
<AREA>
  <LSTFLD>
    <LSTVAR datavar=xmodelv1>Variable model line at top
  <LSTGRP HEADLINE=yes>Subscriber Name
    <LSTCOL DATAVAR=xfname USAGE=out line=2 COLWIDTH=15>First Name
    <LSTCOL DATAVAR=xlname USAGE=out line=2 COLWIDTH=15>Last Name
    <LSTCOL DATAVAR=xmid USAGE=out line=2 COLWIDTH=1>MI </LSTGRP>
  <LSTGRP>Phone
  <LSTCOL DATAVAR=xphone line=2 COLWIDTH=12>Number
  </LSTGRP>
  <LSTGRP>Approved
  <LSTCOL DATAVAR=xapp USAGE=in line=2 REQUIRED=yes
  COLWIDTH=1 MSG=msgf886>(Y or N)
  </LSTGRP>
  <LSTVAR datavar=xmodelv2 line=3>Variable model line at bottom
  </LSTFLD>
</AREA>
<CMDAREA>
</PANEL>

```

```

Subscriber List

Enter phone number, if missing, (format - nnn-xxx-nnnn)&cont.
and approved
indicator (y or n) for each person.

----- Subscriber Name ----- Phone
Approved
Variable model line at top
First Name      Last Name      MI  Number      (Y or N)
Variable model line at bottom
&XMODELV1
-----
&XMODELV2

Command ==>> -----
F1=Help      F2=Split      F3=Exit      F7=Backward  F8=Forward
F9=Swap      F12=Cancel

```

Figure 139. List Variable

## M (Mnemonic)

The M tag defines a single character to be used as a mnemonic selection for action bar or pull-down choices.

```

--<M>--mnemonic-character-----
                                |</M>|

```

### mnemonic-character

The single-byte character following the mnemonic start tag specifies the mnemonic for the action bar choice or pull-down choice. The mnemonic-character must be a single-byte alphabetic or numeric character; double-byte characters are not allowed.

If you want the mnemonic to be a character that is not part of the normal choice text, follow the choice text with the mnemonic character specified within parenthesis. This convention is particularly useful when you have a large number of choices, which makes it difficult to choose a unique mnemonic for each choice. For example, if you had the pull-down choice Add, and the characters A and d were already used on other choices in the same pull-down, you could choose another character for your mnemonic:

```
<pd>>Add(<m>B)
```

In this case B becomes the mnemonic for Add. When an alternate mnemonic is specified on a PDC tag, the resulting 3 bytes of text (the "(B)" in this example), are replaced in the description by a variable. The variable is set to blanks or to the 3-byte value depending on the ZGUI variable, thus displaying the mnemonic only in GUI mode.

## Description

Mnemonic characters are supported by ISPF for pull-down choices only when you are running in GUI mode. They are ignored for host display.

Unless you have specified MNEMGEN=NO on the AB tag, the conversion utility will automatically select a mnemonic character for each action bar and pull-down choice for SBCS conversions. The character selected as the mnemonic is the first alphabetic or numeric character in the choice description not previously used as a mnemonic for that set of choices.

## Conditions

When the conversion utility automatically generates mnemonics, the M tag selection is processed first, and if the specified mnemonic is valid, the automatic mnemonic generation is not used for that choice. If the specified mnemonic character is invalid, or a duplicate of a previously used mnemonic character (either specified or automatically selected), a message is issued and an attempt will be made to select a different mnemonic character.

When processing DBCS conversions or when MNEMGEN=NO is coded on the AB tag, automatic mnemonic character selection is disabled and mnemonic characters are only specified by the M tag. The use of mnemonics should be consistent for all choices in an action bar or pull-down as follows:

- Code the M tag within the text following the ABC and PDC tags.
- Each mnemonic chosen must be unique. The conversion utility will issue a message and discard duplicate mnemonics.
- If mnemonics are used for any action bar or pull-down choice, they should be used for all of the choices. The conversion utility will issue a message if any choice in a group does not have a mnemonic.

## Nested Tags

None.

## Example

In the following example, all of the action bar choices and pull-down choices have been coded to show the use of the M tag. Some of the pull-down choices illustrate the use of the optional end tag.

## MSG

```


<!DOCTYPE DM SYSTEM(
  <!entity sampvar1 sysem>
  <!entity sampbody system>)>
&sampvar1;

<PANEL NAME=m1 KEYLIST=keylxml>Library Card Registration
<AB>
<ABC><M>File
  <PDC><M>A</M>dd Entry
    <ACTION RUN=add>
  <PDC><M>D</M>elete Entry
    <ACTION RUN=delete>
  <PDC><M>U</M>pdate Entry
    <ACTION RUN=update>
  <PDC><M>E</M>xi t
    <ACTION RUN=exi t>
<ABC><M>Search
  <PDC CHECKVAR=whchsrch MATCH=1>Search on <M>n</M>ame
    <ACTION SETVAR=whchsrch VALUE=1>
    <ACTION RUN=search>
  <PDC CHECKVAR=whchsrch MATCH=2>Search on <M>c</M>ard number
    <ACTION SETVAR=whchsrch VALUE=2>
    <ACTION RUN=search>
<ABC><M>Hel p
  <PDC><M>Extended Hel p...
    <ACTION RUN=exhel p>
  <PDC><M>Keys Hel p...
    <ACTION RUN=keyshel p>
</AB>
&sampbody;
</PANEL>

```

## MSG (Message)

The MSG tag defines a message within a message member.



**SUFFIX=message-suffix-number**

This attribute specifies the suffix of the message. The suffix consists of either 1 numeric character (0–9) or a numeric character (0–9) and an optional alpha suffix character as defined for ISPF messages, which is added to the MSGMBR *message-member-name* to form the ISPF message ID.

Each *message-suffix-number* within a message member must be unique. Attempts to define duplicate suffixes will result in a warning message and the duplicate MSG will be ignored.

**HELP=help-panel-name | %varname | \***

Specifies the name of the help panel that is associated with this message and that will be displayed if the user requests help for the message.

If you specify a help panel, ISPDTLC generates “.HELP=help-panel-name” (or “.HELP=&varname” or “.HELP=”) in the ISPF message ID definition. If you don’t specify a help panel, no help is available for the message.

The *help-panel-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

**MSGTYPE=INFO | WARNING | ACTION | CRITICAL | %varname**

This attribute specifies the severity of the message. ISPF displays INFO messages without an alarm. ISPF displays WARNING, ACTION, and CRITICAL messages with an alarm.

ACTION and CRITICAL message types are used to identify the most severe errors. This level of error usually requires a user response. ISPF will always display CRITICAL messages in a pop-up. ACTION messages are displayed based on the value of the LOCATION attribute.

The %varname value specifies that the value INFO, WARNING, ACTION, or CRITICAL will be provided in the named variable by the application before issuing the message.

The conversion utility changes INFO to .TYPE=NOTIFY when formatting the message member.

ISPF recognizes message types (.TYPE=) of NOTIFY, WARNING, ACTION, and CRITICAL. ISPF uses the TYPE value specified in conjunction with the value of .WINDOW to determine the display characteristics of the message. The .WINDOW value is generated from the value specified for the LOCATION attribute. For more information on ISPF messages, refer to *ISPF Dialog Developer’s Guide and Reference*.

**LOCATION=AREA | MODAL | MODAL(L) | MODELESS | MODELESS(L) | %varname**

This attribute specifies how the message is displayed.

LOCATION=AREA (the default) specifies that the message is to appear in the panel message area. However, if the text of the message exceeds the length of the panel message area, ISPF will display the message in a pop-up.

LOCATION=MODAL specifies that the message is to appear in a pop-up which requires a user response. The conversion utility generates .WINDOW=RESP in the ISPF message definition.

LOCATION=MODAL(L) specifies that the long message is to appear in a pop-up which requires a user response. The conversion utility generates .WINDOW=LRESP in the ISPF message definition.

LOCATION=MODELESS specifies that the message is to appear in a pop-up which does not require a user response. The conversion utility generates .WINDOW=NORESP in the ISPF message definition.

LOCATION=MODELESS(L) specifies that the long message is to appear in a pop-up which does not require a user response. The conversion utility generates .WINDOW=LNORESP in the ISPF message definition.

LOCATION=%varname specifies that the value AREA, MODAL, or MODELESS will be provided in the named variable by the application prior to issuing the message. The conversion utility generates .WINDOW=&VARIABLE in the ISPF message definition.

#### **DISP=KANA | NOKANA**

This attribute specifies the addition of either the KANA or NOKANA keyword to the message control information.

#### **ALARM=NO | YES | %varname**

This attribute controls the use of the alarm when the message is displayed.

ALARM=%varname specifies that the value YES or NO will be provided in the named variable by the application before issuing the message.

#### **ABBREV=NONE | KEYWORD | VALUE | BOTH**

This attribute specifies the format of the message control information. You may abbreviate the message control keyword, the message control keyword value, or both.

#### **FORMAT=FLOW | ASIS**

This attribute specifies the formatting of the *message-text*.

The default of **FLOW** means to flow the message text continuously within the WIDTH of the MSGMBR.

When FORMAT=ASIS, the generated message preserves embedded blanks, but drops leading or trailing blanks.

#### **SMSG=short-message-text**

You can provide a short message of up to 24 bytes which ISPF will display in the short message area of the panel.

The VARSUB tag is not supported within the *short-message-text*. If a substitution variable is required, you may code "&variable" to place the variable name in the message. A *short-message-text* consisting of more than one word must be enclosed within quotation marks (" "). If the *short-message-text* contains a single apostrophe ('), the conversion utility generates double apostrophes as it does for *message-text*, as described below.

The short message is not recommended by the CUA Architecture definition.

A short message cannot be created unless the *message-text* is also provided.

#### **message-text**

This is the text of the message. The *message-text* is placed in the long-message area of a message file. The *message-text* is limited to 512 characters. The conversion utility truncates all *message-text* after 512 characters and issues a warning message. If no *message-text* is coded, then no message is generated.

Several characters within the long message area have a special meaning to ISPF. If you use the apostrophe within *message-text*, the conversion utility generates double apostrophes so the single apostrophe will be displayed when ISPF issues the message. If you use the ampersand (&) within the long

message, it must be coded as “&” followed by a blank or semicolon to be interpreted as a literal ampersand character (through ENTITY substitution).

For ISPF substitution variables, you should code the VARSUB tag. ISPF does not perform output translation (specified in the associated VARCLASS tag) on ISPF run-time substitution variables.

Refer to the *ISPF Dialog Developer's Guide and Reference* for a description of the syntax rules you should use for defining consistent messages.

## Description

The MSG tag defines a message within a message member. Each MSG definition within a message member must have a unique *message-suffix-number*.

## Conditions

- You must code the MSG tag within a MSGMBR definition. See “MSGMBR (Message Member)” on page 394 for a complete description of this tag.
- When a “%varname” notation is found on any of the attributes that allow a variable name, the “%varname” entry must follow the standard naming convention described in “Rules for “%variable” Names” on page 205.

## Nested Tags

You can code the following tag within a MSG definition:

Tag	Name	Usage	Page	Required
VARSUB	Variable substitution	Multiple	500	No

## Example

The following markup contains the message member MSGG88, which contains nine MSG definitions. The text of messages MSGG883 and MSGG888 contain variable substitutions. Figure 140 on page 394 shows the generated ISPF message member.

```
<!DOCTYPE DM SYSTEM>

<VARCLASS NAME=msgcls TYPE='char 20' >
<VARLIST>
  <VARDCL NAME=phoneno VARCLASS=msgcls>
  <VARDCL NAME=cnum VARCLASS=msgcls>
</VARLIST>

<MSGMBR NAME=msgg88>
  <MSG SUFFIX=1 disp=kana abbrev=keyword>Name must be alphabetic.
  <MSG SUFFIX=2 disp=nokana abbrev=value>Enter only number of days.
  <MSG SUFFIX=3 MSGTYPE=critical>The only rooms we have available
  are either SINGLE or DOUBLE. Please call the manager of the hotel
  who will arrange equivalent lodging at another
  hotel in the area. This is our mistake, and we will, of course,
  pick up the bill. Please call collect <VARSUB VAR=phoneno>.
  <MSG SUFFIX=4 MSGTYPE=action LOCATION=modal abbrev=both>
  Please enter either BIGCHARGE, V I S T A, EZCARD, CHECK, or CASH.
  <MSG SUFFIX=5 MSGTYPE=warning LOCATION=modeless>Please enter your name.
  <MSG SUFFIX=6>Please enter Y or N.
  <MSG SUFFIX=7>Card number is a seven-digit number.
  <MSG SUFFIX=8 MSGTYPE=warning>The card number you entered,
  <VARSUB VAR=cnum> is not valid.
  <MSG SUFFIX=9>Message '9' contains embedded quotes.
</MSGMBR>
```



**CCSID=n**

CCSID specifies the coded-character-set identifier as defined by the Character Data Representation Architecture. CCSID should be entered as a five-position numeric value. For more information on using the CCSID attribute, refer to the *ISPF Dialog Developer's Guide and Reference*

**WIDTH=76 | 68**

This attribute specifies the width of the formatted messages. When WIDTH=68, the resulting messages are formatted entirely within a normal Edit or View screen.

## Description

The MSGMBR tag defines a message member. You can code multiple message members for a single application.

The *message-member-name* is an explicit part of the identifier for messages coded in the message member. Each message member contains multiple messages. You use the MSG tag to define messages within a message member.

## Conditions

- The MSGMBR tag requires an end tag.
- You cannot code the MSGMBR tag within any other tag definition.

## Nested Tags

You can code the following tags within a MSGMBR definition:

Tag	Name	Usage	Page	Required
COMMENT	Comment	Multiple	275	No
MSG	Message	Multiple	390	Yes

## Example

The following markup defines the message member *MSGM88*, which contains nine MSG definitions. Figure 141 on page 396 shows the generated ISPF message member.

## MSGMBR

```
<!DOCTYPE DM SYSTEM>

<VARCLASS NAME=msgcls TYPE='char 20' >
<VARLIST>
  <VARDCL NAME=phoneno VARCLASS=msgcls>
  <VARDCL NAME=cnum VARCLASS=msgcls>
</VARLIST>

<MSGMBR NAME=msgm88>
  <MSG SUFFIX=1>Name must be alphabetic.
  <MSG SUFFIX=2>Enter only number of days.
  <MSG SUFFIX=3 MSGTYPE=critical>The only rooms we have available
  are either SINGLE or DOUBLE. Please call the manager of the hotel
  who will arrange equivalent lodging at another
  hotel in the area. This is our mistake, and we will, of course,
  pick up the bill. Please call collect <VARSUB VAR=phoneno>.
  <MSG SUFFIX=4 MSGTYPE=action LOCATION=modal>Please enter either
  BIGCHARGE, V I S T A, EZCARD, CHECK, or CASH.
  <MSG SUFFIX=5 MSGTYPE=warning LOCATION=modelless>Please enter your name.
  <MSG SUFFIX=6>Please enter Y or N.
  <MSG SUFFIX=7>Card number is a seven-digit number.
  <MSG SUFFIX=8 MSGTYPE=warning>The card number you
  entered, <VARSUB VAR=cnum> is not valid.
  <MSG SUFFIX=9>Message '9' contains embedded quotes.
</MSGMBR>
```


```
MSGM881 .TYPE=NOTIFY
'Name must be alphabetic.'
MSGM882 .TYPE=NOTIFY
'Enter only number of days.'
MSGM883 .TYPE=CRITICAL
'The only rooms we have available are either SINGLE or DOUBLE. Please call th' +
'e manager of the hotel who will arrange equivalent lodging at another hotel ' +
'in the area. This is our mistake, and we will, of course, pick up the bill. ' +
'Please call collect &PHONENO.'
MSGM884 .TYPE=ACTION .WINDOW=RESP
'Please enter either BIGCHARGE, V I S T A, EZCARD, CHECK, or CASH.'
MSGM885 .TYPE=WARNING .WINDOW=NORESP
'Please enter your name.'
MSGM886 .TYPE=NOTIFY
'Please enter Y or N.'
MSGM887 .TYPE=NOTIFY
'Card number is a seven-digit number.'
MSGM888 .TYPE=WARNING
'The card number you entered, &CNUM is not valid.'
MSGM889 .TYPE=NOTIFY
'Message '9' contains embedded quotes.'
```

Figure 141. Message Member

---

## NOTE (Note)

The NOTE tag defines a single-paragraph note within an information region.

**NOSKIP**

This attribute causes the note to be formatted without creating a blank line before the note.

**INDENT=n**

This attribute specifies that the note be indented from the current left margin.

**TYPE= ET | CH | CT | FP | LEF | LI | NT | PT | SAC | TEXT | WASL | WT**

This attribute defines the attribute type to be applied to the note heading. Using a CUA attribute causes the text to appear in the associated color.

When TYPE=TEXT, a non-CUA attribute is generated and you can specify the color, intensity, and highlighting with the COLOR, INTENS, and HILITE attributes. These attributes are not valid for CUA types.

**COLOR= WHITE | RED | BLUE | GREEN | PINK | YELLOW | TURQ | %varname**

This attribute specifies the color of the note heading. You can define this attribute as a variable name preceded by a percent (%) sign.

**INTENS= HIGH | LOW | NON | %varname**

This attribute defines the intensity of the note heading. You can define this attribute as a variable name preceded by a percent (%) sign.

**HILITE= USCORE | BLINK | REVERSE | %varname**

This attribute specifies the extended highlighting attribute for the note heading. You can define this attribute as a variable name preceded by a percent (%) sign.

**TEXT=alternate-note-heading**

This attribute provides a text string to replace the standard "Note:" heading.

**note-text**

This is the text of the note.

## Description

The NOTE tag defines a single-paragraph note within an information region. You can code the NOTE tag anywhere within an INFO tag.

The text of the note formats as an implied paragraph, at the current left margin. The text “Note:” (or its translated equivalent), or the alternate note heading, begins the paragraph and is aligned with the text of a list item when you use it within a list.

## Conditions

- You must code the NOTE tag within an INFO definition. See “INFO (Information Region)” on page 350 for a complete description of this tag.
- You cannot nest a NOTE tag within another NOTE definition.

## Nested Tags

You can code the following tags within a NOTE tag:

Tag	Name	Usage	Page	Required
HP	Highlighted phrase	Multiple	348	No
PS	Point-and-Shoot	Multiple	438	No
RP	Reference phrase	Multiple	454	No

## Example

The following help panel markup contains a note. Figure 142 on page 399 shows the formatted result.

```
<!DOCTYPE DM SYSTEM>

<HELP NAME=note DEPTH=20>Book / Periodical Search Help
<AREA>
<INFO>
  <P>This entry screen allows you to locate a desired
  book or periodical by entering the title in the entry field.
  <NOTE>If the item you are trying to locate is not
  in stock and you would like to reserve it, please see the
  librarian at the front desk.
</INFO>
</AREA>
</HELP>
```

Book / Periodical Search Help

This entry screen allows you to locate a desired book or periodical by entering the title in the entry field.

Note: If the item you are trying to locate is not in stock and you would like to reserve it, please see the librarian at the front desk.

F1=Hel p

F6=Keyshel p

F10=PrvPage

F3=Exi t

F7=PrvTopi c

F11=NxtPage

F5=Exhel p


F8=NxtTopi c

F12=Cancel

Figure 142. Note

## NOTEL (Note List)

The NOTEL tag defines a list of notes within an information region.



### COMPACT

This attribute causes the list to be formatted without a blank line between the list items.

### NOSKIP

This attribute causes the list to format without creating a blank line before the first line of the list.

### SPACE=NO | YES

The SPACE attribute controls the indentation space for the list item. When the

## NOTEL

SPACE attribute is not specified on the LI tag, the SPACE attribute from the NOTEL tag is used to set the indentation space for the nested LI tag *item-text*.

When SPACE=YES, the indentation is set to 3 spaces.

When SPACE=NO (or SPACE is not specified), the indentation is set to 4 spaces.

The SPACE attribute can be used to control the alignment of list items when the first word of some list items is a DBCS word preceded by a shift-out character and the first word of other list items is an SBCS word.

### **INDENT=n**

This attribute specifies that the note list be indented from the current left margin.

### **TYPE= ET | CH | CT | FP | LEF | LI | NT | PT | SAC | TEXT | WASL | WT**

This attribute defines the attribute type to be applied to the note heading. Using a CUA attribute causes the text to appear in the associated color.

When TYPE=TEXT, a non-CUA attribute is generated and you can specify the color, intensity, and highlighting with the COLOR, INTENS, and HILITE attributes. These attributes are not valid for CUA types.

### **COLOR= WHITE | RED | BLUE | GREEN | PINK | YELLOW | TURQ | %varname**

This attribute specifies the color of the note heading. You can define this attribute as a variable name preceded by a percent (%) sign.

### **INTENS= HIGH | LOW | NON | %varname**

This attribute defines the intensity of the note heading. You can define this attribute as a variable name preceded by a percent (%) sign.

### **HILITE= USCORE | BLINK | REVERSE | %varname**

This attribute specifies the extended highlighting attribute of the note heading. You can define this attribute as a variable name preceded by a percent (%) sign.

### **TEXT=alternate-note-heading**

This attribute provides a text string to replace the standard "Notes:" heading.

## Description

The NOTEL tag defines a numbered list of notes. You can code the NOTEL tag anywhere within an INFO tag.

The first line of the note list formats with the word "Notes:" (or its translated equivalent) or the alternate-note-heading.

Use the LI tag to denote each list item. See "LI (List Item)" on page 358 for more information on the LI tag.

## Conditions

- You must code the NOTEL tag within an INFO definition. See "INFO (Information Region)" on page 350 for a complete description of this tag.
- You cannot nest a NOTEL tag within a NOTEL definition.

## Nested Tags

You can code the following tags within a NOTEL definition:

Tag	Name	Usage	Page	Required
LI	List Item	Multiple	358	No
LP	List Part	Multiple	364	No

## Example

The following help panel markup contains a multiple notes. Notice the numbered format for the content of the notes, which is different from the format generated with the NOTE or NT tag. A P tag is nested within the NOTEL definition to provide an additional paragraph of note text. Figure 143 shows the formatted result.

```
<!DOCTYPE DM SYSTEM>

<HELP NAME=notel DEPTH=20>Book / Periodical Search Help
<AREA>
<INFO>
  <P>This entry screen allows you to locate a desired
  book or periodical by entering the title in the entry field.
  <NOTEL>
    <LI>If the item you are trying to locate is not
      in stock and you would like to reserve it, please see the
      librarian at the front desk.
    <LI>If the librarian is not there, please do not yell for help.
  <P>This is a library!
  </NOTEL>
</INFO>
</AREA>
</HELP>
```





Figure 143. NOTEL

## NT (Note)

The NT tag defines a single- or multiple-paragraph note within an information region.



### NOSKIP

This attribute causes the note to be formatted without creating a blank line before the note.

### INDENT=n

This attribute specifies that the note be indented from the current left margin.

### TYPE= ET | CH | CT | FP | LEF | LI | NT | PT | SAC | TEXT | WASL | WT

This attribute defines the attribute type to be applied to the note heading. Using a CUA attribute causes the text to appear in the associated color.

When TYPE=TEXT, a non-CUA attribute is generated and you can specify the color, intensity, and highlighting with the COLOR, INTENS, and HILITE attributes. These attributes are not valid for CUA types.

### COLOR= WHITE | RED | BLUE | GREEN | PINK | YELLOW | TURQ | %varname

This attribute specifies the color of the note heading. You can define this attribute as a variable name preceded by a percent (%) sign.

### INTENS= HIGH | LOW | NON | %varname

This attribute defines the intensity of the note heading. You can define this attribute as a variable name preceded by a percent (%) sign.

### HILITE= USCORE | BLINK | REVERSE | %varname

This attribute specifies the extended highlighting attribute of the note heading. You can define this attribute as a variable name preceded by a percent (%) sign.

### TEXT=alternate-note-heading

This attribute provides a text string to replace the standard "Note:" heading.

**note-text**

This is the text of the note. You can use the P tag to code additional paragraphs of text.

**Description**

The NT tag defines a single- or multiple-paragraph note within an information region. You can code the NT tag anywhere within an INFO definition.

The text of the note formats as an indented block. The block of text is indented seven spaces from the current left margin. The text “Note:” (or its translated equivalent), or the alternate note heading, begins the paragraph. The note aligns with the text of a list item when you code it within a list.

**Conditions**

- The NT tag requires an end tag.
- You must code the NT tag within an INFO definition. See “INFO (Information Region)” on page 350 for a complete description of this tag.
- You can nest text tags such as paragraphs and lists within a note, but you cannot nest NT and NOTE tags.

**Nested Tags**

You can code the following tags within a NT definition:

Tag	Name	Usage	Page	Required
DL	Definition list	Multiple	292	No
FIG	Figure	Multiple	324	No
HP	Highlighted phrase	Multiple	348	No
LINES	Lines	Multiple	360	No
OL	Ordered list	Multiple	404	No
P	Paragraph	Multiple	406	No
PARML	Parameter list	Multiple	424	No
PS	Point-and-Shoot	Multiple	438	No
RP	Reference phrase	Multiple	454	No
SL	Simple list	Multiple	480	No
UL	Unordered list	Multiple	491	No
XMP	Example	Multiple	508	No

**Example**

The following help panel markup contains a multiple-paragraph note. Notice the indented format for the content of the note, which is different from the format generated with the NOTE tag. A P tag is nested within the NT definition to provide an additional paragraph of note text. Figure 144 on page 404 shows the formatted result.

```
<!DOCTYPE DM SYSTEM>

<HELP NAME=nt DEPTH=20>Book / Periodical Search Help
<AREA>
<INFO>
  <P>This entry screen allows you to locate a desired
  book or periodical by entering the title in the entry field.
  <NT>If the item you are trying to locate is not
  in stock and you would like to reserve it, please see the
  librarian at the front desk.
  <P>If the librarian is not there, please do not yell for help.
  This is a library!
  </NT>
</INFO>
</AREA>
</HELP>
```





Figure 144. NT

## OL (Ordered List)

The OL tag defines an ordered list of items within an information region.



### COMPACT

This attribute causes the list to be formatted without a blank line between the list items.

### NOSKIP

This attribute causes the list to format without creating a blank line before the first line of the list.

### SPACE=NO | YES

The SPACE attribute controls the indentation space for the list item. When the

SPACE attribute is not specified on the LI tag, the SPACE attribute from the OL tag is used to set the indentation space for the nested LI tag *item-text*.

When SPACE=YES, the indentation is set to 3 spaces. When SPACE=NO (or SPACE is not specified), the indentation is set to 4 spaces.

The SPACE attribute can be used to control the alignment of list items when the first word of some list items is a DBCS word preceded by a shift-out

**INDENT=n**

This attribute specifies that the list be indented from the current left margin.

**TEXT=OL-heading-text**

This attribute causes the list to format with a heading line containing the *OL-heading-text*.

## Description

The OL tag defines an ordered list of items within an information region. You use ordered lists to indicate a set of sequential items or steps. You can code the OL tag anywhere within an information region.

Ordered lists are formatted as indented lists, with sequential numbers or letters at the left margin of the list items. Nested lists (lists embedded within other lists) indent four spaces to the right of the left margin of the list that contains them.

**Note:** The SPACE attribute does not affect the indentation of nested lists.

The conversion utility adds a blank line before the first item in the list.

Sequential numbers or letters, depending on the nesting level of the ordered list precede the list items. The levels are as follows:

1. Level 1: 1., 2., 3., . . .
2. Level 2: a., b., c., . . .
3. Level 3: 1), 2), 3), . . .
4. Level 4: a), b), c), . . .

Any additional levels repeat the sequence from level 1.

Panels formatted with the DBCS option use uppercase alphabetic characters for the even-numbered nesting levels.

Use the LI tag to denote each list item. See “LI (List Item)” on page 358 for more information on the LI tag.

## Conditions

- The OL tag requires an end tag.
- You must code the OL tag within an INFO definition. See “INFO (Information Region)” on page 350 for a complete description of this tag.

## Nested Tags

You can code the following tags within an OL definition:

Tag	Name	Usage	Page	Required
LI	List item	Multiple	358	No
LP	List part	Multiple	364	No

## Example

The following help panel markup contains two ordered lists and a paragraph. The second ordered list and the paragraph are nested within the first list. Figure 145 shows the formatted result.

```
<!DOCTYPE DM SYSTEM>

<HELP NAME=ol DEPTH=22 WIDTH=60>Widget Assembly Help
<AREA>
<INFO>
  <P>To assemble your new Widget, you should:
  <OL>
    <LI>Attach the gizmo flexure component to the
    main steering mechanism of the doohickey.
    <OL COMPACT>
      <LI>If slot A fits snugly on retaining
      pin B, proceed to step 2.
      <LI>If slot A does not fit snugly on
      retaining pin B, throw the Widget away
      and buy a new one.
    </OL>
    <LI>Use a screwdriver to turn the power drive unit on.
    <LI>Stand back and watch the fun!
    <P>Wake up the kids and call the neighbors, they won't
    want to miss it!
  </OL>
</INFO>
</AREA>
</HELP>
```




Figure 145. Ordered Lists

## P (Paragraph)

The P tag defines a paragraph of text within an information region.

```
—<P—
  ┌──COMPACT──┐ ┌──INTENSE=varname──┐ ┌──INDENT=n──┐ ┌──OFFSET=n──┐
```

**COMPACT**

This attribute causes the paragraph to format without a blank line before the paragraph.

**INTENSE=varname**

This attribute supplies a variable name that must contain a valid value for the INTENS keyword. The entire paragraph is controlled by this value. For example, if the variable contains the value NON, the paragraph will not be visible.

**INDENT=n**

This attribute specifies that the paragraph be indented from the current left margin.

**OFFSET=n**

This attribute specifies that the formatted text following the first line of the paragraph should be indented an additional *n* bytes.

**SPACE= NO | YES**

This attribute is used when processing <P> tags coded within ENTITY definitions. When the ENTITY keyword SPACE is not specified, text following a paragraph tag within the ENTITY definition is processed as coded by default. This may result in unwanted spaces between words in the paragraph, which can be removed by specifying <p space=yes>.

**paragraph-text**

This is the text of the paragraph.

**Description**

The P tag defines a paragraph of text within an information region. You can code the P tag anywhere within an INFO definition.

Each paragraph formats as an unindented block of text. A blank line is added before the paragraph unless the COMPACT attribute is specified.

Paragraphs within a list align with the text of the list item.

**Conditions**

- You must code the P tag within an INFO definition. See “INFO (Information Region)” on page 350 for a complete description of this tag.

**Nested Tags**

You can code the following tags within a P definition:

Tag	Name	Usage	Page	Required
ATTENTION	Attention	Single	226	No
CAUTION	Caution	Single	234	No
HP	Highlighted phrase	Multiple	348	No
PS	Point-and-Shoot	Multiple	438	No
RP	Reference phrase	Multiple	454	No

Tag	Name	Usage	Page	Required
WARNING	Warning	Single	502	No

## Example

The following help panel markup contains four paragraphs. The first three paragraphs are coded within an information region with a defined width of 40, so the text of the paragraphs will be formatted according to this width. The last paragraph is coded within an information region with no defined width, so the paragraph text will be formatted according to the width defined on the HELP tag. Figure 146 shows the formatted result.

```
<!DOCTYPE DM SYSTEM>

<HELP NAME=p DEPTH=22 WIDTH=60>P Tag Hel p
<AREA>
<INFO WIDTH=40>
  <P>Here's a paragraph.
  Lines are formatted to fill the width of the
  information region.
  <P>Here's another paragraph.
  Notice the line skip between the paragraphs.
  <P>Paragraphs are very versatile.
  You can use them within many other tags.
</INFO>
<INFO WIDTH=58>
  <P>The paragraphs above were formatted within an
  information region defined with a width of 40.
  This paragraph is formatted within the width speci fied
  for the panel.
</INFO>
</AREA>
</HELP>
```





Figure 146. Paragraphs

## PANDEF (Panel Default)

The PANDEF tag defines default values for application panels.



### ID=pandef-id

This attribute defines the identifier for the panel default definition. The *pandef-id* is the value you specify with the PANDEF attribute of PANEL tags that refer to the panel default.

The *pandef-id* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

### HELP=help-panel-name | %varname

This attribute specifies the extended (panel help) help panel that displays when the user selects help on an application panel that specifies the panel default.

The *help-panel-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

Specification of the HELP attribute will cause ISPDTLC to generate “.HELP=help-panel-name” (or “.HELP=&varname”) in the )INIT section during panel generation.

ISPF displays this panel when the application user requests help and the cursor is not on a panel field that has its own field-level help specified. This help panel is also displayed when the user requests extended help.

**DEPTH=*n* | FIT**

This attribute specifies a default depth value for an application panel that refers to this panel default. See “PANEL (Panel)” on page 413, for more information.

**WIDTH=*n* | FIT | %varname**

This attribute specifies a default width value for an application panel that refers to this panel default. See “PANEL (Panel)” on page 413, for more information.

**KEYLIST=*key-list-name***

This attribute specifies the name of a key mapping list associated with panels that refer to this panel default. See “KEYL (Key List)” on page 355 for more information.

**KEYLTYPE= PRIVATE | SHARED**

This attribute is used to add the SHARED keyword to the KEYLIST parameter of the )PANEL statement. For more information about the )PANEL statement, refer to the *ISPF Dialog Developer's Guide and Reference*.

**APPLID=*application-id***

This attribute is used to add the application ID to the )PANEL statement. The *application-id* overrides the KEYLAPPL invocation option value.

**CCSID=*n***

This attribute specifies the default CCSID value for an application panel that refers to this panel default. See “PANEL (Panel)” on page 413 for more information.

**WINDOW= YES | NO**

The WINDOW attribute is used to control the generation of the WINDOW keyword on the panel )BODY section. The default is to create the WINDOW keyword. WINDOW=NO should be used when WIDTH=%varname is also used to create a panel.

**WINTITLE=*window-title***

This attribute is used to add a title on the pop-up window border. The attribute value is placed in the ISPF ZWINTTL variable. The maximum length of the *window-title* text is the panel width minus 1.

**APPTITLE=*application-title***

This attribute is used to add a title on the GUI window border. The attribute value is placed in the ISPF ZAPPTTL variable. The maximum length of the *application-title* text is the panel width minus 1.

**PAD= NULLS | USER | char | %varname**

This attribute specifies the pad character for initializing the field. You can define this attribute as a variable name preceded by a “%”.

**PADC= NULLS | USER | char | %varname**

This attribute specifies the conditional padding character to be used for initializing the field. You can define this attribute as a variable name preceded by a “%”.

**OUTLINE= NONE | L | R | O | U | BOX | %varname**

This attribute provides for displaying lines around the field on a DBCS terminal. You can define this attribute as a variable name preceded by a “%”.

**EXPAND=xy**

This attribute adds the EXPAND(xy) attribute to the )BODY section of the panel. If only one character is present, the second character will be set to the same value. If the EXPAND attribute is present with no value specified, the conversion utility will use a character from the range of low-order hex values available for panel attributes. This removes an available character from possible use as a panel attribute and may cause panel formatting errors.

**MERGESAREA= NO | YES**

This attribute controls an additional formatting step for panels with a single scrollable area. If the entire contents of the scrollable area will fit within a standard 24-line panel (allowing 2 lines for the function keys display), and no input or output fields are found in the panel body following the location of the scrollable area, the scrollable area content is moved into the panel body.

**ENTKEYTEXT=enter-key-text**

This attribute is provide the text for the Enter key push button provided on panels displayed in GUI mode. The ENTKEYTEXT attribute causes a statement to be added to the panel )INIT section to set the value of the ZENTKTX variable to the *enter-key-text* value.

**IMAPNAME=image-name | %varname**

This attribute specifies the name of a image to be placed on the panel when it is displayed in GUI mode. The *image-name* is not used when the panel is displayed in host mode.

The *image-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

**IMAPROW=n | %varname**

This attribute specifies the row number for positioning the image. Image position uses an origin based on 0. Therefore, the minimum row value is 0 and the maximum is 61, relating to the description for the DEPTH attribute on the PANEL tag. If a variable name is used, the application must set the variable to a valid value before the panel is displayed. The value specified should be within the actual panel depth for the image to be visible when the panel is displayed.

**IMAPCOL=n | %varname**

This attribute specifies the column number for positioning the image. Image position uses an origin based on 0. Therefore, the minimum column value is 0 and the maximum is 159, relating to the description for the WIDTH attribute on the PANEL tag. If a variable name is used, the application must set the variable to a valid value before the panel is displayed. The value specified should be within the actual panel width for the image to be visible when the panel is displayed.

**TMARGIN=n**

This attribute provides the number of blank lines to format at the top of the panel as a top margin.

**BMARGIN=n**

This attribute provides the number of blank lines to format at the bottom of the panel as a bottom margin.

## Description

The PANDEF tag defines default values for application panels.

## PANDEF

PANEL tags refer to the panel default by specifying the *pandef-id* definition as the PANDEF attribute value. When a PANEL tag refers to a panel default, the values specified by the associated PANDEF tag are used for the panel unless overridden by values specified in the PANEL tag definition.

The PANEL tag can override any of the PANDEF values by specifying that value within its own definition. Thus, it is possible for a PANEL tag to select certain default values from the panel default and override others.

See “PANEL (Panel)” on page 413 for more information.

You can code multiple panel defaults for an application. Each panel default should have a unique *pandef-id*.

### Conditions

- You cannot code the PANDEF tag within any other tag definition.
- You must code the PANDEF tag before you code any PANEL tag that refers to it.
- If both PAD and PADC have been specified, PAD is ignored and PADC is used.
- When a “%varname” notation is found on any of the attributes that allow a variable name, the “%varname” entry must follow the standard naming convention described in “Rules for “%variable” Names” on page 205.
- EXPAND can operate only when there are no trailing attributes on the line to be expanded. Panel lines formatted as part of a horizontal region require the use of attributes for field alignment. Therefore, the EXPAND feature is functional only for panel sections built within a vertical (or default) region that is not part of any horizontal region.

### Nested Tags

None.

### Example

The following source file markup contains two panel default definitions. The application panels *panel1* and *panel2* both refer to the panel default *pandef1*. The panel *panel1* uses all of the defined default values and *panel2* uses only the default DEPTH and WIDTH values, and overrides the default HELP and KEYLIST values by specifying those values in the PANEL definition. The third application panel, *panel3* refers to all of the default values specified in the panel default *pandef2*.

```

<!DOCTYPE DM SYSTEM(
  <!entity sampvar1 system>
  <!entity sampbody system>)>
&sampvar1;

<PANDEF ID=pan1def1 DEPTH=20 WIDTH=76 HELP=hel paaa KEYLIST=keyl xmp>

<PANDEF ID=pan1def2 DEPTH=22 WIDTH=70 HELP=morehlp>

<PANEL NAME=pandef1 PANDEF=pan1def1>First Panel
&sampbody;
</PANEL>

<PANEL NAME=pandef2 PANDEF=pan1def1
  HELP=morehlp KEYLIST=keyl tbl >Second Panel
&sampbody;
</PANEL>

<PANEL NAME=pandef3 PANDEF=pan1def2>Third Panel
&sampbody;
</PANEL>


<HELP NAME=hel paaa>Hel p panel "hel paaa"
<AREA>
<INFO WIDTH=48>
<P>This is PANDEF hel p panel "hel paaa"
</INFO>
</AREA>
</HELP>

<HELP NAME=morehlp>Hel p panel "morehlp"
<AREA>
<INFO WIDTH=48>
<P>This is PANDEF hel p panel "morehlp"
</INFO>
</AREA>
</HELP>


```

## PANEL (Panel)

The PANEL tag defines an application panel.




## PANEL



### KEYLIST Options:



### IMAP Options:



### NAME=panel-name

This attribute specifies the name of the panel. The *panel-name* is used in the ISPF DISPLAY or TBDISPL service call. The *panel-name* is also used as the panel ID, which the user can display. The *panel-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

If you specify `NAME=*`, the *panel-name* is set to the input DTL source member name. If multiple dialog element definitions have been combined within a single source file, then this notation should be used for only one dialog element definition within the file. See “Dialog Elements” on page 5 for a description of dialog element types created by the conversion utility.

The *panel-name* is used to build the panel output file name in which the conversion utility stores the converted panel. The default is “userid.PANELS(*panel-name*)”.

You can specify the output panel library file name of your choice on the invocation panel for the conversion utility, or in the conversion utility profile as DDname DTLPAN for batch (or command syntax invocation) processing.

If the SCRIPT option has been specified, the *panel-name* is also used to build the file name in which the conversion utility stores the image of the panel. The default name is “userid.SCRIPT(*panel-name*)”.

You can specify the output SCRIPT library file name of your choice on the invocation panel for the conversion utility, or in the conversion utility profile as DDname DTLSCR for batch (or command syntax invocation) processing.

See Chapter 10, “Using the Conversion Utility,” on page 171 for complete information on invocation syntax.

#### **HELP=help-panel-name | %varname**

This attribute specifies the name of a defined extended (panel help) help panel. It identifies the help text that is associated with the panel definition.

The *help-panel-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

Specification of the HELP attribute will cause ISPDTLC to generate “.HELP=help-panel-name” (or “.HELP=&varname”) in the )INIT section during panel generation.

ISPF displays this panel when the application user requests help and the cursor is not on a panel field that has its own field-level help specified. This help panel is also displayed when the user requests extended help.

#### **PANDEF=pandef-id**

This attribute specifies a defined panel default. The *pandef-id* value is the identifier specified on the PANDEF tag. You can override any of the defaults from this PANDEF tag by specifying that attribute on the PANEL tag. See “PANDEF (Panel Default)” on page 409 for information about defining panel defaults.

#### **DEPTH=22 | n | FIT**

This attribute defines the depth of the panel. The default depth is 22 when WINDOW=YES or 24 when WINDOW=NO. When the panel is displayed in a pop-up, ISPF adds two lines to the DEPTH value you specify to accommodate the borders at the top and bottom of the pop-up.

The value specified for the depth is the depth of the entire panel including the panel title, the action bar, the function key area, the message area, any scrollable areas, and the command area.

The maximum depth is 62 and the minimum depth is 5. If the DEPTH value is less than the minimum value allowed or exceeds the maximum value allowed, the conversion utility issues a warning message and sets the depth to the default.

The depth defined should be large enough to include all formatted text and input/output fields as well as the function key area, message area, any scrollable areas, and the command area. If the depth specified is not large enough to include these panel elements, ISPF will overlay with the function keys if the function key display is on or with the message area if the message is not displayed in a pop-up.

If DEPTH=FIT, The conversion utility will format the panel using a depth of 22. When formatting is completed the DEPTH value will be reset to the minimum depth used or to 5 if the formatted panel contains less than 5 lines.

If the DEPTH value exceeds the maximum allowed to display the panel on the device, ISPF issues an error message at run time.

**WIDTH=76 | n | FIT | %varname**

This attribute defines the width (in characters) of the panel. The default width is 76 when WINDOW=YES or 80 when WINDOW=NO. When the panel is displayed in a pop-up, ISPF adds 4 to the WIDTH value you specify to accommodate the left and right borders of the pop-up.

The value specified for the width is the width of the entire panel (or region), including the margins.

The maximum width is 160 and the minimum width is 16.

Because there is a minimum margin width of 1 character on each side of the panel text, the effective width for text for a panel defined with WIDTH=76 is a maximum of 74 characters.

If the WIDTH value fined

**KEYLTYPE=PRIVATE | SHARED**

This attribute is used to add the SHARED keyword to the KEYLIST parameter of the )PANEL statement. For information about the )PANEL statement, refer to the *ISPF Dialog Developer's Guide and Reference*. The KEYLTYPE attribute is ignored if you have not provided the KEYLIST attribute as part of the PANEL tag definition or as part of an associated PANDEF tag definition.

**APPLID=application-id**

This attribute is used to add the application ID to the )PANEL statement. The *application-id* overrides the KEYLAPPL invocation option value. The APPLID attribute is ignored if you have not provided the KEYLIST attribute as part of the PANEL tag definition or as part of an associated PANDEF tag definition.

**CURSOR=cursor-field**

This attribute, together with CSRINDEX and CSRPOS, controls the initial placement of the cursor when the ISPF displays the panel. You can specify *cursor-field* as the value of:

- The NAME attribute of a CHOICE tag (for multiple-choice selection fields)
- The DATAVAR attribute of the CHOFLD tag.
- The DATAVAR attribute of a DTAFLD tag
- The DATAVAR attribute of a LSTCOL tag
- The NAME attribute of a SELFLD tag (for single-choice selection fields).

The cursor can also be placed on the command area, when it is defined for a panel with the CMDAREA tag. Use the ISPF-reserved name *cmdarea* as the value for *cursor-field* to place the cursor on the command area.

**CSRINDEX=index-value**

This attribute, together with CURSOR and CSRPOS, controls the placement of the cursor when ISPF displays a table display panel. This attribute may be specified only when the CURSOR attribute refers to a list column.

CSRINDEX specifies the row in the )MODEL section where ISPF places the cursor when it displays the panel.

**CSRPOS=position-value**

This attribute, together with CURSOR and CSRINDEX, controls the placement of the cursor when ISPF displays the panel. This attribute may be specified only when the CURSOR attribute refers to a data field, list column, or the command area.

CSRPOS specifies the number of byte positions into the entry field that ISPF places the cursor when it displays the panel.

The first position of a field is denoted by 1. The maximum position that you can specify is the length of the underlying data.

If the value specified for this attribute is not valid, the default (1) is used.

**CCSID=n**

This attribute specifies the coded-character-set identifier as defined by the Character Data Representation Architecture. CCSID should be entered as a five-position numeric value. For more information about using the CCSID attribute, refer to the *ISPF Dialog Developer's Guide and Reference*.

**MENU**

This attribute specifies that the panel will be an ISPF menu selection or edit model selection panel. This type of panel does not allow a table display.

## PANEL

### PRIME

This attribute is used together with MENU to specify a primary option menu.

### TUTOR

This attribute specifies that the panel title be formatted with the word *Tutorial* (or its translated equivalent) on each end of the title line, similar to ISPF tutorial panels.

### WINDOW=YES | NO

The WINDOW attribute is used to control the generation of the WINDOW keyword on the panel )BODY section. The default is to create the WINDOW keyword. WINDOW=NO should be used when WIDTH=%varname is also used to create a panel.

### WINTITLE=window-title

This attribute is used to add a title on the pop-up window border. The attribute value is placed in the ISPF ZWINTTL variable. The maximum length of the *window-title* text is the panel width minus 1.

### APTITLE=application-title

This attribute is used to add a title on the GUI window border. The attribute value is placed in the ISPF ZAPPTTL variable. The maximum length of the *application-title* text is the panel width minus 1.

### PAD=NULLS | USER | char | %varname

This attribute specifies the pad character for initializing the field. You can define this attribute as a variable name preceded by a "%".

### PADC= NULLS | USER | char | %varname

This attribute specifies the conditional padding character to be used for initializing the field. You can define this attribute as a variable name preceded by a "%".

### OUTLINE=NONE | L | R | O | U | BOX | %varname

This attribute provides for displaying lines around the field on a DBCS terminal. You can define this attribute as a variable name preceded by a "%".

### EXPAND=xy

This attribute adds the EXPAND(xy) attribute to the )BODY section of the panel. If only one character is present, the second character will be set to the same value. If the EXPAND attribute is present with no value specified, the conversion utility will use a character from the range of low-order hex values available for panel attributes. This removes an available character from possible use as a panel attribute and may cause panel formatting errors.

### MSGLINE=YES | NO

This attribute controls the provision for a long message line in the generated panel. When MSGLINE=NO, the blank line for the long message is not added to the panel )BODY section. It is the panel designer's responsibility to ensure that critical panel areas are positioned so that the long message will not inhibit use of the resulting panel.

### TITLINE=YES | NO

This attribute controls the generation of the panel title line. When TITLINE=NO, the panel title is not added to the generated panel. This option is provided for applications that format a panel title as part of a dynamic area. It is the panel designer's responsibility to ensure that the resulting panel meets CUA requirements.

### CMDLINE=YES | NO

This attribute controls the automatic generation of the command area on

option menu panels and table display panels. When `CMDLINE=NO`, the command area is not automatically added to panels that do not include a `CMDAREA` tag within the panel definition.

#### **ATTRUSE=NO | YES | ALL**

This attribute controls the assignment of panel attributes within the range of `x'01'` through `x'3F'`. When `ATTRUSE=YES` or `ATTRUSE=ALL`, attributes for use in dynamic areas supplied by the `ATTR` tag can be assigned low-order hex values normally used by the conversion utility.

When `ATTRUSE=YES`, all of the attributes specified by the `ATTR` tag plus the required attributes used by the conversion utility must fit in the defined range of `x'01'` through `x'2F'`.

When `ATTRUSE=ALL`, all of the attributes specified by the `ATTR` tag plus the required attributes used by the conversion utility must fit in the defined range of `x'01'` through `x'3F'`.

#### **ENDATTR=DEFAULT | TEXT**

This attribute specifies that when the last attribute on any panel body line is “normal text” (CUA), it will be replaced by the default “text” (ISPF) attribute. The effect is to force any text on subsequent lines not preceded by another attribute from the normal text color to blue.

#### **TYPE=BOTH | GUI | NOGUI**

This attribute specifies that the panel will be used for either host display, GUI display, or both. When `NOGUI` is specified, for example, the panel language control statements that enable check boxes, radio buttons, list boxes, drop-down lists, and combination boxes are not added to the generated panel. When `GUI` is specified, `SELFLD` tag formatting for list boxes, drop-down lists, and combination boxes results in only 1 line in the panel `)BODY` section; the choice list is displayed as a GUI function.

#### **SMSG=short-msg-fieldname**

This attribute provides the name of the field where the short message is to be placed. The *short-msg-fieldname* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

#### **LMSG=long-msg-fieldname**

This attribute provides the name of the field where the long message is to be placed. The *long-msg-fieldname* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

#### **ASIS**

This attribute specifies that the command and long message fields are to appear on the display as specified in the generated panel definition. When `ASIS` is specified, any user request specified on the Settings panel, or by setting the system variable `ZPLACE` is ignored.

#### **ACTBAR**

This attribute causes the action bar information for the panel to be generated, overriding the `NOACTBAR` invocation option.

#### **MERGESAREA=NO | YES**

This attribute controls an additional formatting step for panels with a single scrollable area. If the entire contents of the scrollable area will fit within a standard 24-line panel (allowing 2 lines for the function keys display), and no input or output fields are found in the panel body following the location of the scrollable area, the scrollable area content is moved into the panel body.

## PANEL

### **PANELSTMT=**YES | NO

This attribute controls the creation of the )PANEL statement. You can use this attribute to create a panel without keylist interaction.

### **ENTKEYTEXT=**enter-key-text

This attribute is provide the text for the Enter key push button provided on panels displayed in GUI mode. The ENTKEYTEXT attribute causes a statement to be added to the panel )INIT section to set the value of the ZENTKTEXT variable to the *enter-key-text* value.

### **IMAPNAME=**image-name | %varname

This attribute specifies the name of a image to be placed on the panel when it is displayed in GUI mode. The *image-name* is not used when the panel is displayed in host mode.

The *image-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

### **IMAPROW=**n | %varname

This attribute specifies the row number for positioning the image. Image position uses an origin based on 0. Therefore, the minimum row value is 0 and the maximum is 61, based on the above description for the DEPTH attribute. If a variable name is used, the application must set the variable to a valid value before the panel is displayed. The value specified should be within the actual panel depth for the image to be visible when the panel is displayed.

### **IMAPCOL=**n | %varname

This attribute specifies the column number for positioning the image. Image position uses an origin based on 0. Therefore, the minimum row value is 0 and the maximum is 159, based on the above description for the WIDTH attribute. If a variable name is used, the application must set the variable to a valid value before the panel is displayed. The value specified should be within the actual panel width for the image to be visible when the panel is displayed.

### **TMARGIN=**n

This attribute provides the number of blank lines to format at the top of the panel as a top margin.

### **BMARGIN=**n

This attribute provides the number of blank lines to format at the bottom of the panel as a bottom margin.

### **ERRORCHECK=**NO | YES

This attribute specifies whether error checking logic is added to the end of the )PROC section. The extra logic prevents exit from the panel if any errors are present.

```
IF (.MSG ^= ' ')
  &ZVERB = ' '
  .RESP = ENTER
```

### **ZUP=**zup-id

This attribute provides the name of the Tutorial panel to be assigned to the ZUP variable. It is valid only when the TUTOR attribute has been specified.

### **ZCONT=**zcontid

This attribute provides the name of the Tutorial panel to be assigned to the ZCONT variable. It is valid only when the TUTOR attribute has been specified.

### **AUTONRET=**NO | YES

This attribute specifies whether the .NRET = OFF panel statement is added to

the )PROC section as part of the AUTOTYPE logic. When YES is specified, '.NRET = OFF' is the first AUTOTYPE panel logic statement created in the )PROC section.

#### AUTOTCMD=NO | YES | PROC

This attribute specifies whether the command field will be refreshed during AUTOTYPE processing. When YES is specified, the command field name (normally ZCMD) is included with the AUTOTYPE variables added to the REFRESH statement in the )REINIT section of the panel. When PROC is specified, a REFRESH statement that references the command field name is included in the )PROC section of the panel. The REFRESH statement is inserted after the PANEXIT statement that invokes the AUTOTYPE panel exit.

#### panel-title-text

This is the text of the panel title.

Panel titles should be used when an application can display more than one panel. The *panel-title-text* is centered within the width defined for the panel in accordance with CUA rules. If the *panel-title-text* is wider than the WIDTH specified, the title is truncated from the right and an ellipsis (...) is appended. Two lines are reserved for the panel title and for a blank line between the panel title and the rest of the panel body.

## Description

The PANEL tag defines an application panel.

Tags coded within a PANEL definition (between the PANEL start tag and end tag) define the content of the panel.

## Conditions

- When the MENU attribute is specified, the LSTFLD tag cannot be nested under the PANEL tag.
- The PANEL tag requires an end tag.
- You cannot code a PANEL tag within any other tag definition.
- The PANEL definition must contain at least one of the following tags:
  - BOTINST (See “BOTINST (Bottom Instruction)” on page 232)
  - DA (See “DA (Dynamic Area)” on page 280)
  - DTAFLD (See “DTAFLD (Data Field)” on page 306)
  - GA (See “GA (Graphic Area)” on page 327)
  - INFO (See “INFO (Information Region)” on page 350)
  - LSTFLD (See “LSTFLD (List Field)” on page 377)
  - PNLINST (See “PNLINST (Panel Instruction)” on page 436)
  - SELFLD (See “SELFLD (Selection Field)” on page 464)
  - TOPINST (See “TOPINST (Top Instruction)” on page 488)
- If both PAD and PADC have been specified, PAD is ignored and PADC is used.
- When a “%varname” notation is found on any of the attributes that allow a variable name, the “%varname” entry must follow the standard naming convention described in “Rules for “%variable” Names” on page 205.
- EXPAND can operate only when there are no trailing attributes on the line to be expanded. Panel lines formatted as part of a horizontal region require the use of attributes for field alignment. Therefore, the EXPAND feature is functional only for panel sections built with a vertical (or default) region that is not part of any horizontal region.

## PANEL

### Nested Tags

You can code the following tags within a PANEL definition:

Tag	Name	Usage	Page	Required
AB	Action bar	Single	206	No
AREA	Area	Multiple	217	No
BOTINST	Bottom instruction	Multiple	232	No
CMDAREA	Command area	Single	267	No
COMMENT	Comment	Multiple	275	No
DA	Dynamic area	Multiple	280	No
DIVIDER	Area divider	Multiple	289	No
DTACOL	Data column	Multiple	300	No
DTAFLD	Data field	Multiple	306	No
GA	Graphic area	Single	327	No
GENERATE	Generate	Multiple	330	No
GRPHDR	Group header	Multiple	332	No
HP	Highlighted phrase	Multiple	348	No
INFO	Information region	Multiple	350	No
LSTFLD *	List field	Single	377	No
PNLINST	Panel Instruction	Multiple	436	No
REGION	Region	Multiple	446	No
SELFLD	Selection field	Multiple	464	No
SOURCE	Source	Multiple	482	No
TEXTLINE	Text Line	Single	485	No
TOPINST	Top instruction	Multiple	488	No

**Note:** Tags marked with \* are not valid within an ISPF selection menu panel.

### Example

The following application panel markup contains an action bar, a top instruction, two selection fields, and a command area. The PANEL KEYLIST attribute specifies a key mapping list, which is displayed below the command area. Figure 147 on page 424 shows the formatted result.

```

<!DOCTYPE DM SYSTEM>

<VARCLASS NAME=selcls TYPE='CHAR 2'>
<VARLIST>
  <VARDCL NAME=loc VARCLASS=selcls>
  <VARDCL NAME=mode VARCLASS=selcls>
</VARLIST>

<PANEL NAME=panel HELP=trvlhlp KEYLIST=keylxmlp
  DEPTH=22 WIDTH=60>Dream Vacation Guide
<AB>
  <ABC>File
    <PDC>Add Entry
      <ACTION RUN=add>
    <PDC>Delete Entry
      <ACTION RUN=delete>
    <PDC>Update Entry
      <ACTION RUN=update>
    <PDC>Exit
      <ACTION RUN=exit>
  <ABC>Help
    <PDC>Extended Help...
      <ACTION RUN=exhelp>
    <PDC>Keys Help...
      <ACTION RUN=keyshelp>
</AB>
<TOPINST>Choose one of the following exotic locations and
your preferred mode of travel, then press Enter.
<AREA>
  <REGION DIR=horiz>
  <SELFLD NAME=loc PMTWIDTH=23 SELWIDTH=25>Exotic Location:
    <CHOICE>Athens, GA
    <CHOICE>Berlin, CT
    <CHOICE>Cairo, IL
    <CHOICE>Lizard Lick, NC
    <CHOICE>Paris, TX
    <CHOICE>Rome, NY
    <CHOICE>Venice, FL
  </SELFLD>
  <DIVIDER>
  <SELFLD NAME=mode PMTWIDTH=25 SELWIDTH=25>Travel Mode:
    <CHOICE>Boxcar
    <CHOICE>Hi tchhi ke
    <CHOICE>Mule
  </SELFLD>
  </REGION>
</AREA>
<CMDAREA>
</PANEL>

<HELP NAME=trvlhlp>Sample help panel "trvlhlp"
<AREA>
<INFO WIDTH=48>
<P>This is help panel "trvlhlp"
</INFO>
</AREA>
</HELP>

```





Figure 147. Application Panel

## PARML (Parameter List)

The PARML tag defines a parameter list within an information region.



### **TSIZE=10 | S1 S2... Sn**

This attribute defines the space allocated for the parameter term. The default is 10 characters. The minimum TSIZE value is 0 and the maximum is 40.

When multiple TSIZE values are specified, a PT tag must be coded for each value. The sizes are applied to the PT tags in the order the tags are encountered in the DTL source file.

### **BREAK=ALL | FIT | NONE**

This attribute controls the formatting of the parameter terms and descriptions. If BREAK=ALL (the default), every description is on the line below the term. If BREAK=FIT, the description is on the line below the term if the term is longer than the TSIZE value. If BREAK=NONE, the term is on the same line as the description, spilling into the description area if the length exceeds the TSIZE value.

**COMPACT**

This attribute causes the conversion utility to format the list without a blank line between the items.

**SKIP**

This attribute causes a blank line to be formatted before the first parameter term when COMPACT is also specified.

**INDENT=n**

This attribute specifies that the parameter list be indented from the current left margin.

**FORMAT=START | CENTER | END**

This attribute specifies the placement of the PT tag text within the space specified by TSIZE. The PARML tag FORMAT setting applies to all of the PT tags within the parameter list.

**DIVEND=NO | YES**

This attribute specifies whether a divider character will be formatted following the PD tag text. When DIVEND=YES, the formatting width of the PD text is reduced to allow space for the divider character.

**SPLIT=NO | YES**

This attribute controls the format of the last PT tag in a multiple PT tag group. It is used only when BREAK=ALL or when BREAK=FIT and the PT tag text length exceeds the TSIZE value. When SPLIT=YES, the text following the last PT tag in the PT group (typically one or two dashes) is placed in front of the first line of the formatted PD tag text. The SPLIT setting on a PARML tag applies to all of the PT tag groups within the parameter list.

## Description

The PARML tag defines a parameter list within an information region.

Parameter lists are similar to definition lists. They involve three tags: PARML (parameter list) and a matching end tag, PT (parameter term), and PD (parameter description). As in definition lists, the term tag defines a term, and the definition tag defines the description associated with the term. The PD tag must immediately follow the PT tag that it is associated with.

Parameter lists can occur anywhere in an information region; you can nest them within other lists, and you can nest other lists within parameter lists.

## Conditions

- The PARML tag requires an end tag.
- You must code the PARML tag within an INFO definition. See “INFO (Information Region)” on page 350 for a complete description of this tag.

## Nested Tags

You can code the following tags within a PARML definition:

Tag	Name	Usage	Page	Required
PD	Parameter description	Multiple	427	No
PLDIV	Parameter List Divider	Multiple	434	No
PT	Parameter term	Multiple	441	No
PTDIV	Parameter Term Divider	Multiple	443	No

## Example

The following help panel markup contains two parameter lists. The second parameter list is nested within the second parameter description of the first list. Figure 148 shows the formatted result.

```
<!DOCTYPE DM SYSTEM>

<HELP NAME=parmls DEPTH=22>Part Number Code Help
<AREA>
<INFO>
  <P>Valid part numbers consist of a three-digit
  number followed by a 2-character suffix.
  <PARML TSIZE=6>
    <PT>123
    <PD>The first three digits represent
    the lot number of the part.
    <PT>AA
    <PD>The 2-character suffix represents the
    department the part originated from.
    The valid suffixes are:
    <PARML BREAK=none COMPACT>
      <PT>T0
      <PD>Tools
      <PT>EL
      <PD>Electrical
      <PT>ME
      <PD>Mechanical
    </PARML>
  </PARML>
</INFO>
</AREA>
</HELP>
```




Figure 148. Parameter List

## PD (Parameter Description)

The PD tag defines a parameter description in a parameter list.

```
<PD> _____
      | parameter-description | | </PD> |
```

### parameter-description

This is the text of the parameter description.

## Description

The PD tag defines a parameter description in a parameter list.

## Conditions

- You must code the PD tag within a PARML definition. See “PARML (Parameter List)” on page 424 for a complete description of this tag.
- Each PD tag must be paired with a PT tag. You can specify only one PD tag for each PT tag within a parameter list. The PD tag must immediately follow the PT tag it is associated with.

## Nested Tags

You can code the following tags within a PD definition:

Tag	Name	Usage	Page	Required
DL	Definition list	Multiple	292	No
FIG	Figure	Multiple	324	No
HP	Highlighted phrase	Multiple	348	No
LINES	Lines	Multiple	360	No
NOTE	Note	Multiple	396	No
NOTEL	Note List	Multiple	399	No
NT	Note	Multiple	402	No
OL	Ordered list	Multiple	404	No
P	Paragraph	Multiple	406	No
PARML	Parameter list	Multiple	424	No
PS	Point-and-Shoot	Multiple	438	No
RP	Reference phrase	Multiple	454	No
SL	Simple list	Multiple	480	No
UL	Unordered list	Multiple	491	No
XMP	Example	Multiple	508	No

## Example

The following help panel markup contains a parameter list with three PD definitions. Figure 149 on page 428 shows the formatted result.

```

<!DOCTYPE DM SYSTEM>

<HELP NAME=pd DEPTH=20>Help for Ordering Parts
<AREA>
<INFO>
  <P>Use one of the following codes when ordering
  a part number from inventory:
  <PARML TSIZE=5>
    <PT>ST
      <PD>Indicates that the part
      order is for stock replenishment.
    <PT>CU
      <PD>Indicates that the part
      order is for immediate customer shipment.
    <PT>EL
      <PD>Indicates that the part
      order is for shipment to an external location.
  </PARML>
</INFO>
</AREA>
</HELP>

```






Figure 149. Parameter Descriptions

## PDC (Pull-Down Choice)

The PDC tag defines a pull-down choice for an action bar pull-down.





**HELP=**NO | YES | **help-panel-name** | \***help-message-id** | %**varname** | \*%**varname**

This attribute specifies the help action taken when the user requests help for a pull-down choice selection.

When HELP=YES, control is returned to the application. You can specify either a help panel or a message identifier. If a message identifier is used, it must be prefixed with an asterisk (\*).

The help attribute value can be specified as a variable name. When %**varname** is coded, a panel variable name is created. When \*%**varname** is coded, a message variable name is created.

If the user requests help on a choice and no help is defined, the extended help panel is displayed. If an extended help panel is not defined for the panel, the application or ISPF tutorial is invoked.

The *help-panel-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

See “HELP (Help Panel)” on page 335 for information about creating help panels. For information about creating messages, see “MSG (Message)” on page 390.

**Note:** This attribute is valid only when the SELFLD tag has been specified with TYPE=MULTI.

**UNAVAIL=***unavail-variable-name*

This attribute specifies the name of a variable that is used by ISPF to determine the availability of the pull-down choice. When the variable value is 1, the pull-down choice is unavailable.

The *unavail-variable-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

**CHECKVAR=***check-variable-name*

This attribute specifies a variable whose value indicates whether or not the pull-down choice is preselected when the pull-down is displayed. If the value of the variable is equivalent to the *match-string* you specify with the MATCH attribute, the pull-down choice appears preselected. Otherwise, it does not. The *check-variable-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

**Note:** Unlike selection fields, ISPF does not reset the *check-variable-name* to indicate the pull-down choice the user selects. Therefore, you should code the SETVAR attribute in an ACTION tag associated with the pull-down choices when the application needs to know which pull-down choice was selected.

**MATCH=**1 | **match-string**

This attribute defines the value that causes the pull-down choice to be

preselected. The value of variable specified by the CHECKVAR attribute is compared to the *match-string* value, and if they are equal, the pull-down choice appears preselected.

**ACC1=key1**

This attribute specifies an accelerator key to be used when operating in GUI mode. The *key1* value can be Ctrl, Shift, Alt, Insert, Delete, Backspace, F1–F12, A–Z, a–z, or 0–9.

**ACC2=key2**

This attribute specifies an accelerator key to be used when operating in GUI mode. The *key2* value can be Ctrl, Shift, Alt, Insert, Delete, Backspace, F1–F12, A–Z, a–z, or 0–9.

**ACC3=key3**

This attribute specifies an accelerator key to be used when operating in GUI mode. The *key3* value can be Ctrl, Shift, Alt, Insert, Delete, Backspace, F1–F12, A–Z, a–z, or 0–9.

**pull-down-description-text**

This is the text for the pull-down choice. The maximum length of the text is 64 bytes.

Each *pull-down-description-text* is prefixed with a sequential number beginning with 1 to allow selection by number.

## Description

The PDC tag defines a pull-down choice for an action bar pull-down. If you do not code any PDC tags within an ABC tag, that action bar choice will not appear on the action bar.

To provide for a pull-down selection, an input field is generated prior to the first *pull-down-description-text* that allows entry of the number of the selected pull-down choice. Since field names are being generated, the application developer should not use field names beginning with Z.

Up to three accelerator keys may be specified. ISPD TLC checks for valid combinations of ACCn attributes. Invalid combinations are reset to blank and a warning message is issued.

- Insert, Delete, Backspace, and Fn are valid single keys.
- Only one ACCn can be a function key.
- SHIFT plus A–Z, a–z, or 0–9 is not valid.
- When three keys are specified, two must be CTRL, ALT, or SHIFT.
- When two keys are specified, one must be CTRL, ALT, or SHIFT.
- No two keys can have the same value.
- The combined length of the key values including any connecting “+” characters must be 30 bytes or less.
- An accelerator key combination can be used only one time on a panel.

## Conditions

- You must code the PDC tag within an ABC definition. See “ABC (Action Bar Choice)” on page 208 for a complete description of this tag.
- The maximum number of pull-down choices that will be generated is 60. However, the depth specified on the enclosing PANEL tag can further reduce this maximum number.

## Nested Tags

You can code the following tags within a PDC definition:

Tag	Name	Usage	Page	Required
ACTION	Action	Multiple	211	No
COMMENT	Comment	Multiple	275	No
M	Mnemonic	Single	388	No
SOURCE	Source	Multiple	482	No

## Example

The following application panel markup produces the action bar and pull-down shown in Figure 150 on page 432.

In this example, when the action bar choice **Search** is chosen, the variable *whchsrch* is tested to see if one of the pull-down choices should be preselected. If *whchsrch*=1 then the pull-down choice **Search on name** is preselected with a 1 in the pull-down selection entry field. If *whchsrch*=2 then the pull-down choice **Search on card number** is preselected with a 2 in the pull-down selection entry field. If *whchsrch* is not equal to 1 or 2, then neither pull-down choice is preselected. The example shows the **Search on name** choice preselected. If *srch2*=1, then the UNAVAIL attribute on the pull-down choice Search on card number would cause that choice to be unavailable. The example shows the result.

```
<!DOCTYPE DM SYSTEM(
  <!entity sampvar1 system>
  <!entity sampbody system>)>
&sampvar1;

<PANEL NAME=pc2 KEYLIST=keyl xmp>Library Card Registration
<AB>
<ABC>File
  <PDC>Add Entry
    <ACTION RUN=add>
  <PDC>Delete Entry
    <ACTION RUN=delete>
  <PDC>Update Entry
    <ACTION RUN=update>
  <PDC>Exit
    <ACTION RUN=exit>
<ABC>Search
  <PDC CHECKVAR=whchsrch MATCH=1 UNAVAIL=srch1>
    ACC1=ctrl ACC2=alt ACC3=n>Search on name
    <ACTION SETVAR=whchsrch VALUE=1>
    <ACTION RUN=search>
  <PDC CHECKVAR=whchsrch MATCH=2 UNAVAIL=srch2
    ACC1=ctrl ACC2=alt ACC3=c>Search on card number
    <ACTION SETVAR=whchsrch VALUE=2>
    <ACTION RUN=search>
<ABC>Help
  <PDC>Extended Help...
    <ACTION RUN=exhelp>
  <PDC>Keys Help...
    <ACTION RUN=keyshelp>
</AB>
&sampbody;
</PANEL>
```



```

<!DOCTYPE DM SYSTEM(
  <!entity sampvar1 sysem>
  <!entity sampbody system>)>
&sampvar1;

<PANEL NAME=pdsep KEYLIST=keyl xmp>Library Card Registration
<AB>
<ABC>File
  <PDC>Add Entry
    <ACTION RUN=add>
  <PDC>Delete Entry
    <ACTION RUN=delete>
<PDC>Update Entry
  <ACTION RUN=update>
<PDSEP>
<PDC>Exit
  <ACTION RUN=exit>
BC>Search
<PDC CHECKVAR=whchsrch MATCH=1 UNAVAIL=srch1
  acc1=ctrl acc2=alt acc3=n >Search on name
  <ACTION SETVAR=whchsrch VALUE=1>
  <ACTION RUN=search>
<PDC CHECKVAR=whchsrch MATCH=2 UNAVAIL=srch2
  acc1=ctrl acc2=alt acc3=c>Search on card number
  <ACTION SETVAR=whchsrch VALUE=2>
  <ACTION RUN=search>
<ABC>Help
  <PDC>Extended Help...
  <ACTION RUN=exhelp>
  <PDC>Keys Help...
  <ACTION RUN=keyshelp>
</AB>
&sampbody;
</PANEL>

```





Figure 151. Pull-Down Separator

## PLDIV (Parameter List Divider)

The Parameter List Divider tag creates a blank or visible divider within the text portion of a parameter list.



### TYPE=NONE | SOLID | DASH | TEXT

This attribute specifies the type of parameter list divider line.

The default value is NONE, which produces a blank line. You must specify SOLID, DASH, or TEXT to produce a visible divider line. When the GRAPHIC invocation option is specified, SOLID produces a solid line for host display and DASH produces a dashed line. When NOGRAPHIC is specified or the panel is displayed in GUI mode, both SOLID and DASH produce a dashed line.

### GAP=YES | NO

When GAP=NO, the divider line completely crosses from one side of the text area to the other. When GAP=YES, a 1-character gap remains at each end of the divider line.

### GUTTER=1 | n

This attribute specifies the total width of the parm list divider. If the GUTTER value is an even number, the conversion utility increases the number by 1 so that the divider is centered within the defined width.

The minimum GUTTER value, and the default, is 1.

### FORMAT=START | CENTER | END

This attribute specifies the position of the divider text within the width of the divider line.

### divider-text

This is the text of the area divider line.

## Description

The PLDIV tag creates a blank or solid divider within the text portion of an application panel. A horizontally formatted visible divider is created when you specify the TYPE attribute value as SOLID or DASH. When the GRAPHIC invocation option is specified, SOLID produces a solid line for host display and DASH produces a dashed line. When NOGRAPHIC is specified or the panel is displayed in GUI mode, both SOLID and DASH produce a dashed line.

The divider line can be formatted with descriptive text. When this feature is used, the FORMAT attribute must be specified. If FORMAT is not specified, the tag text is ignored. You control the text padding with the TYPE attribute. If TYPE=TEXT, the *divider-text* is padded with blanks. When TYPE=SOLID or TYPE=DASH, the *divider-text* is padded with the specified character.

## Conditions

- You must code the PLDIV tag within a PARML tag definition.

## Nested Tags

You can code the following tags within a PLDIV definition:

Tag	Name	Usage	Page	Required
HP	Highlighted phrase	Multiple	348	No

## Example

The following example illustrates the use of the PLDIV tag. Figure 152 on page 436 shows the formatted result.

```
<!DOCTYPE DM SYSTEM>

<HELP NAME=pldiv DEPTH=22 WIDTH=60>Part Number Code Help
<AREA>
<INFO>
  <P>Valid part numbers consist of a three-digit
  number followed by a 2-character suffix.
  <DIVIDER>
  <PARML TSIZE=6 compact>
    <PLDIV TYPE=solid>
      <PT>123
      <PD>The first three digits represent
      the lot number of the part.
    <PLDIV TYPE=solid>
      <PT>AA
      <PD>The 2-character suffix represents the
      department the part originated from.
      The valid suffixes are:
      <PARML BREAK=none COMPACT SKIP>
        <PT>TO
        <PD>Tools
        <PT>EL
        <PD>Electrical
        <PT>ME
        <PD>Mechanical
      </PARML>
    </PARML>
  </INFO>
</AREA>
</HELP>
```





Figure 152. Parameter List Divider

## PNLINST (Panel Instruction)

The PNLINST tag defines panel instructions for an application panel.



### COMPACT

This attribute causes the panel instruction to format without a blank line before the text.

### instruction-text

This is the text of the panel instruction. The *instruction-text* must fit in the remaining panel depth.

## Description

The PNLINST tag defines panel instructions for an application panel. The *instruction-text* formats as a paragraph based on the width of the application panel, area, or region. You can code multiple paragraphs of instruction text by using a new panel instruction tag for each new paragraph.

If the COMPACT attribute is not specified, the conversion utility inserts a blank line before the panel instruction text.

## Conditions

- You must code the PNLINST within a PANEL, AREA, or REGION definition.

## Nested Tags

You can code the following tags within a PNLINST definition:

Tag	Name	Usage	Page	Required
HP	Highlighted phrase	Multiple	348	No

Tag	Name	Usage	Page	Required
PS	Point-and-Shoot	Multiple	438	No
RP	Reference phrase	Multiple	454	No

## Example

The following application panel markup contains one panel instruction. Figure 153 shows the formatted result.

```

<!DOCTYPE DM SYSTEM>

<VARCLASS NAME=selcls TYPE='char 2'>
<VARLIST>
  <VARDCL NAME=loc VARCLASS=selcls>
  <VARDCL NAME=mode VARCLASS=selcls>
</VARLIST>

<PANEL NAME=pnlinst HELP=trvlhlp WIDTH=60 DEPTH=22 KEYLIST=keyl xmp>
Dream Vacation Guide
<AB>
  <ABC>File
    <PDC>Add Entry
      <ACTION RUN=add>
    <PDC>Delete Entry
      <ACTION RUN=delete>
    <PDC>Update Entry
      <ACTION RUN=update>
    <PDC>Exit
      <ACTION RUN=exit>
  <ABC>Help
    <PDC>Extended Help...
      <ACTION RUN=exhlp>
    <PDC>Keys Help...
      <ACTION RUN=keyshlp>
</AB>
<AREA>
  <PNLINST>Choose one of the following exotic locations and
your preferred mode of travel, then press Enter.
  <DIVIDER>
  <REGION DIR=horiz>
  <SELFLD NAME=loc PMTWIDTH=23 SELWIDTH=25>Exotic Location:
    <CHOICE>Athens, GA
    <CHOICE>Berlin, CT
    <CHOICE>Cairo, IL
    <CHOICE>Lizard Lick, NC
    <CHOICE>Paris, TX
    <CHOICE>Rome, NY
    <CHOICE>Venice, FL
  </SELFLD>
  <DIVIDER>
  <SELFLD NAME=mode PMTWIDTH=25 SELWIDTH=25>Travel Mode:
    <CHOICE>Boxcar
    <CHOICE>Hi tchhi ke
    <CHOICE>Mule
  </SELFLD>
</REGION>
</AREA>
<CMDAREA>
</PANEL>

```





Figure 153. Panel Instructions

## PS (Point-and-Shoot)


The PS tag defines a text string that is to be enabled for point-and-shoot.



### IMAP options



### IMAP group



**VAR=point-and-shoot-variable-name | %varname**

This attribute provides the name of a variable which is to be set when a point-and-shoot phrase is clicked on for selection. You can define this attribute as a variable name preceded by a “%”.

The *point-and-shoot-variable-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

**VALUE=point-and-shoot-value | %varname | \***

This attribute provides the value to be placed in the field specified by the VAR attribute. You can define this attribute as a variable name preceded by a “%”. To specify a blank value, the " ' " (quotation mark, apostrophe, blank, apostrophe, quotation mark) coding notation should be used.

When the PS tag is used with the CHOICE tag, VALUE=\* can be used to automatically use the current choice number (or SELCHAR value) as the point-and-shoot selection value.

**CSRGRP=NO | YES | n**

When CSRGRP=YES, the conversion utility generates a cursor group number to be used for this point-and-shoot text field. When CSRGRP=n, the number provided is used for this field.

**DEPTH=n | %varname**

This attribute defines the depth reserved for the point-and-shoot field. When the panel is displayed in GUI mode, the resulting push button is displayed with the specified DEPTH. You use this attribute in combination with the IMAPNAME attribute to provide space for the image. The minimum value is 1 and the maximum value is the remaining panel depth.

**IMAPNAME=image-name | %varname**

This attribute specifies the name of a image to be placed on the point-and-shoot push button when it is displayed in GUI mode. The *image-name* is not used when the panel is displayed in host mode.

The *image-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

**IMAPNAMEP=image-namep | %varname**

This attribute specifies the name of a image to be placed on the point-and-shoot push button after it has been pushed when it is displayed in GUI mode. The *image-namep* is not used when the panel is displayed in host mode.

The *image-namep* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

**PLACE=ABOVE | BELOW | LEFT | RIGHT | %varname**

This attribute specifies the position of the image relative to the text within the point-and-shoot push button.

**point-and-shoot-text**

This is the text of a point-and-shoot entry.

## Description

The PS tag is valid as part of the text following:

**INFO TAGS** ATTENTION, CAUTION, DD, DDHD, DT, DTHD, FIG, FIGCAP, H2, H3, H4, LI, LINES, LP, NOTE, NT, P, PD, PT, WARNING, and XMP.

PANEL TAGS BOTINST, CHOFLD, CHOICE, DTAFLD, DTAFLDD, GRPHDR, LSTCOL, LSTGRP, PNLINST, SELFLD, and TOPINST.

The *point-and-shoot-text* is color emphasized within the text of the panel. When running in GUI mode, the *point-and-shoot-text* displays as a push button. For host displays, the user places the cursor on the *point-and-shoot-text* and presses ENTER to select the option.

## Conditions

- The PS tag requires an end tag.
- When a “%varname” notation is found on any of the attributes that allow a variable name, the “%varname” entry must follow the standard naming convention described in “Rules for “%variable” Names” on page 205.

## Nested tags

None.

## Example

The following example is provided to show the use of point-and-shoot selection for a sample option menu. Figure 154 on page 441 shows the formatted result.

```
<!doctype dm system (>
<!-- Sample selection menu with point-and-shoot -->
<panel name=ps1 menu keylist=keylxml>Sample Point-and-Shoot
  <topinst>This is a selection panel.
  <selfld type=menu pmtloc=before
    selwidth=40 pmtwidth=10>Select an option
    <choice checkvar=xtest1 match=a>
      <PS VAR=zcmd VALUE=1>Selection #1 (Command Tstch1)
    </PS>
    <action run=tstch1 parm='1 2 3 4'
      passlib newpool suspend>
    <choice checkvar=xtest1 match=b>
      <PS VAR=zcmd VALUE=2>Selection #2 (Command Tstch2)
    </PS>
    <action run=tstch2 parm=1234>
    <choice checkvar=xtest1 match=c>
      <PS VAR=zcmd VALUE=3>Selection #3 (Command Tstch3)
    </PS>
    <action run=tstch3 parm=abcd>
    <choice checkvar=xtest1 match=d>
      <PS VAR=zcmd VALUE=4>Selection #4 (Command Tstch4)
    </PS>
    <action run=tstch4 parm='a b c d' >
  </selfld>
  <cmdarea>
</panel>
```





Figure 154. Point-and-Shoot Fields

## PT (Parameter Term)

The PT tag defines a term in a parameter list.



### FORMAT = START | CENTER | END

This attribute specifies the placement of the PT tag text within the space provided by TSIZE. The PT tag FORMAT setting overrides the FORMAT setting of the enclosing PARML tag.

### NOSKIP

This attribute causes the definition term to be formatted without a blank line before the term. It is used to control the formatting of the parameter term when COMPACT has not been specified on the enclosing PARML tag. When the PARML tag TSIZE attribute specifies that multiple PT tags are to be formatted for each PD tag, NOSKIP should be coded on the first PT tag. It is ignored for the second and subsequent PT tags.

### SPLIT=NO | YES

This attribute controls the format of the last PT tag in a multiple PT tag group. It is used only when BREAK=ALL or when BREAK=FIT and the PT tag text length exceeds the TSIZE value. When SPLIT=YES, the text following the last PT tag in the PT group (typically one or two dashes) is placed in front of the first line of the formatted PD tag text. The PT tag SPLIT setting overrides the SPLIT specified in the enclosing PARML tag.

### parameter-term

This is the text of the parameter term.

## Description

The PT tag defines a parameter term in a parameter list.

## Conditions

- You must code the PT tag within a PARML definition. See “PARML (Parameter List)” on page 424 for a complete description of this tag.
- Each PT tag must be paired with an associated PD tag. You can specify only one PT tag for each PD tag within a parameter list. The PT tag must immediately precede the PD tag it is associated with.

## Nested Tags

You can code the following tags within a PT definition:

Tag	Name	Usage	Page	Required
HP	Highlighted phrase	Multiple	348	No
PS	Point-and-Shoot	Multiple	438	No
PTSEG	Parameter term segment	Multiple	445	No
RP	Reference phrase	Multiple	454	No

## Example

The following help panel markup contains a parameter list with two parameter terms. Figure 155 on page 443 shows the formatted result.

```
<!DOCTYPE DM SYSTEM>

<HELP NAME=pt WIDTH=40 DEPTH=18>Help for the Duplex Function
<AREA>
<INFO>
  <P>The two options associated with
  the DUPLEX function are:
  <PARML TSIZE=5>
    <PT>DCopies
    <PD>Which prints one-sided copies that
    are prepared for future duplex copying.
    <PT>DPrint
    <PD>Which prints two-sided copies.
  </PARML>
</INFO>
</AREA>
</HELP>
```




Figure 155. Parameter Terms

---

## PTDIV (Parameter Term Divider)

The PTDIV tag defines a visible vertical divider (|) between multiple PT tags.

—<PTDIV—  
└─</PTDIV>─┘

### Description

The PTDIV tag can be used to create a visual separation between the parameter terms. Each PTDIV tag adds a vertical bar (plus display control attributes) to the parameter list.

### Conditions

The PTDIV tag can be coded before the first PT tag, between PT tags, or following the last PT tag (before the PD tag definition).

### Nested Tags

None.

### Example

The following example illustrates the use of the PTDIV tag in combination with the DIVEND attribute of the PARML tag. Figure 156 on page 444 shows the formatted result.

## PTDIV

```
<!DOCTYPE DM SYSTEM>

<HELP NAME=ptdiv DEPTH=22 WIDTH=60>Part Number Code Help
<AREA>
<INFO>
  <P>Valid part numbers consist of a three-digit
  number followed by a 2-character suffix.
  <DIVIDER>
  <PARML TSIZE=6 compact>
    <PLDIV TYPE=solid>
      <PT>123
      <PD>The first three digits represent
      the lot number of the part.
      <PLDIV TYPE=solid>
      <PT>AA
      <PD>The 2-character suffix represents the
      department the part originated from.
      The valid suffixes are:
      <PARML BREAK=none COMPACT SKIP DIVEND=yes>
        <PLDIV TYPE=solid>
          <PTDIV>
          <PT>TO
          <PTDIV>
          <PD>Tools
          <PTDIV>
          <PT>EL
          <PTDIV>
          <PD>Electrical
          <PTDIV>
          <PT>ME
          <PTDIV>
          <PD>Mechanical
        </PARML>
      </PARML>
    </INFO>
  </AREA>
</HELP>
```




Figure 156. Parameter Term Divider

## PTSEG (Parameter Term Segment)

The PTSEG tag defines a segment of the parameter term. It is used to provide vertical separation of the PT tag text.

```
--<PTSEG>
└─┬─┘
  └─</PTSEG>─┘
```

### Description

The PTSEG tag is used to create a vertical separation within the parameter term. The text following the PTSEG tag is formatted directly under any previous parameter term tag text. Multiple PTSEG tags create additional PT text lines.

Use of the PTSEG tag affects the PARML tag BREAK attribute. The first (or only) line of PT tag text is processed according to the BREAK attribute of the PARML tag. For additional lines, when TSIZE is large enough to accommodate the text segments, the PTSEG text is formatted in front of the associated PD tag text. When TSIZE is not large enough to accommodate the largest segment, all of the PT and PTSEG text is formatted above the associated PD tag text.

### Conditions

- The PTSEG tag can be coded within the text following a PT tag.
- When a PTSEG tag is coded, then all remaining PT tag text for the current PT tag set must follow a PTSEG tag.
- The PT nested tags RP and PS are not supported within PT tag text following any PTSEG tag in a PT/PD tag set.

### Nested Tags

You can code the following tag within a PTSEG definition:

Tag	Name	Usage	Page	Required
HP	Highlighted phrase	Multiple	348	No

### Example

The following example illustrates the use of the PTSEG tag in combination with a multiple PT tag set. The last PT tag includes the SPLIT=yes attribute to format the dash in front of the PD tag text. Figure 157 on page 446 shows the formatted result.

```
<!DOCTYPE DM SYSTEM(>
```

```
<PANEL NAME=ptseg KEYLIST=ISRHELP APPLID=ISR WINDOW=no PADC=user
      TUTOR ZUP=ISP7R000>Traces - Primary Commands
```

```
<CMDAREA CAPS=on>
<AREA DEPTH=1 EXTEND=on>
```

```
<INFO WIDTH=*>
<P>
```

```
Enter a <hp>Primary Command</hp> in the command input field.
It is processed after all row modifications and all line commands
are processed. The following primary commands are valid for the
Traces options:
```

```
<PARML TSIZE="8 1" INDENT=2>
<PT>
```

```

LOCATE
function-name
(Function Traces) or variable name (Variable Traces)
<PTSEG>
LOC or
<PTSEG>
L
<PT SPLIT=yes>-
<PD>The LOCATE command positions the scrollable display at the
first (or next) row containing the function name (Function
Traces option) or the variable name (Variable Traces option).
</PARML>
</INFO>
</AREA>
</PANEL>

```

Tutorial ----- Traces - Primary Commands ----- Tutorial  
 Command ==>> \_\_\_\_\_


Enter a Primary Command in the command input field. It is processed after all row modifications and all line commands are processed. The following primary commands are valid for the Traces options:

LOCATE function-name (Function Traces) or variable-name (Variable Traces)  
 LOC or - The LOCATE command positions the scrollable display at the first  
 L (or next) row containing the function name (Function Traces option) or the variable name (Variable Traces option).


Figure 157. Parameter Term Segment

## REGION (Region)

The REGION tag defines the characteristics of a panel section including the direction in which fields on an application panel are arranged.



### GRPBOX Group:



**DIR=VERT | HORIZ**

This attribute specifies in which direction the contents of a region is arranged. The default value is VERT, which formats the contents of the region in a vertical direction; that is, top to bottom. If you specify the HORIZ value for DIR, the contents of the region are formatted horizontally; that is, left to right within the region.

**INDENT=n**

This attribute defines the number of columns to indent the current region from the current left region boundary.

**WIDTH=n | \***

This attribute defines the width of a panel region. If WIDTH is not specified or WIDTH=\*, the default value is the remaining available panel width.

**DEPTH=n | \***

This attribute defines the size of a scrollable region. When EXTEND=OFF, the minimum value is 2 and the maximum value is the remaining panel depth. When EXTEND=ON, the minimum value is 1. If the DEPTH value is specified as "\*", the conversion utility will reserve the remaining available panel depth for the scrollable region.

If DEPTH is not specified the region will not be scrollable.

**EXTEND=OFF | ON | FORCE**

This attribute defines the run-time display size for the scrollable region. If EXTEND=ON is specified, the panel definition is expanded from the minimum DEPTH to the size of the logical screen. Only one EXTEND=ON attribute value is allowed on a panel. The first tag (AREA, DA, GA, REGION, SELFLD) with EXTEND=ON is accepted; the EXTEND attribute on any subsequent tag is ignored.

If you intend to display the panels in a pop-up window, it is recommended that you code EXTEND=OFF.

If the EXTEND attribute is specified without the DEPTH attribute, a warning message is issued and the EXTEND attribute is ignored.

If EXTEND=FORCE is specified within a horizontal area or region, the EXTEND(ON) keyword is added to the scrollable area attribute statement in the )ATTR panel section. The conversion utility issues a message to advise of a potential display error if other panel fields are formatted on or after the last defined line of the scrollable area.

**ALIGN=YES | NO**

This attribute controls the horizontal alignment of the first fields in horizontal regions. The default is to align the fields to facilitate cursor movement by tabbing. This attribute is valid only when DIR=HORIZ.

**GRPBOX=NO | YES**

This attribute is used to specify a group box. The default value is NO. The group box outline is visible only when running ISPF in GUI mode.

When GRPBOX=YES is specified on the same REGION tag that defines a scrollable region, the group box title is formatted as the first line within the )AREA panel section.

**GRPWIDTH=n**

This attribute is used to specify the width of the group box. The default and maximum group box width is the region width.

## REGION

GRPWIDTH can be used to specify a group box width smaller than the default value. As an example, when the region consists only of a SELFLD tag that is formatted into multiple columns for host display, but is specified as a list box or drop-down list, the GUI mode display appears as a single column. The right border of the group box would normally extend beyond the space required for the GUI display. The GRPWIDTH attribute can be used to limit the group box to the width of the list box or drop-down list.

### **GRPBXVAR=variable-name**

This attribute defines a variable whose value indicates whether the group box outline is added when the panel is displayed in GUI mode. If the variable is equal to the value specified by the GRPBXMAT attribute, the group box outline is added.

The GRPBXVAR attribute value must be specified without a leading % sign. The *variable-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

### **GRPBXMAT=1 | string**

This attribute defines the value for the GRPBXVAR variable that indicates the group box outline is to be added to the panel in GUI mode. The *string* can be any character string. GRPBXMAT=1 is the default.

### **LOCATION=DEFAULT | TITLE**

This attribute is used to build a panel ‘title’ which requires data fields in specific column positions. A single line may be formatted to be placed in the panel title position by enclosing the appropriate tags within a horizontal region specifying LOCATION=TITLE. The resulting line displays with the colors associated with the tags used to format the line. This attribute is valid only when DIR=HORIZ.

### **group-box-title**

This is the title for the group box. The *group-box-title* should be supplied only when GRPBOX=YES. In other cases a warning message will be issued.

## Description

The REGION tag defines the characteristics of a panel section. You can code multiple regions within an application panel.

Nonscrollable horizontal regions are normally aligned left-to-right using the first input field from each region. If a panel consists of both scrollable and nonscrollable regions formatted horizontally, scrollable regions will normally be aligned with the first input fields of nonscrollable regions.

Regions containing data formatted from INFO tags or from the GRPHDR tag will normally start with a blank line when formatted in the )BODY panel section. The blank line is omitted when these tags are formatted at the beginning of a scrollable area.

If you specify the CMDAREA tag within your DTL source file, it must appear before the REGION tag when DEPTH=\* is specified. The REGION tag DEPTH may have to be adjusted to allow for additional lines which result from tags present within the panel definition following the end REGION tag.

## Conditions

- The REGION tag requires an end tag.

- You must code the REGION tag within an AREA or PANEL definition. See “AREA (Area)” on page 217 and “PANEL (Panel)” on page 413 for descriptions of these tags.
- You can also nest regions within other regions.
- You can code only one LSTFLD tag within a REGION definition.

#### Compatibility Considerations

In Version 3, the conversion utility did not format nested horizontal regions. In this release, nested horizontal formatting is supported.

## Nested Tags

You can code the following tags within a REGION definition:

Tag	Name	Usage	Page	Required
COMMENT	Comment	Multiple	275	No
DA	Dynamic area	Multiple	280	No
DIVIDER	Area divider	Multiple	289	No
DTACOL	Data column	Multiple	300	No
DTAFLD	Data field	Multiple	306	No
GA	Graphic area	Single	327	No
GENERATE	Generate	Multiple	330	No
GRPHDR	Group header	Multiple	332	No
INFO	Information region	Multiple	350	No
LSTFLD	List field	Single	377	No
PNLINST	Panel Instruction	Multiple	436	No
REGION	Region	Multiple	377	No
SELFLD	Selection field	Multiple	464	No

## Help Panel

You can code the following tags within a REGION definition on a help panel:

Tag	Name	Usage	Page	Required
DIVIDER	Area divider	Multiple	289	No
INFO	Information region	Multiple	350	No
REGION	Region	Multiple	446	No

## Example

The following application panel markup contains both horizontal and vertical regions. The first two horizontal regions arrange the fields coded within them in a horizontal format. The third horizontal region arranges the selection field and the contents of the vertical region nested within it in a horizontal format. In this example, the INDENT attribute has been used to indent all fields formatted within a region 2 positions under the previous text. The ALIGN attribute has adjusted the default placement of fields in the last vertical region. Figure 158 on page 452 shows

## REGION

the formatted result.

```
<!DOCTYPE DM SYSTEM>

<VARCLASS NAME=chr25 TYPE=' char 25' >
<VARCLASS NAME=chr12 TYPE=' char 12' >
<VARCLASS NAME=chr10 TYPE=' char 10' >
<VARCLASS NAME=chr9 TYPE=' char 9' >
<VARCLASS NAME=chr8 TYPE=' char 8' >
<VARCLASS NAME=chr2 TYPE=' char 2' >

<VARLIST>
  <VARDCL NAME=name VARCLASS=chr25>
  <VARDCL NAME=date VARCLASS=chr8>
  <VARDCL NAME=addr VARCLASS=chr25>
  <VARDCL NAME=ci ty VARCLASS=chr10>
  <VARDCL NAME=state VARCLASS=chr9>
  <VARDCL NAME=zi p VARCLASS=chr12>
  <VARDCL NAME=l evel VARCLASS=chr2>
  <VARDCL NAME=graddate VARCLASS=chr2>
  <VARDCL NAME=maj or VARCLASS=chr10>
</VARLIST>
```

```

<PANEL NAME=region1 keylist=keyl xmp>Application Form
<TOPINST>Complete all of the fields below, then press Enter.
<AREA>
  <REGION INDENT=2>
    <REGION DIR=horiz>
      <DTACOL PMTWIDTH=10>
        <DTAFLD DATAVAR=name ENTWIDTH=25>Name
        <DTAFLD DATAVAR=date ENTWIDTH=8 DESWIDTH=10>Date
          <DTAFLDD>(mm/dd/yy)
      </DTACOL>
    </REGION>
      <DTAFLD DATAVAR=addr ENTWIDTH=25 PMTWIDTH=10>Address
    <REGION DIR=horiz>
      <DTAFLD DATAVAR=city PMTWIDTH=10 ENTWIDTH=25>City
      <DTAFLD DATAVAR=state PMTWIDTH=9 ENTWIDTH=2>State
      <DTAFLD DATAVAR=zip PMTWIDTH=12 ENTWIDTH=5>Zip code
    </REGION>
  </REGION>
  <DIVIDER TYPE=solid GUTTER=3>
  <REGION DIR=horiz INDENT=2 ALIGN=no>
    <SELFLD NAME=level SELWIDTH=35 PMTWIDTH=25>Highest education level:
      <CHOICE>Some high school
      <CHOICE>High school graduate
      <CHOICE>Some college
      <CHOICE>College graduate
      <CHOICE>Some post-graduate work
      <CHOICE>Post-graduate degree
    </SELFLD>
  <DIVIDER TYPE=solid>
  <REGION>
    <GRPHDR FORMAT=none COMPACT STRIP>
      For applicants who are
      high school or college
      graduates:
    <REGION INDENT=2>
      <DTACOL PMTWIDTH=20>
        <DTAFLD DATAVAR=graddate ENTWIDTH=2>Year of graduation
        <DTAFLD DATAVAR=major ENTWIDTH=10>Field of study
      </DTACOL>
    </REGION>
  </REGION>
</AREA>
<CMDAREA>Enter a command
</PANEL>

```

## REGION

Application Form

Complete all of the fields below, then press Enter.

Name . . . \_\_\_\_\_ Date . . . \_\_\_\_\_ (mm/dd/yy)  
Address \_\_\_\_\_  
City . . . \_\_\_\_\_ State . . . \_\_ Zip code . . . \_\_\_\_\_

-----

Highest education level:		For applicants who are
__ 1. Some high school		high school or college
2. High school graduate		graduates:
3. Some college		Year of graduation ____
4. College graduate		Field of study . . . _____
5. Some post-graduate work		
6. Post-graduate degree		

Enter a command ==>> \_\_\_\_\_  
F1=Help      F3=Exit      F5=Display      F6=Keyshelp      F10=Actions  
F12=Cancel

*Figure 158. Regions*

The following example illustrates the use of the WIDTH and DEPTH attributes. The first vertical region width reserves the space required for the second vertical region, which is also scrollable. Figure 159 on page 454 shows the formatted result.

```

<!DOCTYPE DM SYSTEM(
  <!entity sampvar2 sysem>
  <!entity sampabc system>)>
&sampvar2;

<PANEL NAME=region3 KEYLIST=keyl xmp>File-A-Case
<AB>
&sampabc;
</AB>
<CMDAREA>Enter a command
<TOPINST COMPACT>
  Type in client's name and case number (if applicable).
<TOPINST>Then select an action bar choice.
<REGION DIR=horiz>
  <REGION WIDTH=50>
    <DTAFLD DATAVAR=caseno PMTWIDTH=12 ENTWIDTH=7 DESWIDTH=21>Case No
    <DTAFLDD>(A 7-digit number)
    <DTAFLD DATAVAR=name PMTWIDTH=12 ENTWIDTH=25 DESWIDTH=8>Name
    <DTAFLDD>(Last, First, M.I.)
    <DTAFLD DATAVAR=address PMTWIDTH=12 ENTWIDTH=25>Address
    <DIVIDER>
    <SELFLD NAME=casesel PMTWIDTH=11 PMTLOC=before SELWIDTH=38>Choose
    one of the following
    <CHOICE CHECKVAR=case MATCH=civ>Civil
    <CHOICE CHECKVAR=case MATCH=estate>Real Estate
    <CHOICE CHECKVAR=case MATCH=envi ron>Environmental
    </SELFLD>
  </REGION>
  <REGION DEPTH=10>
    <SELFLD TYPE=multi PMTWIDTH=24 SELWIDTH=26>
    Check type of offense
    <CHOICE NAME=patin HELP=patin CHECKVAR=val>Patent Infringement
    <CHOICE NAME=defa HELP=defame CHECKVAR=def>Defamation
    <CHOICE NAME=cont HELP=cont CHECKVAR=con>Breach of Valid Contract
    <CHOICE NAME=priv HELP=priv CHECKVAR=pri>Invasion of Privacy
    <CHOICE NAME=incr HELP=incr CHECKVAR=icr>Interference with
    Contractual Relations
    <CHOICE NAME=di sp HELP=di sp CHECKVAR=di s>Improper Disposal of
    Medical By-Products
    <CHOICE NAME=fraud HELP=fraud CHECKVAR=fra>Fraud
    </SELFLD>
  </REGION>
</REGION>
</PANEL>

```

```

File Search Help
-----
                          File-A-Case

Type in client's name and case number (if applicable).
Then select an action bar choice.

Case No . . . _____ (A 7-digit number)          #SAREA37          #
Name . . . . _____ (Last, First, M.I.)          #                #
Address . . _____                               #                #
Choose one of the following — 1. Civil                #                #
                                2. Real Estate          #                #
                                3. Environmental        #                #

Enter a command ==>> _____
F1=Help      F3=Exit      F5=Display      F6=Keyshelp  F10=Actions
F12=Cancel
    
```

The contents of the scrollable area are as follows:

```

)AREA SAREA37


Check type of offense
- Patent Infringement
- Defamation
- Breach of Valid Contract
- Invasion of Privacy
- Interference with Contractual Relations
- Improper Disposal of Medical By-Products
- Fraud

)AREA SAREA37
    
```

Figure 159. Using WIDTH and DEPTH Attributes

## RP (Reference Phrase)

The RP tag specifies a word or phrase within panel text that has additional help information associated with it.



**HELP= help-panel-name | \*help-message-id | %varname | \*%varname**

This attribute specifies the name of a panel that displays when the user requests help for the *reference-phrase*.

You can specify either a help panel or a message identifier. If a message identifier is used, it must be prefixed with an asterisk (\*).

The help attribute value can be specified as a variable name. When `%varname` is coded, a panel variable name is created. When `*%varname` is coded, a message variable name is created.

If the user requests help on a choice and no help is defined, the extended help panel is displayed. If an extended help panel is not defined for the panel, the application or ISPF tutorial is invoked.

The *help-panel-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

See “HELP (Help Panel)” on page 335 for information about creating help panels. For information about creating messages, see “MSG (Message)” on page 390.

#### **reference-phrase**

This is the text of the phrase.

## **Description**

The RP tag specifies a word or phrase within panel text that has additional information associated with it.

The RP tag is valid as part of the text following:

**INFO tags**      ATTENTION, CAUTION, DD, DDHD, DT, DTHD, FIG, FIGCAP, H2, H3, H4, LI, LINES, LP, NOTE, NT, P, PD, PT, WARNING, and XMP.

**PANEL tags**    BOTINST, CHOFLD, CHOICE, DTAFLD, DTAFLDD, GRPHDR, LSTCOL, LSTGRP, PNLINST, SELFLD, and TOPINST.

The *reference-phrase* is emphasized within the text of the panel to inform the user that additional information is available. The user positions the cursor on the reference phrase and presses F1=Help to obtain help on the phrase.

Each reference phrase is related to additional help panels in a manner similar to field-level help. The panel that appears when you request help from a reference phrase can also contain reference phrases.

Each *reference-phrase* results in one or more entries in the )HELP panel section. Multiple entries are required for phrases that span lines; a separate entry is created for each panel line used by the *reference-phrase*.

## **Conditions**

- The RP tag requires an end tag.

## **Nested Tags**

None.

## **Example**

The following help panel markup contains a reference phrase definition for the phrase, “lifetime warranty”. Figure 160 on page 456 shows the formatted result.

```

<!DOCTYPE DM SYSTEM>

<HELP NAME=rp>HELP for Appliances
<AREA>
<INFO>
<p>In addition to our free delivery and installation program, we also
offer an exclusive <rp help=warrtyh>lifetime warranty</rp> on all
of our appliances.
</INFO>
</AREA>
</HELP>

<help name=warrtyh>Help for Lifetime Warranty
<AREA>
<INFO>
<p>Lifetime warranty covers the replacement of any part that breaks
or becomes non-functional while this product is used by the original
owner.
</INFO>
</AREA>
</HELP>

```




Figure 160. Reference Phrase Example

Accordingly, when the user selects the reference phrase **lifetime warranty**, the help panel specified by the HELP attribute (help=warrtyh) is displayed. Figure 161 shows the formatted result.





Figure 161. Reference Phrase Example

## SCRFLD (Scrollable Field)

The SCRFLD tag defines a field on an application panel as being scrollable. The panel field is defined using either the DTAFLD or LSTCOL tag. The SCRFLD tag must be nested within either a DTAFLD or LSTCOL tag.

Using the SCRFLD tag causes the conversion utility to format an entry in the )FIELD section of the generated panel. Refer to the *ISPF Dialog Developer's Guide and Reference* for a description of the )FIELD section.

**Notes:**

- 1 When the SCRFLD tag is nested in a DTAFD tag, FLDSPOS can be BELOW or SAME. When the SCRFLD tag is nested in a LSTCOL tag, FLDSPOS can be BELOW or ABOVE.

**DISPLEN=n | %varname**

This attribute is used to specify a length for the variable displayed in the scrollable field.

When DISPLEN=*n* is used, *n* specifies the initial length of the variable. *n* must be a value between 1 and 32 767.

*%varname* is a dialog variable that can contain a value between 1 and 32 767 to specify the initial length of the variable displayed in the scrollable field. After the panel is displayed *%varname* contains the maximum of the length of the dialog variable displayed and the initial length specified. When the scrollable field has been defined using the LSTCOL tag, the length of the dialog variable displayed will be the maximum of all instances on the current display for that variable.

**INDVAR=ind-var**

This attribute specifies the name of a dialog variable that contains the left and right scroll indicator.



The SINDVAL attribute can only be specified together with the SINDVAR attribute.

#### **LCOLIND=lcol-var**

This attribute specifies the name of a dialog variable that contains the value of the left column position for the displayed scrollable field.

*lcol-var* is a dialog variable that is updated when the field is scrolled to contain the value of the left column position. This dialog variable can be used to specify an initial left column position for the scrollable field.

**Note:** If the same *lcol-var* is specified on multiple SCRFLD tags the associated panel fields will scroll simultaneously. When the same *lcol-var* is associated with multiple panel fields, the conversion utility will only define *lcol-var* as a left column position indicator panel field for the first of those panel fields.

#### **LCOLDISP=NO | YES**

This attribute is used to specify whether the left column position indicator defined using the LCOLIND attribute is displayed on the panel.

When LCOLDISP=NO, the left column indicator is not generated as a panel field.

#### **RCOLIND=rcol-var**

This attribute specifies the name of a dialog variable that contains the value of the right column position for the displayed scrollable field.

*rcol-var* is a dialog variable that is updated when the field is scrolled to contain the value of the right column position.

**Note:** If the same *rcol-var* is specified on multiple SCRFLD tags the associated panel fields will scroll simultaneously. When the same *rcol-var* is associated with multiple panel fields, the conversion utility will only define *rcol-var* as a right column position indicator panel field for the first of those panel fields.

#### **RCOLDISP=NO | YES**

This attribute is used to specify whether the right column position indicator defined using the LCOLIND attribute is displayed on the panel.

When RCOLDISP=NO, the right column indicator is not generated as a panel field.

#### **SCALE=scale-var**

This attribute specifies the name of a dialog variable that contains the scale indicator.

*scale-var* is a dialog variable that is updated with a scale line reflecting the current columns being displayed for the scrollable field.

#### **SCROLL=ON | OFF | %varname**

This attribute is used to specify whether the field is scrollable or not.

When SCROLL=OFF, the field is not scrollable.

*%varname* is used to specify the name of a scroll control dialog variable. This can be set to a value of ON or OFF to turn scrolling for the field either on or off.

#### **FLDSPOS=BELOW | ABOVE | SAME**

This attribute is used to specify where the scroll indicator panel fields are

## SCRFLD

positioned in relation to the heading text for a table display field defined using the LSTCOL tag or in relation to the display field defined using the DTAFLD tag.

With FLDSPOS=BELOW, the conversion utility defines all scroll indicator panel fields for the scrollable table display field below the heading text or below the data field defined by the DTAFLD tag.

With FLDSPOS=SAME, the conversion utility attempts to define *ind-var*, *lind-var*, and *rind-var* for the data field on the same line as the data field. This option is not valid when the SCRFLD tag is nested within a LSTCOL tag.

With FLDSPOS=ABOVE, the conversion utility defines all scroll indicator panel fields for the scrollable table display field above the heading text. This option is not valid when the SCRFLD tag is nested within a DTAFLD tag.

### Description

The SCRFLD tag defines a field on an application panel as being scrollable. The panel field is defined using either the DTAFLD or LSTCOL tag. The SCRFLD tag must be nested within either a DTAFLD or LSTCOL tag.

Using the SCRFLD tag causes the conversion utility to format an entry in the )FIELD section of the generated panel. Refer to the *ISPF Dialog Developer's Guide and Reference* for a description of the )FIELD section.

#### Scroll indicator fields

The conversion utility implicitly defines *ind-var*, *lind-var*, *rind-var*, and *sind-var* as scroll-indicator panel fields, and *scale-var* as a scale-indicator panel field. This topic describes where the scroll and scale indicator fields appear on the panel. Their position depends on whether the SCRFLD tag is nested within a DTAFLD or LSTCOL tag, and on the attributes specified on the SCRFLD tag.

The order in which the scroll indicator fields are created by the conversion utility is as follows:

1. lcol\_var
2. rcol\_var
3. ind\_var | lind\_var
4. rind\_var

**Position of scroll indicator fields under the LSTCOL tag:** Depending on the attributes specified on the SCRFLD tag, the conversion utility can create below or above the column heading text up to four panel lines containing scroll indicator fields. The following table identifies the order in which the scroll indicator fields are created by the conversion utility, assuming FLDSPOS=BELOW is specified.

Relative Line from Column Heading <b>1</b>	Scroll Indicator Dialog Variables	Comments
+1	<i>ind-var</i>   <i>lind-var</i> and <i>rind-var</i>	Displays either the left/right scroll indicator variable OR the left and right scroll indicator variables.  The scroll indicator variables are positioned left-justified relative to the column.

Relative Line from Column Heading <b>1</b>	Scroll Indicator Dialog Variables	Comments
+2	<i>lcol-var</i> and <i>rcol-var</i>	The left and right column position indicators are positioned left-justified relative to the column.  The number of characters used for the left and right column indicators is one more than the larger of the dimension of the initial field display length or the dimension of the column width.
+3	<i>sind-var</i>	Separator scroll indicator field spans the width of the column.
+4	<i>scale-var</i>	Scale indicator field spans the width of the column.

**1** If the associated scroll indicator dialog variables are not specified, the conversion utility will use the line for the next scroll indicator field.

**Position of scroll indicator fields under the DTAFLD tag:** Depending on the attributes specified on the SCRFLD tag, the conversion utility can create below or on the same line as the data field up to four panel lines containing scroll indicator fields. The following table identifies the order in which the scroll indicator fields are created by the conversion utility, assuming FLDSPOS=BELOW is specified.

The conversion utility defines on the following panel lines output fields for the scroll indicator variables specified using the SCRFLD tag attributes. The following table identifies the order in which the scroll indicator fields are created by the conversion utility:

Relative Line from DTAFLD Field <b>1</b>	Scroll Indicator Dialog Variables	Comments
+1	<i>scale-var</i>	Scale indicator field spans the width of the field.
+2	<i>sind-var</i>	Separator scroll indicator field spans the width of the field.
+3	<i>lcol-var</i> and <i>rcol-var</i>	The left and right column position indicators are positioned left-justified relative to the column.  The number of characters used for the left and right column indicators is one more than the initial field display length.
+4	<i>ind-var</i>   <i>lind-var</i> and <i>rind-var</i>	Displays either the left/right scroll indicator variable OR the left and right scroll indicator variables.  The scroll indicator variables are positioned left-justified relative to the field.

**1** If the associated scroll indicator dialog variables are not specified, the conversion utility will use the line for the next scroll indicator field.

When the SCRFLD tag is associated with a DTAFLD tag that is immediately within a vertical region, scale and separator scroll indicators are not permitted.

## Conditions

- You must code the SCRFLD tag within a LSTCOL or DTAFLD tag.

## Nested Tags

You can code the following tags within a SCRFLD definition:

Tag	Name	Usage	Page	Required
COMMENT	Comment	Multiple	275	No
SOURCE	Source	Multiple	482	No

## Example

In the following source file markup the application panel contains two scrollable fields: the Address field and the Comments field. A scroll separator is displayed with the Address field and a scale line is displayed with the Comments field. Figure 162 on page 463 shows the formatted result.

```
<!DOCTYPE DM SYSTEM>

<VARCLASS NAME=date TYPE=' char 8' >
<VARCLASS NAME=name TYPE=' char 20' >
<VARCLASS NAME=addr TYPE=' char 40' >
<VARCLASS NAME=prod TYPE=' char 25' >
<VARCLASS NAME=comm TYPE=' char 55' >

<VARLIST>
  <VARDCL NAME=curdate VARCLASS=date>
  <VARDCL NAME=snamvar VARCLASS=name>
  <VARDCL NAME=fnamvar VARCLASS=name>
  <VARDCL NAME=sindvar VARCLASS=addr>
  <VARDCL NAME=addrvar VARCLASS=addr>
  <VARDCL NAME=prodvar VARCLASS=prod>
  <VARDCL NAME=scalvar VARCLASS=comm>
  <VARDCL NAME=commvar VARCLASS=comm>
</VARLIST>
<PANEL NAME=scrfl d0 HELP=loghelp>Customer Feedback
<TOPINST>Complete the following fields, then press Enter.
<AREA>
  <DTACOL PMTWIDTH=15>
    <DIVIDER>
      <DTAFLD DATAVAR=curdate USAGE=out ENTWIDTH=8 FLDSpace=27>Date
    <DTAFLDD>(Current Date)
    <DIVIDER>
      <DTAFLD DATAVAR=snamvar ENTWIDTH=20>Surname
    <DIVIDER>
      <DTAFLD DATAVAR=fnamvar ENTWIDTH=20>First Names
    <DIVIDER>
      <DTAFLD DATAVAR=addrvar ENTWIDTH=40 DESWIDTH=15>Address
    <DTAFLDD>(Optional)
      <SCRFLD DISPLEN=80 SINDVAR=sindvar>
    <DIVIDER>
      <DTAFLD DATAVAR=prodvar ENTWIDTH=25 DESWIDTH=25>Product
    <DTAFLDD>(Product Purchased)
    <DIVIDER>
      <DTAFLD DATAVAR=commvar ENTWIDTH=55>Comments
      <SCRFLD DISPLEN=110 SCALE=scalvar>
    </DTACOL>
  </AREA>
<CMDAREA scrollvar=scrvar>Command
</PANEL>
```

Customer Feedback

Complete the following fields, then press Enter.

Date . . . . : 02/10/21 (Current Date)

Surname . . . . Smith

First Names . . John Joseph

Address . . . . Apartment 10a, 100 Happiness Street, Ple (Optional)  
 ----->

Product . . . . Hammer (Product Purchased)

Comments . . . . An implement that has proved very useful for driving na  
 -----1-----2-----3-----4-----5-----

Command ==>>> \_\_\_\_\_ Scroll ==>> CSR  
 F1=Help F3=Exit F7=Up F8=Down F10=Left F11=Right F12=Cancel

Figure 162. List Field

The following source file markup uses the LSTFLD and LSTCOL tags to display the data in an ISPF table. The SCRFLD tag is used to display the Customer and Comments data in scrollable fields. Left and right column indicators are displayed in the column headings for the Customer and Comments data. A separator scroll indicator is also displayed in the heading for the Customer column. A scale indicator is displayed in the heading for the Comments column. Figure 163 on page 464 shows the formatted result.

```
<!DOCTYPE DM SYSTEM>

<VARCLASS NAME=date TYPE=' char 8' >
<VARCLASS NAME=cust TYPE=' char 15' >
<VARCLASS NAME=prod TYPE=' char 15' >
<VARCLASS NAME=comm TYPE=' char 30' >

<VARLIST>
  <VARDCL NAME=datevar VARCLASS=date>
  <VARDCL NAME=custvar VARCLASS=cust>
  <VARDCL NAME=prodvar VARCLASS=prod>
  <VARDCL NAME=commvar VARCLASS=comm>
</VARLIST>

<PANEL NAME=scrfl d1 HELP=loghelp>Customer Feedback Display
<AREA>
<LSTFLD SCROLLVAR=scrollamt SCRHELP=scrhelp>
  <LSTCOL DATAVAR=datevar USAGE=out COLWIDTH=8>Date
  <LSTCOL DATAVAR=custvar USAGE=out COLWIDTH=15>Customer
    <SCRFLD DISPLEN=50 SINDVAR=sindvar LCOLIND=custcol LCOLDISP=YES
      RCOLIND=cusrcol RCOLDISP=YES>
  <LSTCOL DATAVAR=prodvar USAGE=out COLWIDTH=15>Product
  <LSTCOL DATAVAR=commvar USAGE=out COLWIDTH=30>Comments
    <SCRFLD DISPLEN=110 SCALE=scalvar LCOLIND=comlcol LCOLDISP=YES
      RCOLIND=comrcol RCOLDISP=YES>
  </LSTFLD>
</AREA>
<CMDAREA>Command
</PANEL>
```

# SELFLD







Figure 163. List Variable

## SELFLD (Selection Field)

The SELFLD tag defines a field that includes a list of choices.





**NAME=field-name**

This attribute specifies the name for the selection field. The *field-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

The NAME field is required if TYPE=SINGLE because the selection field name is used as the input field for single-choice selection fields. The NAME field is ignored if TYPE=MULTI.

The NAME field is optional for TYPE=MENU, TYPE=MODEL, or TYPE=TUTOR. If present, it is used in place of the command field name in the construction of the option selection statement. However, because the input field is the command line, you must provide panel logic using the SOURCE tag to ensure that the selection choice is placed in the NAME field.

For single-choice selection fields, the *field-name* can be used to position the cursor on the field using the CURSOR attribute of the enclosing PANEL tag or the CURSOR parameter of the DISPLAY service call. In addition, you can use the *field-name* to position a pop-up using the POPLOC parameter of the ADDPOP service call.

**HELP=NO | YES | help-panel-name | \*help-message-id | %varname | \*%varname**

This attribute specifies the help action taken when the user requests help for a selection field. This is field-level help.

When HELP=YES, control is returned to the application. You can specify either a help panel or a message identifier. If a message identifier is used, it must be prefixed with an asterisk (\*).

The help attribute value can be specified as a variable name. When %varname is coded, a panel variable name is created. When \*%varname is coded, a message variable name is created.

If the user requests help on a field and no help is defined, the extended help panel is displayed. If an extended help panel is not defined for the panel, the application or ISPF tutorial is invoked.

The *help-panel-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

See “HELP (Help Panel)” on page 335 for information about creating help panels. For information about creating messages, see “MSG (Message)” on page 390.

**Note:** This attribute is valid only when TYPE=SINGLE.

#### TYPE=SINGLE | MULTI | MENU | MODEL | TUTOR

This attribute specifies whether the selection field is single-choice, multiple-choice, an ISPF selection menu, an edit model selection menu, or a tutorial selection menu.

Single-choice selection fields allow the user to select only one choice from the selection list. Choices in a single-choice selection field appear with sequential numbers before each choice. An input field precedes the first choice in the selection field.

Multiple-choice selection fields allow the user to select one or more choices from the selection list. Choices in a multiple-choice selection field appear with a single character input field before each choice.

The use of TYPE=MENU, TYPE=MODEL, or TYPE=TUTOR is allowed only when the MENU keyword has been specified on the PANEL tag. ISPF selection menu, edit model, or tutorial selection menu fields are formatted in a manner similar to single-choice selection fields. Choices appear with sequential numbers before each choice and the user may select only one choice from the selection list. With these options, the command line is used as the entry choice field. Because the HELP attribute on the SELFLD tag is not valid when TYPE=MENU, TYPE=MODEL, or TYPE=TUTOR, help for selection menu or edit model menu choices must be entered on the CMDAREA tag.

**Note:** Because the selection menu, edit model menu, or tutorial menu panel uses the command line for choice selection, a command area is required. The conversion utility will automatically generate a command area if no CMDAREA tag is provided.

#### PMTLOC=ABOVE | BEFORE

This attribute specifies whether the *field-prompt-text* appears above or in front of the selection field.

#### PMTWIDTH=n | \* | \*\*

This attribute specifies the number of bytes to be used by the prompt for the selection field. When you specify PMTWIDTH=\*, the conversion utility uses the length of the prompt text as the prompt width. When you specify PMTWIDTH=\*\*, the conversion utility uses the maximum available space as the prompt width. If any prompt is longer than this value, the prompt is word-wrapped to fit on multiple lines. The minimum value is 0 and the maximum is the remaining available panel (or region) value. This value overrides the PMTWIDTH value on an enclosing DTACOL tag.

#### SELWIDTH=n | \*

This attribute specifies the number of bytes used for the choices in the selection field. It is useful for defining a consistent appearance for the selection choices. If you do not specify the SELWIDTH parameter on the SELFLD tag, the SELWIDTH parameter on any enclosing DTACOL tag is used. If you do not specify a SELWIDTH value and SELWIDTH is not specified on an enclosing DTACOL tag, then the remaining available width of the panel (or current region) determines the width used to format the choice text. If the SELWIDTH value is specified as “\*”, the conversion utility will use the remaining available width.

## SELFLD

If the width required by the *choice-description-text* and its entry-field exceeds the value specified for SELWIDTH, the text is word-wrapped to multiple lines.

**Note:** Because all of the remaining space is used if no SELWIDTH attribute is provided or if SELWIDTH="\*" is coded, you should specify a SELWIDTH value for fields defined:

- With PMTLOC=BEFORE, because PMTWIDTH is not part of the space reserved by SELWIDTH.
- Within a horizontal region if additional fields are to be formatted to the right of the SELFLD section.

SELWIDTH for selection fields defined within a horizontal region if additional fields are to be formatted to the right of the SELFLD section.

The width specified for a single-choice selection field should include all or a portion of the *choice-description-text* plus 8-13 positions, determined as follows:

- The choice selection entry-field (1-3 characters)
- The entry-field 3270 attributes (2 characters)
- The choice-number inserted by the conversion utility (3-5 characters)
- The 3270 attributes that enclose the *choice-description-text* (2 characters).

The width of a multiple-choice selection field should include all or a portion of the *choice-description-text* plus 5 positions, determined as follows:

- The choice selection entry-fields (1 character)
- The entry-field 3270 attributes (2 characters)
- The 3270 attributes that enclose the *choice-description-text* (2 characters).

The width specified for a menu-choice, model-choice, or tutorial-choice selection field should include all or a portion of the choice-description-text plus 4-19 positions, determined as follows:

- The choice selection entry-field (1-16 characters)
- The entry-field 3270 attribute (1 character)
- The 3270 attributes that enclose the choice-description-text (2 characters).

### ENTWIDTH=2 | n | 'e1 e2...en'

This attribute is valid only when TYPE=SINGLE, TYPE=MENU, TYPE=MODEL, or TYPE=TUTOR.

Multiple ENTWIDTH values can be used when TYPE=MENU, TYPE=MODEL, or TYPE=TUTOR. For these types of selection lists, the ENTWIDTH is used only to format the amount of space used by the selection character(s). The multiple width format is used when CHOICECOLS is greater than 1 to customize the width required for each column of choices. If the number of ENTWIDTH values is less than the number of columns, the last (or only) ENTWIDTH value is used for the remaining columns. If more ENTWIDTH values are supplied than there are columns of choices, the excess ENTWIDTH values are ignored.

When TYPE=SINGLE and the value of LISTTYPE is not COMBO, ENTWIDTH specifies the number of bytes used for both the entry field and the space between the selection identifier and the selection text. The default width value is 2. The minimum width value is 1, which can be specified for any single-choice selection list. The maximum width value (when LISTTYPE is not COMBO) is 3, which can be specified for selection lists within a scrollable panel area. The width of 3 is provided for use when the number of CHOICE tags will exceed 99.

When LISTTYPE=COMBO, the maximum ENTWIDTH value is 2 bytes less than the SELWIDTH value.

**Note:** A width of 1 should only be used when the total number of CHOICE tags is less than 10. The conversion utility discards choices which cannot be selected with the specified entry width.

When TYPE=MENU, TYPE=MODEL, or TYPE=TUTOR, the command area is used as the input field and the ENTWIDTH value is used only to determine the spacing between the selection identifier and the selection text. The maximum ENTWIDTH value for these types is 16.

#### **REQUIRED=NO | YES**

This attribute indicates if the field requires input.

If REQUIRED=YES is coded, a VER(variable,NONBLANK) statement will be built by ISPDTLC and placed in the )PROC section of the generated ISPF panel.

**Note:** This attribute is valid only when TYPE=SINGLE.

#### **MSG=message-identifier**

This attribute specifies the message that is displayed when the user does not choose a selection (defined with the REQUIRED attribute). If you do not specify a *message-identifier*, ISPF displays a default message.

If you specify the MSG attribute and REQUIRED=YES, a VER(variable,NONBLANK,MSG=message-identifier) statement is built by ISPDTLC and placed in the )PROC section of the generated ISPF panel. If you specify the MSG attribute and REQUIRED=NO (the default), the conversion utility issues a warning message.

#### **FCHOICE=1 | 0**

The FCHOICE attribute controls the starting choice number for TYPE=SINGLE, TYPE=MENU, TYPE=MODEL or TYPE=TUTOR. When FCHOICE=0, the first choice is the number 0.

**Note:** This attribute is valid only when TYPE=SINGLE, TYPE=MENU, TYPE=MODEL, or TYPE=TUTOR.

#### **AUTOTAB=YES | NO**

When AUTOTAB=YES, the cursor moves to the next field capable of input when the user enters the last character in this field. If no other field capable of user input exists on the panel, the cursor returns to the beginning of this field.

The ISPF SKIP keyword is not supported when running in GUI mode.

**Note:** This attribute is valid only when TYPE=SINGLE.

#### **DEPTH=n | \***

This attribute defines the minimum size of a scrollable selection list. If DEPTH is not specified, the selection list will not be scrollable. If the DEPTH value is specified as "\*", the conversion utility will reserve the remaining available panel depth. When EXTEND=OFF, the minimum depth is 2. When EXTEND=ON, the minimum depth is 1. The DEPTH attribute is ignored when LISTTYPE=COMBO.

#### **EXTEND=OFF | ON | FORCE**

This attribute defines the run-time display size for the scrollable list area. If EXTEND=ON is specified, the panel definition is expanded from the

minimum DEPTH to the size of the logical screen. Only one EXTEND=ON attribute value is allowed on a panel. The first tag (AREA, DA, GA, REGION, SELFLD) with EXTEND=ON is accepted; the EXTEND attribute on any subsequent tag is ignored.

If the EXTEND attribute is specified without the DEPTH attribute, a warning message is issued and the EXTEND attribute is ignored. The EXTEND attribute is ignored when LISTTYPE=COMBO.

If you intend to display the panels in a pop-up window, it is recommended that you code EXTEND=OFF.

If EXTEND=FORCE is specified within a horizontal area or region, the EXTEND(ON) keyword is added to the scrollable area attribute statement in the )ATTR panel section. The conversion utility issues a message to advise of a potential display error if other panel fields are formatted on or after the last defined line of the scrollable area.

**TRAIL='trail-var-1 trail-var-2 ... trail-var-n'**

This attribute specifies variable name(s) that the application uses to obtain the TRAIL information created by menu or model selection processing.

Each trail variable specified must follow the standard naming convention described in "Rules for Variable Names" on page 205.

**Note:** This attribute is valid only when TYPE=MENU or TYPE=MODEL.

**CHOICECOLS=1 | n**

This attribute specifies the number of columns to format with the CHOICE items. The default is 1. The CHOICECOLS attribute is ignored when LISTTYPE=COMBO.

**CHOICEDEPTH=n | \***

This attribute specifies the number of CHOICE entries to be placed in each column. The minimum CHOICEDEPTH value is 1. The normal maximum and default is the remaining panel depth. If the DEPTH attribute has been specified on the SELFLD tag, or an enclosing REGION or AREA tag, (and the corresponding tag attribute value for EXTEND is OFF) the most recently specified depth value is used as the maximum and default value. You may specify CHOICEDEPTH="\*" which tells the conversion utility to calculate the column depth based on the total number of CHOICE tags and the number of columns specified by the CHOICECOLS attribute.

If more CHOICE entries are specified than can be formatted in the available number of columns specified by the CHOICECOLS attribute, the remaining CHOICE entries are placed in the rightmost (or only) available column for the current SELFLD tag. The CHOICEDEPTH attribute is ignored when LISTTYPE=COMBO.

**CWIDTHS='w1 w2...wn'**

This attribute specifies the number of bytes to be allocated for each column of CHOICE entries. The 'w1 w2...wn' notation provides the number of bytes for each column. You may use an asterisk or a number combined with an asterisk to specify a proportional allocation of column space. For example, the specification of '2\* \* 3\*' for 3 columns would result in a space calculation based on 6 units, with 2 units allocated to column 1, 1 unit allocated to column 2, and 3 units allocated to column 3. If more columns have been specified by CHOICECOLS than are accounted for by CWIDTHS, the remaining space is divided evenly between the remaining columns. If CWIDTHS is not specified,

the available formatting space is divided evenly based on the CHOICECOLS value. The CWIDTHS attribute is ignored when LISTTYPE=COMBO.

**PAD=NULLS | USER | char | %varname**

This attribute specifies the pad character for initializing the field. You can define this attribute as a variable name preceded by a "%".

**Note:** This attribute is valid only when TYPE=SINGLE.

**PADC=NULLS | USER | char | %varname**

This attribute specifies the conditional padding character to be used for initializing the field. You can define this attribute as a variable name preceded by a "%".

**Note:** This attribute is valid only when TYPE=SINGLE.

**OUTLINE=NONE | L | R | O | U | BOX | %varname**

This attribute provides for displaying lines around the field on a DBCS terminal. You can define this attribute as a variable name preceded by a "%".

**Note:** This attribute is valid only when TYPE=SINGLE.

**SELMSG=selfld-msg-identifier**

This attribute specifies the message that is displayed when an invalid single-choice entry is selected.

**SELMSGU=selfld-msg-unavailable**

This attribute specifies the message that is displayed when an unavailable single-choice entry is selected.

**INIT=YES | NO | init-value**

This attribute controls the single-choice and multi-choice selection field variables initialization in the panel )INIT section. When INIT = NO, the variables are not initialized to blank. When TYPE = SINGLE, you can alternatively provide a valid choice selection by specifying INIT = init-value.

CHOICE tag CHECKVAR processing can override the INIT value.

**VERIFY=YES | NO**

This attribute controls the single-choice verification and menu-choice, model-choice, or tutor-choice selection logic generation in the panel )PROC section. When TYPE=MENU, TYPE=MODEL, or TYPE=TUTOR, VERIFY=NO bypasses the creation of the ZSEL statement. You can provide a replacement ZSEL statement with the <SOURCE> tag.

**REFRESH=YES | NO**

This attribute controls the creation of the REFRESH statement in the panel )REINIT section for multi-choice selection lists.

**SELFMT=START | END**

This attribute controls the placement of the choice selection character(s) within the width specified by ENTWIDTH. The default is to left justify the choice selection character(s).

**Note:** This attribute is valid only when TYPE=SINGLE, TYPE=MENU, TYPE=MODEL, or TYPE=TUTOR.

**CHKBOX=YES | NO**

This attribute controls the creation of panel keywords that enable check boxes when running ISPF in GUI mode. The default value is YES.

## SELFLD

The CHKBOX attribute is not valid and is ignored for single-choice, menu-choice, and model-choice selection lists.

If the conversion utility has been invoked with the NOGUI option, specifying CHKBOX=YES on the SELFLD tag will override the invocation option so that check-box controls will be generated.

### ZGUI=YES | NO

This attribute controls the creation of the "VGET (ZGUI)" statement in the panel )INIT section for multi-choice selection lists that specify the "&multipmt" ENTITY as *field-prompt-text*.

### CSRGRP=NO | YES | n

The CSRGRP attribute is valid only when TYPE=MULTI and CHKBOX=YES (either specified or defaulted). When CSRGRP=YES, the conversion utility generates a cursor group number to be used for this selection list. When CSRGRP=n, the number provided is used for the CHOICE fields within this SELFLD tag.

### TSIZE='s1 s2...sn'

The TSIZE attribute provides the number of bytes to indent multiple lines of CHOICE text. Multiple TSIZE values can be used to provide unique indentation amounts for multiple column lists (when CHOICECOLS is greater than 1). If the number of TSIZE values is less than the number of columns, the last (or only) TSIZE value is used for the remaining columns. If more TSIZE values are supplied than there are columns of choices, the extra TSIZE values are ignored.

### LISTTYPE=RADIO | LISTBOX | DDLIST | COMBO

This attribute controls the creation of panel keywords that cause single-choice selection lists to be displayed with radio buttons, or as a list box, drop-down list, or combination box when running ISPF in GUI mode.

When LISTTYPE=COMBO or LISTTYPE=DDLIST and the PANEL tag has specified TYPE=GUI, a single input field is placed in the panel )BODY section, and the DEPTH, EXTEND, CHOICECOLS, CHOICEDEPTH, and CWIDTHS attributes are ignored. The length of the input field is determined by the ENTWIDTH attribute. For combination boxes, you should consider placing a list of the valid possible choices in a help panel accessible through field-level help.

**Note:** This attribute is valid only when TYPE=SINGLE.

### LISTREF=list-name

This attribute is not used for LISTTYPE=RADIO. The *list-name* specifies the name for the )LIST section in the generated panel. The *list-name* must follow the standard naming convention described in "Rules for Variable Names" on page 205. If you don't specify *list-name*, the default *list-name* is the *field-name* provided by the NAME attribute.

If a panel contains more than one SELFLD tag that has the same set of CHOICES, the CHOICE tags can be provided within the first SELFLD tag definition, and then referenced in subsequent SELFLD tags by specifying the first SELFLD tag *list-name* as the LISTREF value of the subsequent SELFLD tag(s).

### LISTDEPTH=n

The LISTDEPTH attribute is not used for LISTTYPE=RADIO. LISTDEPTH provides the number of panel lines to be used for the list box, drop-down list, or combination box.

When LISTTYPE=LISTBOX and you don't specify LISTDEPTH, the list box depth will be defaulted to use the number of panel lines formatted for a numbered selection list, allowing for the horizontal scroll bar. If LISTDEPTH is specified, the value should be less than the number of lines formatted for a numbered selection list to allow for the horizontal scroll bar.

When LISTTYPE=DDLIST and you don't specify LISTDEPTH, the drop-down list depth is determined by ISPF when the panel is displayed. If LISTDEPTH is specified, the minimum LISTDEPTH value is 1. The normal maximum value is the remaining panel depth. If the DEPTH attribute has been specified on the SELFLD tag or on an enclosing REGION or AREA tag (and the corresponding tag attribute value for EXTEND is OFF), the most recently specified depth value is the maximum value.

#### **DBALIGN=**YES | NO | FIELD | FORCE

This attribute defines the DBALIGN value. DBALIGN is used only for DBCS language conversions when PMTLOC=ABOVE and the DBALIGN invocation option is specified.

When DBALIGN=YES, and the field-prompt-text starts with a DBCS character or a single-choice or multi-choice selection list definition does not include field-prompt-text, the entry field for the choice is shifted 1 position to the right.

When DBALIGN=NO, no alignment adjustment is made.

When DBALIGN=FIELD, the entry field is shifted but no adjustment is done for the prompt. The FORCE and FIELD values are useful when alignment is required with other SELFLD or DTAFLD tags.

When DBALIGN=FORCE, the entry field is shifted and the field-prompt-text is also adjusted to match even if the field-prompt-text starts with a single byte character.

#### **NOSEL=no-selection-value**

This attribute provides a value to be placed the CHECKVAR variable (specified by the CHOICE tag) when no selection is chosen from the available list.

If REQUIRED=YES is specified, a message is issued and NOSEL is ignored.

If no CHOICE tag specifies a CHECKVAR attribute, the NOSEL attribute is ignored.

**Note:** This attribute is valid only when TYPE=SINGLE.

#### **SELDEFAULT=x**

This attribute is used to provide a default choice selection when TYPE=SINGLE, MENU, MODEL, or TUTOR. The value x must be a valid choice selection. If no selection is made by the user, the default value is returned to the application.

#### **PMTSKIP=**NO | YES

This attribute is used for horizontal formatting of input fields. When PMTSKIP=YES, and the previous DTAFLD definition includes the NOENDATTR attribute, the cursor will move past the prompt text to the input field when the user enters the last character in the previous field. If there is no other input field on the panel, the cursor returns to the first input field on the panel. The ISPF SKIP keyword is not supported in GUI mode.

#### **FLDTYPE=**CUA | ISPF

This attribute defines the attribute type to be applied to the selection entry

## SELFLD

field when LISTTYPE is LISTBOX, DDLIST, or COMBO. TYPE=CUA, the default, causes the field to display using the standard CUA attribute. When FLDDTYPE=ISPF, a non-CUA attribute is generated and you may specify the color, intensity and highlighting with the COLOR, INTENS and HILITE attributes. These attributes are not valid when FLDDTYPE=CUA.

**COLOR=WHITE | RED | BLUE | GREEN | PINK | YELLOW | TURQ | %varname**

This attribute specifies the color of the field. You can define this attribute as a variable name preceded by a "%".

**INTENS=HIGH | LOW | NON | %varname**

This attribute defines the intensity of a field. You can define this attribute as a variable name preceded by a "%".

**HILITE=USCORE | BLINK | REVERSE | %varname**

This attribute specifies the extended highlighting attribute of the field. You can define this attribute as a variable name preceded by "%".

**SELCHECK = NO | YES**

This attribute is used with menu-choice selection to specify that panel logic is to be included in selection processing to check for valid selection entries. For example, a message is issued if a period (.) or a period followed by data (.xxx) is entered as a selection choice.

**Note:** This attribute is valid only when TYPE=MENU.

**VARDCL=YES | NO**

When VARDCL=NO the field name is not checked to the declared variable information provided with the VARCLASS and VARDCL tags.

**Note:** This attribute is only valid when TYPE=SINGLE.

### field-prompt-text

This is the prompt text for the selection field. The prompt text can appear in front of or above the field, based on the value assigned to the PMTLOC attribute.

Multi-choice selections are displayed as check boxes when running in GUI mode. To support both host and workstation forms of multi-choice prompt text, a special pre-defined ENTITY name of "&multiptm" may be specified as the *field-prompt-text*. When the panel is displayed, the *field-prompt-text* will be  
Enter "/" to select option

(or its translated equivalent) for host display or  
Check box to select option

(or its translated equivalent) for workstation display. The panel definition should specify a PMTWIDTH value large enough to format the prompt as a single line. If there is insufficient space to present the entire *field-prompt-text*, it will be truncated to fit the available space.

## Description

The SELFLD tag defines a selection field that includes a list of choices. CHOICE tags coded within the SELFLD definition define the choices for the selection field.

The TYPE attribute of the SELFLD tag determines how the choices appear. If TYPE=SINGLE, the SELFLD NAME attribute is used as the selection input field. If

TYPE=MULTI, the CHOICE NAME attribute is used as the selection input field for each choice. If TYPE=MENU, TYPE=MODEL, or TYPE=TUTOR, the command line is used as the selection input field.

When a selection list is formatted as a scrollable list:

- The multi-choice list entry field scrolls with the choice descriptions.
- The single-choice entry field is formatted beside the choice list and remains visible when the choice descriptions scroll.
- Choice descriptions that are formatted in multiple columns (CHOICECOLS and CHOICEDEPTH attributes specified) result in a separate scrollable area for each column.

The )LIST section is added to the panel if you specify:

- The LISTREF attribute
- A scrollable selection list (DEPTH is provided)
- The SELFLD tag within a scrollable AREA or REGION
- A multiple column selection list (CHOICECOLS > 1)
- LISTTYPE=COMBO
- TYPE=GUI on the PANEL tag.

**Note:** If you specify the CMDAREA tag within your DTL source file, it must appear before the SELFLD tag when TYPE=MENU, TYPE=MODEL, or TYPE=TUTOR and CHECKVAR or UNAVAIL attributes are specified on nested CHOICE tags.

If you specify the CMDAREA tag within your DTL source file, it must appear before the SELFLD tag when DEPTH=\* is specified. The SELFLD tag DEPTH may have to be adjusted to allow for additional lines which result from tags present within the panel definition following the end SELFLD tag.

## Conditions

- The SELFLD tag requires an end tag.
- You must code the SELFLD tag within an AREA, DTACOL, REGION, or PANEL definition. See “AREA (Area)” on page 217, “DTACOL (Data Column)” on page 300, “REGION (Region)” on page 446, and “PANEL (Panel)” on page 413 for descriptions of these tags.
- Single-choice selection fields (the default TYPE value) should have an associated VARDCL definition for the *field-name* specified with the NAME attribute. See “VARDCL (Variable Declaration)” on page 497 for a complete description of this tag.
- If both PAD and PADC have been specified, PAD is ignored and PADC is used.
- When a “%varname” notation is found on any of the attributes that allow a variable name, the “%varname” entry must follow the standard naming convention described in “Rules for “%variable” Names” on page 205.
- You should code a CMDAREA on any panel that contains a SELFLD definition that specifies TYPE=MENU, TYPE=MODEL, or TYPE=TUTOR. If you do not include the CMDAREA tag, the conversion utility inserts one and issues a message, unless the PANEL tag specifies CMDLINE=NO.
- Only one menu-choice or model-choice list is formatted for any panel. If multiple menu-choice or model-choice lists are specified, the first one will be formatted as a menu; subsequent menu-choice or model-choice lists will be formatted as single-choice lists.

## Nested Tags

You can code the following tags within a SELFLD definition:

Tag	Name	Usage	Page	Required
CHDIV	Choice Divider	Multiple	236	No
CHOICE	Selection choice	Multiple	255	No
COMMENT	Comment	Multiple	275	No
HP	Highlighted phrase	Multiple	348	No
PS	Point-and-Shoot	Multiple	438	No
RP	Reference phrase	Multiple	454	No
SOURCE	Source	Multiple	482	No

## Example

The following application panel markup contains two selection fields. The first selection field is a single-choice selection field with the prompt text located before the selection field. The single-choice selection field can be preselected depending on the value assigned to the variable *card*.

The second selection field is a multiple-choice selection field with the prompt text located above the selection field. Choices within this field may be preselected depending on the value assigned to the CHECKVAR attribute variable specified on the respective CHOICE tags.

```

<!DOCTYPE DM SYSTEM(
  <!entity sampvar1 sysem>
  <!entity sampabc system>)>
&sampvar1;

<PANEL NAME=sel fld3 KEYLIST=keyl xmp>Library Card Registration
<AB>
&sampabc;
</AB>
<TOPINST>Type in patron's name and card number (if applicable).
<TOPINST>Then select an action bar choice.
<AREA>
  <DTAFLD DATAVAR=curdate PMTWIDTH=12 ENTWIDTH=8 USAGE=out>Date
  <DTAFLD DATAVAR=cardno PMTWIDTH=12 ENTWIDTH=7 DESWIDTH=25>Card No
    <DTAFLDD>(A 7-digit number)
  <DTAFLD DATAVAR=name PMTWIDTH=12 ENTWIDTH=25 DESWIDTH=25>Name
    <DTAFLDD>(Last, First, M.I.)
  <DTAFLD DATAVAR=address PMTWIDTH=12 ENTWIDTH=25>Address
  <DIVIDER>
  <REGION DIR=horiz>
  <SELFLD NAME=cardsel PMTWIDTH=30 SELWIDTH=40
    entwidth=1 required=yes autotab=yes>
    Choose one of the following
    <CHOICE CHECKVAR=card MATCH=new>New
    <CHOICE CHECKVAR=card MATCH=renew>Renewal
    <CHOICE CHECKVAR=card MATCH=replace>Replacement
  </SELFLD>
  <SELFLD TYPE=multi PMTWIDTH=30 SELWIDTH=36
    depth=5 init=no>
    Check valid branches
    <CHOICE NAME=north HELP=nthhlp CHECKVAR=nth>North Branch
    <CHOICE NAME=south HELP=sthhlp CHECKVAR=sth>South Branch
    <CHOICE NAME=east HELP=esthlp CHECKVAR=est>East Branch
    <CHOICE NAME=west HELP=wsthlp CHECKVAR=wst>West Branch
    <CHOICE NAME=ci ty HELP=ctyhlp CHECKVAR=cty>Ci ty Branch
    <CHOICE NAME=cnty HELP=cnthlp CHECKVAR=cnt>County Branch
  </SELFLD>
  </REGION>
</AREA>
<CMDAREA>Enter a command
</PANEL>

```

Figure 164 on page 478 shows the formatted result.

```

File Search Help
-----
Library Card Registration

Type in patron's name and card number (if applicable).

Then select an action bar choice.

Date . . . : _____
Card No . . . _____ (A 7-digit number)
Name . . . _____ (Last, First, M.I.)
Address . . . _____

Choose one of the following          Check valid branches
_ 1. New                             #SAREA37                               #
_ 2. Renewal                          #                               #
_ 3. Replacement                       #                               #
                                         #                               #

Enter a command ==> _____
F1=Help      F3=Exit      F5=Display      F6=Keyshelp      F10=Actions
F12=Cancel

```

The contents of the scrollable area are as follows:

```

)AREA SAREA37

- North Branch
- South Branch
- East Branch
- West Branch
- City Branch
- County Branch

)AREA SAREA37

```

Figure 164. Selection Fields

The following example illustrates the creation of an ISPF selection menu. The FCHOICE attribute specifies that the first selection number is 0. The choice selection for Exit is specified on the CHOICE tag. The ACTION tag for the Exit choice selection specifies both the RUN and TYPE attributes because RUN is required on the ACTION tag and TYPE is necessary to specify the ISPF selection for the generated ZSEL panel statement.

```

<!doctype dm system ()>
<!-- Sample selection menu -->
<varclass name=vc1 type='char 80'>
  <xlatl format=upper>
  </xlatl>

<varlist>
  <vardcl name=zcmd varclass=vc1>
</varlist>

<panel name=selfld2 menu keylist=keylxml>Sample Selection Panel
  <topinst>This is a selection panel.
  <selfld type=menu pmtloc=before fchoice=0 trail=nextsel
    selwidth=40 pmtwidth=10>Select an option
    <choice checkvar=xtest1 match=a>
      Selection #0 (Command Selch0)
      <action run=Selch0>
    <choice checkvar=xtest1 match=b>
      Selection #1 (Command Selch1)
      <action run=Selch1 parm='1 2 3 4'
        passlib newpool suspend>
    <choice checkvar=xtest1 match=c>
      Selection #2 (Command Selch2)
      <action run=Selch2 parm=1234>
    <choice checkvar=xtest1 match=d>
      Selection #3 (Command Selch3)
      <action run=Selch3 parm=abcd>
    <choice checkvar=xtest1 match=e>
      Selection #4 (Command Selch4)
      <action run=Selch4 parm='a b c d'>
    <choice selchar=X>
      Exit
      <action run=exit type=exit>
  </selfld>
  <cmdarea>
</panel>

```

Figure 165 shows the formatted result.





Figure 165. Selection Menu

## SL (Simple List)

The SL tag defines a simple list of items within an information region.



### COMPACT

This attribute causes the list to be formatted without a blank line between the list items.

### NOSKIP

This attribute causes the list to format without creating a blank line before the first line of the list.

### SPACE=NO | YES

The SPACE attribute controls the indentation space for the list item. When the SPACE attribute is not specified on the LI tag, the SPACE attribute from the SL tag is used to set the indentation space for the nested LI tag *item-text*.

When SPACE=YES, the indentation is set to 3 spaces. When SPACE=NO (or SPACE is not specified), the indentation is set to 4 spaces.

The SPACE attribute can be used to control the alignment of list items when the first word of some list items is a DBCS word preceded by a shift-out character and the first word of other list items is a SBCS word.

### INDENT=n

This attribute specifies that the list be indented from the current left margin.

### TEXT=SL-heading-text

This attribute causes the list to format with a heading line containing the *SL-heading-text*.

## Description

The SL tag defines a simple list of items within an information region.

Simple lists are indented lists, with no bullets, dashes, or hyphens preceding the list items. Nested lists indent four spaces to the right of the left margin of the list that contains them.

**Note:** The SPACE attribute does not affect the indentation of nested lists.

The conversion utility adds a blank line before the first item in the list.

Use the LI tag to denote each list item. See “LI (List Item)” on page 358 for more information on the LI tag.

## Conditions

- The SL tag requires an end tag.
- You must code the SL tag within an INFO definition. See “INFO (Information Region)” on page 350 for a complete description of this tag.

## Nested Tags

You can code the following tags within the SL tag:

Tag	Name	Usage	Page	Required
LI	List item	Multiple	358	No
LP	List part	Multiple	364	No

## Example

The following help panel markup contains two simple lists. The second simple list is compact, and is nested within the first list. Figure 166 shows the formatted result.

```
<!DOCTYPE DM SYSTEM>

<HELP NAME=sl WIDTH=40 DEPTH=22>Help for Shel fBrowse
<AREA>
<INFO>
  <P>Using Shel fBrowse, you can locate the following items:
  <SL>
    <LI>Audi otapes
    <LI>Books
    <LI>Periodi cal s
      <SL COMPACT>
        <LI>Newspapers
        <LI>Magazi nes
      </SL>
    <LI>Reference materi al
    <LI>Vi deotapes
  </SL>
</INFO>
</AREA>
</HELP>
```





Figure 166. Simple List

## SOURCE (Source)

The SOURCE tag defines ISPF panel logic statements within an application panel.



**TYPE=PROC | REINIT | INIT | ABCINIT | ABCPROC**

This attribute specifies the panel section that will be updated with the SOURCE tag *text*.

**text** This is the unformatted ISPF panel statement.

## Description

The SOURCE tag defines ISPF panel statements within an application panel.

Lines of text from a SOURCE tag that follows an AREA, CHOICE, DA, DTACOL, DTAFLD, HELP, LSTCOL, LSTFLD, LSTGRP, PANEL, REGION, or SELFLD tag are added to the )INIT, )REINIT, or )PROC panel section when encountered in the DTL source file.

For example, if a SOURCE tag follows the DTAFLD tag, any logic or other entries normally generated by DTAFLD would be completed before the lines within SOURCE are added.

The use of a SOURCE tag within a SELFLD tag results in the placement of the SOURCE tag lines after any logic created by the previous CHOICE tag. Additional )INIT, )REINIT, or )PROC section entries may be added when the end SELFLD tag is processed. You can control the placement of the SOURCE tag entries by nesting the SELFLD tag definition within a DTACOL tag, and placing the SOURCE tag definition either before or after the SELFLD tag definition.

Lines of text from a SOURCE tag within an action bar definition are added to:

- )ABCINIT *following* all other generated statements for that PDC tag.
- )ABCPROC *before* any other generated statements for that PDC tag.

SOURCE tags within an action bar definition must specify the TYPE as ABCINIT or ABCPROC. SOURCE tags that follow the other listed tags cannot specify TYPE as ABCINIT or ABCPROC.

When the SOURCE tag is coded within a GENERATE tag, the TYPE attribute is ignored. TYPE is automatically determined from the placement of the GENERATE tag within the DTL source file.

If the length of any line exceeds the record length of the output panel file, the conversion utility truncates the line and issues a warning message.

Text found between the SOURCE and SOURCE end tags is placed in the specified panel section as coded; that is, no formatting except entity substitution is performed. To refer to an entity within <SOURCE> tag text, the entity name is preceded by a percent (%) instead of an ampersand (&). Using the percent (%) sign avoids conflict with variable names. A valid percent sign can be specified as

“%amp;” to avoid an “entity not found” message. For example, you would refer to the TSO command “%xyz” as “%amp;xyz”.

## Conditions

- The SOURCE tag requires an end tag.
- You must code the SOURCE tag within an ABC, AREA, CHOICE, DA, DTACOL, DTAFLD, GENERATE, HELP, INFO, LSTCOL, LSTFLD, LSTGRP, PANEL, PDC, REGION, or SELFLD tag definition.

## Nested Tags

None.

## Example

```
<!DOCTYPE DM SYSTEM(
  <!entity sampvar1 sysem>
  <!entity sampabc system>)>
&sampvar1;

<PANEL NAME=source1 KEYLIST=keyl xmp>Library Card Registration
<AB>
&sampabc;
</AB>
<TOPINST>Type in patron's name and card number (if applicable)
<TOPINST>Then select an action bar choice.
<AREA>
  <DTACOL PMTWIDTH=12 ENTWIDTH=25 DESWIDTH=25 SELWIDTH=25>
  <DTAFLD DATAVAR=curdate USAGE=out ENTWIDTH=8>Date
  <DTAFLD DATAVAR=cardno ENTWIDTH=7>Card No.
  <DTAFLDD>(A 7-digit number)
  <DTAFLD DATAVAR=name>Name
  <DTAFLDD>(Last, First, M.I.)
  <DTAFLD DATAVAR=address>Address
  </DTACOL>
<DIVIDER>
<REGION DIR=horiz>
<SELFLD NAME=cardsel PMTWIDTH=30 SELWIDTH=38>Choose
one of the following
  <CHOICE CHECKVAR=card MATCH=new>New
  <CHOICE CHECKVAR=card MATCH=renew>Renewal
  <CHOICE CHECKVAR=card MATCH=replace>Replacement
  <SOURCE TYPE=proc>
  if (&cardsel = 1)
    VER (&name,nb)
    VER (&address,nb)
  </SOURCE>
</SELFLD>
<SELFLD TYPE=multi PMTWIDTH=30 SELWIDTH=25>Check valid branches
  <CHOICE NAME=north HELP=nthlp CHECKVAR=nth>North Branch
  <CHOICE NAME=south HELP=sthhlp CHECKVAR=sth>South Branch
  <CHOICE NAME=east HELP=esthlp CHECKVAR=est>East Branch
  <CHOICE NAME=west HELP=wsthlp CHECKVAR=wst>West Branch
</SELFLD>
</REGION>
</AREA>
<CMDAREA>Enter a command
</PANEL>
```

## T (Truncation)

The T tag designates the minimum command name that the user must enter to issue a command.

```
--<T>
  └─</T>─┘
```

### Description

You must code the T tag within the *external-command-name* of the CMD tag. For example, if the following command is coded in an application command table, the user could enter com, comp, compa, compar, or compare to run the command.

```
<cmd name=compare>com<t>pare
```

The command name must be at least 2 bytes.

At run time, ISPF runs the first valid command in the command table that matches the character string entered in the command area.

You should be careful to avoid specifying values that conflict with other commands. For example:

```
<cmd name=compare>co<t>mpare
<cmd name=copy>co<t>py
```

In this situation, if the user enters co as a command, ISPF will run the COMPARE command.

### Conditions

- You must code the T tag within the *external-command-name* of a CMD definition. See "CMD (Command Definition)" on page 262 for a complete description of this tag.

### Nested Tags

None.

### Example

The following source file markup contains a command table. The commands DELETE and UPDATE have truncation definitions that allow the user to enter "del" and "upd", respectively, as the minimum command name.

```
<!DOCTYPE DM SYSTEM>

<CMDTBL APPLID=conv>
  <CMD NAME=update>Upd<T>ate
    <CMDACT ACTION='alias add' >
  <CMD NAME=add>Add
    <CMDACT ACTION=setverb>
  <CMD NAME=delete>Del<T>ete
    <CMDACT ACTION=passthru>
  <CMD NAME=search>Search
    <CMDACT ACTION=passthru>
</CMDTBL>
```

The following table shows the resultant ISPF application command table.

Table 6. ISPF Application Command Table

ZCTVERB	ZCTTRUNC	ZCTACT
UPDATE	3	ALIAS ADD
ADD	0	SETVERB
DELETE	3	PASSTHRU
SEARCH	0	PASSTHRU

---

## TEXTLINE (Text Line)

The TEXTLINE tag generates a single line of text to replace the regular tag text for the HELP and PANEL tags.

—<TEXTLINE>—</TEXTLINE>—

### Description

The TEXTLINE tag encloses one or more TEXTSEG tags, used to define the parts or segments of the replacement text. Text defined by the TEXTSEG tag(s) is accumulated in a left to right order. The resulting text is used to create or replace the text portion of the HELP or PANEL tag definition.

### Conditions

- The TEXTLINE tag requires an end tag.
- You must code the TEXTLINE tag within a HELP or PANEL tag definition.

### Nested Tags

You can code the following tags within a TEXTLINE definition:

Tag	Name	Usage	Page	Required
DTAFLD	Data Field	Multiple	306	No
TEXTSEG	Text Segment	Multiple	485	Yes

### Example

See the example for “TEXTSEG (Text Segment).”

---

## TEXTSEG (Text Segment)

The TEXTSEG tag creates a text segment to be accumulated for the replacement text line created by the TEXTLINE tag.

—<TEXTSEG—  
 └─EXPAND=—AFTER—┘ └─WIDTH=—n—┘  
 └─BEFORE—┘  
 └─BOTH—┘  
 →—text—  
 └─</TEXTSEG>—┘

### EXPAND=ABOVE | BEFORE | BOTH

This attribute specifies whether expand control is added to the provided text.

## TEXTSEG

Expand characters are obtained from the HELP or PANEL tag definition, if available. If no expand character(s) have been specified on those tags, the conversion utility generates the necessary character. You may place the expand control before, after, or both before and after the text.

### **WIDTH=n**

This attribute specifies the number of bytes to reserve for the text. The default is to not allow space beyond the actual text length.

### **Text**

This is the text of the segment.

## Description

The TEXTSEG tag defines a part or segment of a replacement text line. When multiple TEXTSEG tags are present within the TEXTLINE definition, the replacement text line is created from left to right in the order the TEXTSEG tags are coded.

## Conditions

- You must code the TEXTSEG tag within a TEXTLINE tag definition.
- If the EXPAND attribute is not specified and the resulting replacement text is less than the panel width, the text will be centered as the panel title.

## Nested Tags

You can code the following tags within a TEXTSEG definition:

Tag	Name	Usage	Page	Required
HP	Highlighted Phrase	Multiple	348	No

## Example

The following example uses the TEXTLINE and TEXTSEG tags to create a special panel title that includes the system time and date. Because the EXPAND attribute is specified in the second TEXTSEG tag, the resulting title replacement text has the time and date fields placed at the left and right panel border.

```

<!doctype dm system ()>
<!-- Sample selection menu -->

<varclass name=vc1 type=' char 80' >
  <xlatl format=upper>
  </xlatl >

<varlist>
  <vardcl name=zcmd varclass=vc1>
</varlist>

<panel name=textseg1 menu keylist=keyl xmp>

  <textline>
    <textseg>&ztime
    <textseg expand=both>
      Sample Selection Panel with TEXTLINE tag
    <textseg>&zdate(8)
  </textline>

  <topinst>This is a selection panel.
  <selfld type=menu pmtloc=before fchoice=0 trail=nextsel
    selwidth=40 pmtwidth=10>Select an option
    <choice checkvar=xtest1 match=a>
      Selection #0 (Command Selch0)
    <action run=Selch0>
    <choice checkvar=xtext1 match=b>
      Selection #1 (Command Selch1)
    <action run=Selch1 parm=' 1 2 3 4' >
      passlib newpool suspend
    <choice checkvar=xtest1 match=c>
      Selection #2 (Command Selch2)
    <action run=Selch2 parm=1234>
    <choice checkvar=xtest1 match=d>
      Selection #3 (Command Selch3)
    <action run=Selch3 parm=abcd>
    <choice checkvar=xtest1 match=e>
      Selection #4 (Command Selch4)
    <action run=Selch4 parm=' a b c d' >
  <chdiv>
  <choice selchar=x>
    Exit
  <action run=exit type=exit>
</selfld>
<cmdarea>
</panel >

```

```

07:30          Sample Selection Panel with TEXTLINE tag          99/12/15
Option ==> _

This is a selection panel .

Select an
option . . . 0 Selection #0 (Command Selch0)
              1 Selection #1 (Command Selch1)
              2 Selection #2 (Command Selch2)
              3 Selection #3 (Command Selch3)
              4 Selection #4 (Command Selch4)

              X Exit

```

---

## TOPINST (Top Instruction)

The TOPINST tag defines top instructions for an application panel.

```

--<TOPINST-->
  [COMPACT]
  [instruction-text]
  </TOPINST>

```

### COMPACT

This attribute causes the top instruction to format without a blank line after the text.

### instruction-text

This is the text of the top instruction. The *instruction-text* must fit in the remaining panel depth.

## Description

The TOPINST tag defines top instructions for an application panel. The *instruction-text* formats as a paragraph based on the width of the application panel. You can code multiple paragraphs of instruction text by using a new top instruction tag for each new paragraph.

If the COMPACT attribute is not specified, the conversion utility inserts a blank line after the top instruction text.

## Conditions

- You must code the TOPINST within a PANEL definition. See “PANEL (Panel)” on page 413 for a complete description of this tag.
- You cannot code a TOPINST tag within an AREA definition. If you define an area for the panel, code the TOPINST tag before the AREA start tag.

## Nested Tags

You can code the following tags within a TOPINST definition:

Tag	Name	Usage	Page	Required
HP	Highlighted phrase	Multiple	348	No
PS	Point-and-Shoot	Multiple	438	No
RP	Reference phrase	Multiple	454	No

## Example

The following application panel markup contains top instructions. Figure 167 on page 491 shows the formatted result.

## TOPINST

```
<!DOCTYPE DM SYSTEM>

<VARCLASS NAME=selcls TYPE='CHAR 2'>
<VARLIST>
  <VARDCL NAME=loc VARCLASS=selcls>
  <VARDCL NAME=mode VARCLASS=selcls>
</VARLIST>

<PANEL NAME=topinst HELP=trvlhlp WIDTH=60 DEPTH=22 KEYLIST=keyl xmp>
Dream Vacation Guide
<AB>
  <ABC>File
    <PDC>Add Entry
      <ACTION RUN=add>
    <PDC>Delete Entry
      <ACTION RUN=delete>
    <PDC>Update Entry
      <ACTION RUN=update>
    <PDC>Exit
      <ACTION RUN=exit>
  <ABC>Help
    <PDC>Extended Help...
      <ACTION RUN=exhlp>
    <PDC>Keys Help...
      <ACTION RUN=keyshlp>
</AB>
<TOPINST>Choose one of the following exotic locations and
your preferred mode of travel, then press Enter.
<AREA>
  <REGION DIR=horiz>
  <SELFLD NAME=loc PMTWIDTH=23 SELWIDTH=25>Exotic Location:
    <CHOICE>Athens, GA
    <CHOICE>Berlin, CT
    <CHOICE>Cairo, IL
    <CHOICE>Lizard Lick, NC
    <CHOICE>Paris, TX
    <CHOICE>Rome, NY
    <CHOICE>Venice, FL
  </SELFLD>
  <DIVIDER>
  <SELFLD NAME=mode PMTWIDTH=25 SELWIDTH=25>Travel Mode:
    <CHOICE>Boxcar
    <CHOICE>Hi tchhi ke
    <CHOICE>Mule
  </SELFLD>
  </REGION>
</AREA>
<CMDAREA>
</PANEL>
```





Figure 167. Top Instructions

## UL (Unordered List)

The UL tag defines an unordered list of items within an information region.



### COMPACT

This attribute causes the list to be formatted without a blank line between the list items.

### NOSKIP

This attribute causes the list to format without creating a blank line before the first line of the list.

### SPACE=NO | YES

The SPACE attribute controls the indentation space for the list item. When the SPACE attribute is not specified on the LI tag, the SPACE attribute from the UL tag is used to set the indentation space for the nested LI tag *item-text*.

When SPACE=YES, the indentation is set to 3 spaces. When SPACE=NO (or SPACE is not specified), the indentation is set to 4 spaces.

The SPACE attribute can be used to control the alignment of list items when the first word of some list items is a DBCS word preceded by a shift-out character and the first word of other list items is a SBCS word.

### INDENT=n

This attribute specifies that the list be indented from the current left margin.

### TEXT=UL-heading-text

This attribute causes the list to format with a heading line containing the *UL-heading-text*.

## Description

The UL tag defines an unordered list of items within an information region. Unordered lists format as indented lists, with the list item identifier at the left margin. Nested lists indent four spaces to the right of the left margin of the list that contains them.

**Note:** The SPACE attribute does not affect the indentation of nested lists.

The conversion utility adds a blank line before the first item in the list. There are three levels of item identifiers: bullets (o), hyphens (-), and dashes (--). Each level is used successively when you nest unordered lists.

Panels formatted with the DBCS option use an uppercase 'O' as the bullet character.

Use the LI tag to denote each list item. See "LI (List Item)" on page 358 for more information on the LI tag.

## Conditions

- The UL tag requires an end tag.
- You must code the UL tag within an INFO definition. See "INFO (Information Region)" on page 350 for a complete description of this tag.

## Nested Tags

You can code the following tags within a UL definition:

Tag	Name	Usage	Page	Required
LI	List item	Multiple	358	No
LP	List part	Multiple	364	No

## Example

The following help panel markup contains two unordered lists. The second unordered list is nested within the second list item of the first unordered list. Figure 168 on page 493 shows the formatted result.

```

<!DOCTYPE DM SYSTEM>

<HELP NAME=ul DEPTH=22>Help for Reference Section
<AREA>
<INFO>
  <P>Learn everything about anything,
  and more, in our Reference section.
  Our Reference section includes:
  <UL>
    <LI>Atlases
    <LI>Dictionaries
      <UL COMPACT>
        <LI>English
        <LI>Other Languages
      </UL>
    <LI>Encyclopedias
    <LI>How-to books
    <LI>Magazines and periodicals
  </UL>
</INFO>
</AREA>
</HELP>

```





Figure 168. Unordered List

## VARCLASS (Variable Class)

The VARCLASS tag defines information related to a class of variables.

—<VARCLASS—NAME=variable-class-name—

## VARCLASS



### **NAME=variable-class-name**

This attribute specifies the name of this variable class.

The *variable-class-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

### **TYPE=type of data**

This attribute specifies the data type and display length characteristics for variables that refer to the variable class.

For data fields and list columns, the conversion utility uses the lengths specified in this attribute when CHOFLD or DTAFLD ENTWIDTH or LSTCOL COLWIDTH attributes cannot otherwise be determined. The lengths specified control the width of the data field in the panel.

The allowable TYPE values are:

#### **'CHAR maximum-length'**

This specifies a character string for which the maximum length, in bytes, is given by *maximum-length*.

#### **'DBCS maximum-length'**

This is a double-byte character string for which the maximum length, in bytes, is given by *maximum-length*. The maximum length must be an even number.

#### **'MIXED maximum-length'**

This specifies a character string containing single-byte characters, double-byte characters, or both for which the maximum length, in bytes, is given by *maximum-length*. Strings of DBCS characters are delimited by shift-out (SO) and shift-in (SI) codes.

#### **'ANY maximum-length'**

This attribute is processed by the conversion utility as TYPE=MIXED.

#### **'EBCDIC maximum-length'**

This specifies a character string containing only single-byte characters for which the maximum length, in bytes, is given by *maximum-length*.

#### **'%varname maximum-length'**

This specifies a variable name will be used to define the type of character string. The maximum length, in bytes, is given by *maximum-length*. It is the

responsibility of the application developer to ensure that %varname contains a valid TYPE value before attempting to display the panel.

**ITIME**

The conversion utility will add a "VEDIT (*variable*)" statement to the )PROC section of the panel for variables which are related to this VARCLASS. The default length value of ITIME is set by the conversion utility to 5.

**STDTIME**

The conversion utility will add a "VEDIT (*variable*)" statement to the )PROC section of the panel for variables which are related to this VARCLASS. The default length value of STDTIME is set by the conversion utility to 8.

**IDATE**

The conversion utility will add a "VEDIT (*variable*)" statement to the )PROC section of the panel for variables which are related to this VARCLASS. The default length value of IDATE is set by the conversion utility to 8.

**STDDATE**

The conversion utility will add a "VEDIT (*variable*)" statement to the )PROC section of the panel for variables which are related to this VARCLASS. The default length value of STDDATE is set by the conversion utility to 10.

**JDATE**

This attribute is supported as an ISPF extension to the Dialog Tag Language. The conversion utility will add a "VEDIT (*variable*)" statement to the )PROC section of the panel for variables which are related to this VARCLASS. The default length value of JDATE is set by the conversion utility to 6.

**JSTD**

This attribute is supported as an ISPF extension to the Dialog Tag Language. The conversion utility will add a "VEDIT (*variable*)" statement to the )PROC section of the panel for variables which are related to this VARCLASS. The default length value of JSTD is set by the conversion utility to 8.

**'VMASK maximum-length'**

This attribute is supported as an ISPF extension to the Dialog Tag Language. The VMASK attribute is provided to support the user mask option the ISPF VMASK service. The *maximum-length* value is limited to the ISPF maximum of 20. The conversion utility will add a "VEDIT (*variable*)" statement to the )PROC section of the panel for variables which are related to this VARCLASS.

**'NUMERIC total-digits 0 | fractional-digits'**

This attribute allows you to check to see if the user has entered a valid number. A valid number can include thousands separators, a decimal separator, and a sign. The conversion utility builds the VER(variable ENUM) statement to perform numeric validation. The value specified for *total-digits* must not be greater than 16.

The *total-digits* and *fractional-digits* are used to determine a *maximum-length* value which is used for field entry width, if necessary, in DTAFD and

## VARCLASS

LSTCOL processing. For example, 'NUMERIC 8 2' defines a width of 11, composed of 8 possible digits, a decimal point, a thousands separator, and a leading sign.

**Note:** ISPF does not check to verify proper positioning of the decimal point. Refer to the discussion on VER(variable ENUM) in the *ISPF User's Guide* for more information.

### **MSG=message-identifier**

This attribute indicates the default message to be displayed if the variable fails any of the enclosed checks. See "MSG (Message)" on page 390 for information on creating messages.

## Description

The VARCLASS tag defines information related to a class of variables. You can group validation and translation checks you want ISPF to perform within one VARCLASS definition. You point to the VARCLASS definition from one or more VARDCL tags you code within the VARLIST definition.

**Note:** The ISPF Dialog Tag Language conversion utility does not require that you code the VARCLASS, VARDCL, or VARLIST tags for a successful generation of a panel, command table, or message member that includes variables. If the conversion utility finds a variable that does not have an associated VARDCL definition, it issues a warning message.

The use of the VARCLASS, VARDCL, and VARLIST tags is required if you want to use the facilities provided by the CHECKL and XLATL tags.

## Conditions

- You cannot code the VARCLASS tag within any other tag definition.
- You must code the VARCLASS tag before any other tag within the source file that refers to it.
- Within the variable class definition, you must code any and all XLATL tags before any CHECKL tags.

## Nested Tags

You can code the following tags within a VARCLASS definition:

Tag	Name	Usage	Page	Required
CHECKL	Check list	Multiple	247	No
XLATL	Translate list	Multiple	506	No

## Example

The following example contains two variable classes. The first variable class provides an alphabetic validity check. The second variable class provides input translation to uppercase and validates that the input is one of the listed values. Also shown in the markup are two input data fields (within a PANEL definition) that refer to the variable declarations associated with the variable classes.



## Conditions

- You must code the VARDCL tag within a VARLIST tag. See “VARLIST (Variable List)” on page 499 for a complete description of this tag.

## Nested Tags

None.

## Example

The following source file markup contains variable declarations for all of the variables defined in the panel definition. The declared variables include:

- The variable *whchsrch* specified in the CHECKVAR attributes associated with the pull-down choices of the **Search** action bar choice.
- The data field variables *curdate*, *cardno*, *name*, and *address*.
- The variable *cardsel*, which is the entry-field of the single-choice selection field.
- The variables *north*, *south*, *east*, and *west*, which are the entry-fields associated with the multiple-choice selection field.
- The variables defined as the check variables (CHECKVAR attribute) for the selection fields.

```
<!DOCTYPE DM SYSTEM(
  <!entity sampabc sysem>
  <!entity sampbody system>)>

<VARCLASS NAME=date    TYPE=' char 8' >
<VARCLASS NAME=numcls  TYPE=' numeric 7' >
<VARCLASS NAME=namecls TYPE=' char 25' >
<VARCLASS NAME=char1cls TYPE=' char 1' >
<VARCLASS NAME=char7cls TYPE=' char 7' >

<VARLIST>
  <VARDCL NAME=whchsrch VARCLASS=char1cls>
  <VARDCL NAME=curdate  VARCLASS=date>
  <VARDCL NAME=cardno   VARCLASS=numcls>
  <VARDCL NAME=name     VARCLASS=namecls>
  <VARDCL NAME=address  VARCLASS=namecls>
  <VARDCL NAME=cardsel  VARCLASS=char1cls>
  <VARDCL NAME=card     VARCLASS=char7cls>
  <VARDCL NAME=north    VARCLASS=char1cls>
  <VARDCL NAME=south    VARCLASS=char1cls>
  <VARDCL NAME=east     VARCLASS=char1cls>
  <VARDCL NAME=west     VARCLASS=char1cls>
  <VARDCL NAME=nth      VARCLASS=char1cls>
  <VARDCL NAME=sth      VARCLASS=char1cls>
  <VARDCL NAME=est      VARCLASS=char1cls>
  <VARDCL NAME=wst      VARCLASS=char1cls>
</VARLIST>

<PANEL NAME=vardcl>Library Card Registration
<AB>
&sampabc;
</AB>
&sampbody;
</PANEL>
```

## VARLIST (Variable List)

The VARLIST tag provides the means to code VARDCL tags in a single list.

—<VARLIST>—</VARLIST>—

### Description

The VARLIST tag provides the means to code VARDCL tags in a single list. The VARDCL tags coded within a VARLIST definition declare variables that are referred to in the dialog element definitions within a DTL source file.

**Note:** The ISPF Dialog Tag Language conversion utility does not require that you code the VARCLASS, VARDCL, or VARLIST tags for a successful generation of a panel, command table, or message member that includes variables. If the conversion utility finds a variable that does not have an associated VARDCL definition, it issues a warning message.

The use of the VARCLASS, VARDCL, and VARLIST tags is required if you want to use the facilities provided by the CHECKL and XLATL tags.

### Conditions

- The VARLIST tag requires an end tag.
- You cannot code the VARLIST tag within any other tag definition.
- You can code the VARLIST tag immediately after any and all VARCLASS tags within the DTL source file and before any tag definitions that refer to the variables declared in the variable list.

### Nested Tags

You code the following tag within a VARLIST definition:

Tag	Name	Usage	Page	Required
VARDCL	Variable declaration	Multiple	499	No

### Example

The following source file markup contains a variable list. The variable declarations within the list define variables for the fields within the PANEL definitions that refer to them.

## VARSUB

```
<!DOCTYPE DM SYSTEM>

<VARCLASS NAME=char8 TYPE='char 8'>
<VARCLASS NAME=name TYPE='char 25'>
<VARCLASS NAME=phoncls TYPE='char 12'>
<VARCLASS NAME=apcls TYPE='char 1'>
  <XLATL FORMAT=upper>
  </XLATL>
<CHECKL>
  <CHECKI TYPE=values PARM1=EQ PARM2='Y N'>
</CHECKL>

<VARLIST>
  <VARDCL NAME=curdate VARCLASS=char8>
  <VARDCL NAME=namevar VARCLASS=name>
  <VARDCL NAME=passvar VARCLASS=char8>
  <VARDCL NAME=xlname VARCLASS=name>
  <VARDCL NAME=xphone VARCLASS=phoncls>
  <VARDCL NAME=xapp VARCLASS=apcls>
</VARLIST>

<PANEL NAME=varlist1 KEYLIST=keyl xmp>System Log On
<TOPINST>Complete the following fields, then press Enter.
<AREA>
  <DTACOL PMTWIDTH=12>
    <DTAFD DATAVAR=curdate ENTWIDTH=8 USAGE=out>Date
    <DTAFD DATAVAR=namevar ENTWIDTH=25 DESWIDTH=15>Name
    <DTAFD DATAVAR=passvar ENTWIDTH=8 DISPLAY=no>Password
  </DTACOL>
</AREA>
</PANEL>

<PANEL NAME=varlist2 DEPTH=14 KEYLIST=keytbl>Subscriber List
<TOPINST>Enter phone number, if missing,
(format - nnn-xxx-nxxx) and approved
indicator (y or n) for each person.
<AREA>
  <LSTFLD>
    <LSTCOL DATAVAR=xlname USAGE=out COLWIDTH=25>Last Name
    <LSTCOL DATAVAR=xphone COLWIDTH=12>Phone Number
  <LSTGRP>Approved
    <LSTCOL DATAVAR=xapp USAGE=in REQUIRED=yes
      COLWIDTH=1 MSG=msgv886>(Y or N)
  </LSTGRP>
</LSTFLD>
</AREA>
<CMDAREA>Enter a command
</PANEL>
```

---

## VARSUB (Variable Substitution)

The VARSUB tag specifies a variable to substitute in message text.

—<VARSUB—VAR=variable-name—>

└─</VARSUB>─┘

### VAR=variable-name

This attribute specifies the variable whose value is substituted within the message.

The *variable-name* should be declared with a VARDCL tag.

The *variable-name* must follow the standard naming convention described in “Rules for Variable Names” on page 205.

## Description

The VARSUB tag specifies a variable to substitute in message text. You use the required VAR attribute to specify the variable whose value is resolved and inserted into the message text when the message is displayed. The value coded must be a variable name without leading % notation.

You can code the VARSUB tag in the *message-text* of a MSG tag. The variable value is inserted by ISPF at run time at the position in the message text where the VARSUB tag is coded.

For example, assume the following VARSUB tag was coded within the text of this message:

```
<msgmbr name=abca00>
<msg suffix=1 msgtype=warning>Invalid name,
"<VARSUB VAR=LASTN>", specified.
The name may contain only alphabetic characters.
</msgmbr>
```

When a dialog refers to a message *abca001* (with a GETMSG, SETMSG, DISPLAY, or TBDISPL service call) or the message is displayed by ISPF during panel validation, the value of *lastn* is retrieved and inserted into the message text. The message after substitution would appear as follows:

```
Invalid name, "Jones1", specified.
The name may contain only alphabetic characters.
```

## Conditions

- You must code the VARSUB tag within the text of a MSG definition. See "MSG (Message)" on page 390 for a complete description of this tag.
- The value specified by the VAR attribute should be declared with a VARDCL tag. See "VARDCL (Variable Declaration)" on page 497 for a complete description of this tag.

## Nested Tags

None.

## Example

The following markup contains a message member which contains nine MSG definitions. The text of messages *MSGV883* and *MSGV888* contain variable substitutions. Figure 169 on page 502 shows the generated message member.

## VARSUB

```
<!DOCTYPE DM SYSTEM>

<VARCLASS NAME=msgcls TYPE='char 20' >
<VARLIST>
  <VARDCL NAME=phoneno VARCLASS=msgcls>
  <VARDCL NAME=cnum VARCLASS=msgcls>
</VARLIST>

<MSGMBR NAME=msgv88>
  <MSG SUFFIX=1>Name must be alphabetic.
  <MSG SUFFIX=2>Enter only number of days.
  <MSG SUFFIX=3 MSGTYPE=critical>The only rooms we have available
  are either SINGLE or DOUBLE. Please call the manager of the hotel
  who will arrange equivalent lodging at another
  hotel in the area. This is our mistake, and we will, of course,
  pick up the bill. Please call collect <VARSUB VAR=phoneno>.
  <MSG SUFFIX=4 MSGTYPE=action LOCATION=modal>Please enter either
  BIGCHARGE, V I S T A, EZCARD, CHECK, or CASH.
  <MSG SUFFIX=5 MSGTYPE=warning LOCATION=modelless>Please enter your name.
  <MSG SUFFIX=6>Please enter Y or N.
  <MSG SUFFIX=7>Card number is a seven-digit number.
  <MSG SUFFIX=8 MSGTYPE=warning>The card number you
  entered, <VARSUB VAR=cnum> is not valid.
  <MSG SUFFIX=9>Message '9' contains embedded quotes.
</MSGMBR>
```

```
MSGV881 .TYPE=NOTIFY
'Name must be alphabetic.'
MSGV882 .TYPE=NOTIFY
'Enter only number of days.'
MSGV883 .TYPE=CRITICAL
'The only rooms we have available are either SINGLE or DOUBLE. Please call th' +
'e manager of the hotel who will arrange equivalent lodging at another hotel ' +
'in the area. This is our mistake, and we will, of course, pick up the bill. ' +
'Please call collect &PHONENO.'
MSGV884 .TYPE=ACTION .WINDOW=RESP
'Please enter either BIGCHARGE, V I S T A, EZCARD, CHECK, or CASH.'
MSGV885 .TYPE=WARNING .WINDOW=NORESP
'Please enter your name.'
MSGV886 .TYPE=NOTIFY
'Please enter Y or N.'
MSGV887 .TYPE=NOTIFY
'Card number is a seven-digit number.'
MSGV888 .TYPE=WARNING
'The card number you entered, &CNUM is not valid.'
MSGV889 .TYPE=NOTIFY
'Message '9' contains embedded quotes.'
```

Figure 169. Variable Substitution

## WARNING (Warning)

The WARNING tag defines text that alerts the user to a risk of possible error conditions in the system.

```
—<WARNING>—┬──</WARNING>—
               └──text──┘
```

**text** This is the text of the warning.

## Description

The WARNING tag defines text that alerts the user to a risk of possible error conditions in the system.

The WARNING tag is one of the tags that alert the user of a possible risk; the others are the CAUTION tag and the ATTENTION tag.

Code a warning statement before the text to which it pertains so that the user can read about the possible risks before reading the text.

When a warning statement is displayed, the string “Warning:” (or its translated equivalent) appears on the screen before the text of the warning statement.

You can code additional paragraphs of warning text by coding the P (paragraph) tag within a WARNING definition. You can also code other tags allowed in an information area within a WARNING definition.

## Conditions

- The WARNING tag requires an end tag.
- You must code the WARNING tag within an INFO definition. See “INFO (Information Region)” on page 350 for a complete description of this tag.
- The WARNING tag must be immediately preceded by a P, LI, or LP tag. If the WARNING tag is coded on the same line as one of these tags, there can be no intervening blanks. See “P (Paragraph)” on page 406, “LI (List Item)” on page 358, and “LP (List Part)” on page 364 for descriptions of these tags.
- You cannot nest WARNING, ATTENTION, or CAUTION tags within each other.

## Nested Tags

You can code the following tags within a WARNING definition:

Tag	Name	Usage	Page	Required
DL	Definition list	Multiple	292	No
FIG	Figure	Multiple	324	No
HP	Highlighted phrase	Multiple	348	No
LINES	Lines	Multiple	360	No
NOTE	Note	Multiple	396	No
NOTEL	Note List	Multiple	399	No
NT	Note	Multiple	402	No
OL	Ordered list	Multiple	404	No
P	Paragraph	Multiple	406	No
PARML	Parameter list	Multiple	424	No
PS	Point-and-Shoot	Multiple	438	No
RP	Reference phrase	Multiple	454	No
SL	Simple list	Multiple	480	No
UL	Unordered list	Multiple	491	No
XMP	Example	Multiple	508	No

## WARNING

### Example

The following help panel markup contains a warning statement. The warning statement starts at the left margin because it is embedded in the LP tag.

```
<!DOCTYPE DM SYSTEM>

<HELP NAME=warning DEPTH=20>Help For Changing a File
<AREA>
<INFO>
  <OL>
    <LI>Type over the existing data
      in the entry fields with the new data.
      <LP><WARNING>Performing the next step will save
        all changes and delete the existing data.
      <P>To quit this function without
        deleting the existing data, press F12.
      </WARNING>
    <LI>Press Enter to save the
      updated data.
  </OL>
</INFO>
</AREA>
</HELP>
```




Figure 170. Warning Statement

---

## XLATI (Translate Item)

The XLATI tag defines an individual list element in a translate list.

```
—<XLATI—>—  
  |_____| |_____| |_____|  
  VALUE=internal-value displayed-value </XLATI>
```

### VALUE=internal-value

ISPF saves this value in the variable pool when translating on input and retrieves it from the variable pool when translating on output. If the *internal-value* contains characters other than A–Z, a–z, and 0–9, you must enclose the value in quotes.

Omitting this attribute indicates that any value is acceptable. When translating on input, ISPF does not translate the *displayed-value* before storing it in the pool. When translating on output, ISPF translates to the *displayed-value* any value that is not already matched.

#### displayed-value

This attribute specifies the displayed value that must be matched when doing a translation on input and the result when doing a translation on output. The test for a translation match is case-sensitive. Any characters, including embedded blanks, are allowed in the *displayed-value*. If the value has blanks that you want preserved, or the value consists of only blanks, the value should be coded within the LIT (Literal) tag. If the LIT tag is not used, all blanks will be stripped and any value with only blanks will indicate that no value was specified.

Omitting this value indicates that any value is acceptable. When translating on output, this means that the *internal-value* is not to be translated before being displayed. When translating on input, it means that any value not already matched is to translate to the *internal-value*.

## Description

The XLATI tag defines an individual list element in a translate list. As many XLATI tags as are necessary (up to a limit of 126) to accomplish the desired translation can be included within the translation list.

Each XLATI tag provides information necessary to translate a *displayed-value* to an *internal-value* and vice versa. Translation is done in the order given by the tags. Translation stops when a match is found. An XLATI tag that omits both *internal-value* and *displayed-value* has the following effect: when translating on output the variable value is displayed, and when translating on input the entered value is stored in the variable.

The ISPF TRANS() function will be used for all translations. When translating on output, ISPF )INIT panel logic translates the *internal-value* to the *displayed-value*. When translating on input, ISPF )PROC panel logic translates the *displayed-value* to the *internal-value*. The test for a translation match is case-sensitive. You can code an XLATL FORMAT=UPPER definition before an XLATL definition that contains XLATI tags to convert user input to uppercase before the translate list is processed.

## Conditions

You must code the XLATI tag within an XLATL definition. See “XLATI (Translate Item)” on page 504 for a complete description of this tag.

## Nested Tags

You can code the following tag within an XLATI definition:

Tag	Name	Usage	Page	Required
LIT	Literal	Multiple	362	No

## Example

The following source file markup contains a variable class with a translate list that performs input and output translation on values assigned to the winter months. The associated variable declarations and fields are also shown.

## XLATL

```
<!DOCTYPE DM SYSTEM>

<VARCLASS NAME=monthcls type='char 3'>
  <XLATL FORMAT=upper>
  </XLATL>
  <XLATL MSG=abcd003>
    <XLATI VALUE=11>NOV
    <XLATI VALUE=12>DEC
    <XLATI VALUE=01>JAN
    <XLATI VALUE=02>FEB
    <XLATI VALUE=03>MAR
  </XLATL>

<VARCLASS NAME=costcls TYPE='numeric 6' MSG=abcd001>

<VARCLASS NAME=typecls TYPE='char 4'>
  <XLATL FORMAT=upper>
  </XLATL>
  <CHECKL MSG=abcd002>
    <CHECKI TYPE=values Parm1=EQ Parm2='GAS OIL ELEC'>
  </CHECKL>

<VARLIST>
  <VARDCL NAME=month VARCLASS=monthcls>
  <VARDCL NAME=cost VARCLASS=costcls>
  <VARDCL NAME=heat VARCLASS=typecls>
</VARLIST>


<PANEL NAME=xlati KEYLIST=keylxml>Heating Cost Survey
  <TOPINST>Complete the information below and then press Enter.
  <AREA>
    <DTACOL PMTWIDTH=20 DESWIDTH=30>
      <DTAFLD DATAVAR=month ENTWIDTH=3>Winter month
      <DTAFLDD>Enter Nov, Dec, Jan, Feb, or Mar
      <DTAFLD DATAVAR=cost ENTWIDTH=6>Heating cost
      <DTAFLD DATAVAR=heat ENTWIDTH=4>Type of heating
      <DTAFLDD>Enter Oil, Gas, or Elec
    </DTACOL>
  </AREA>
  <BOTINST>Thank you for your participation.
</PANEL>

<MSGMBR NAME=abcd00>
  <MSG SUFFIX=1>Heating cost must be numeric
  <MSG SUFFIX=2>Type of heating must be "Gas", "Oil", or "Elec"
  <MSG SUFFIX=3>Winter month must be "Nov", "Dec", "Jan", "Feb", or "Mar"
</MSGMBR>
```

---

## XLATL (Translate List)

The XLATL tag defines a translate list for a variable class.



### FORMAT=NONE | UPPER

This attribute defines the type of translation. NONE specifies that enclosed

XLATI tags are to be used to translate the value on an item for item basis. UPPER specifies that the variable value is translated to uppercase.

#### **TRUNC=n | char**

This attribute defines the type of truncation to be performed on input values. It is valid only when FORMAT=NONE. If a number is provided, truncation occurs at the length indicated. If a nonnumeric character is provided, truncation occurs at the first occurrence of that character.

#### **MSG=message-identifier**

This attribute specifies the ID of a message to be issued for the error condition that results when an input translation fails because the user entered a value not specified in the list. Specifying an XLATI tag with no *internal-value* and no *displayed-value* ensures that any value not in the list is accepted without error. If no message ID is specified and an error occurs, the *message-identifier* specified on the VARCLASS tag is used. If no *message-identifier* is specified on the XLATL tag or the VARCLASS tag, no message is displayed.

**Note:** This message is not used if translation on output fails. The variable value is displayed as is, subject to whatever size restrictions apply to the field.

## Description

The XLATL tag defines a translate list for a variable class. XLATI tags, which define the elements of the translation list, are coded within the XLATL tag. A translation list is defined within a VARCLASS tag.

If FORMAT=NONE is specified, it is expected that there are XLATI tags within the XLATL definition. If FORMAT=UPPER is specified, no XLATI tags are accepted in the XLATL definition.

Translation lists are optional and provide a means of translating between a displayed value and the internal value of the variable. Translation can occur on input (the translation result is stored in the variable pool), on output (the value from the pool is translated before the user sees it), or both, depending on the USAGE attribute of the DTAFLD tag that is associated with the variable. Translation for table display is not supported by ISPF. Refer to the *ISPF Dialog Developer's Guide and Reference* for additional information about the TRANS function.

## Conditions

- The XLATL tag requires an end tag.
- You must code the XLATL tag within a VARCLASS definition. See “VARCLASS (Variable Class)” on page 493 for a complete description of this tag.
- You must code any and all XLATL tags before any CHECKL tags in the same variable class.

## Nested Tags

You can code the following tag within the XLATL tag:

Tag	Name	Usage	Page	Required
XLATI	Translate item	Multiple	504	Yes

## Example

The following source file markup includes translation of user input for *monthcls* to uppercase followed by a translation list of the abbreviated month to an internal value. If no match is found, message *abcd003* is issued. The example also shows the use of uppercase translation before a check for a list of values for **Type of heating**.

```
<!DOCTYPE DM SYSTEM>

<VARCLASS NAME=monthcls type='char 3'>
  <XLATL FORMAT=upper>
  </XLATL>
  <XLATL MSG=abcd003>
    <XLATI VALUE=11>NOV
    <XLATI VALUE=12>DEC
    <XLATI VALUE=01>JAN
    <XLATI VALUE=01>FEB
    <XLATI VALUE=03>MAR
  </XLATL>

<VARCLASS NAME=costcls TYPE='numeric 6' MSG=abcd001>

<VARCLASS NAME=typecls TYPE='char 4'>
  <XLATL FORMAT=upper>
  </XLATL>
  <CHECKL MSG=abcd002>
    <CHECKI TYPE=values Parm1=EQ Parm2='GAS OIL ELEC'>
  </CHECKL>

<VARLIST>
  <VARDCL NAME=month VARCLASS=monthcls>
  <VARDCL NAME=cost VARCLASS=costcls>
  <VARDCL NAME=heat VARCLASS=typecls>
</VARLIST>

<PANEL NAME=xlatl KEYLIST=keyl xmp>Heating Cost Survey
  <TOPINST>Complete the information below and then press Enter.
  <AREA>
    <DTACOL PMTWIDTH=20 DESWIDTH=30>
      <DTAFLD DATAVAR=month ENTWIDTH=3>Winter month
      <DTAFLDD>Enter Nov, Dec, Jan, Feb, or Mar
      <DTAFLD DATAVAR=cost ENTWIDTH=6>Heating cost
      <DTAFLD DATAVAR=heat ENTWIDTH=4>Type of heating
      <DTAFLDD>Enter Oil, Gas, or Elec
    </DTACOL>
  </AREA>
  <BOTINST>Thank you for your participation.
</PANEL>

<MSGMBR NAME=abcd00>
  <MSG SUFFIX=1>Heating cost must be numeric
  <MSG SUFFIX=2>Type of heating must be "Gas", "Oil", or "Elec"
  <MSG SUFFIX=3>Winter month must be "Nov", "Dec", "Jan", "Feb", or "Mar"
</MSGMBR>
```

---

## XMP (Example)

The XMP tag defines unformatted text within an information region.

```
—<XMP [NOSKIP] text </XMP>—
```

**NOSKIP**

This attribute causes the blank line normally placed before the example to be skipped.

**text**

This is the text of the example.

**Description**

The XMP tag defines unformatted text within an information region.

Text coded between the XMP start and end tags is indented two spaces and formats from the current left margin. Tags which normally cause word-wrapping (for example, P and LI) will not cause word-wrapping when nested within an XMP tag.

When defining text for an example in your source file, you should be careful not to exceed the width of the information region it is coded within. If the source text on any line exceeds the formatting width, the conversion utility truncates the line. A warning message is issued the first time truncation occurs.

**Conditions**

- The XMP tag requires an end tag.
- You must code the XMP tag within an INFO definition. See “INFO (Information Region)” on page 350 for a complete description of this tag.
- You can code multiple XMP tags within an INFO definition, as long as they are not nested within each other.

**Nested Tags**

You can code the following tags within an XMP definition:

Tag	Name	Usage	Page	Required
DL	Definition list	Multiple	292	No
HP	Highlighted phrase	Multiple	348	No
NOTE	Note	Multiple	396	No
NOTEL	Note List	Multiple	399	No
NT	Note	Multiple	402	No
OL	Ordered list	Multiple	404	No
P	Paragraph	Multiple	406	No
PARML	Parameter list	Multiple	424	No
PS	Point-and-Shoot	Multiple	438	No
RP	Reference phrase	Multiple	454	No
SL	Simple list	Multiple	480	No
UL	Unordered list	Multiple	491	No

**Example**

The following help panel markup contains an example. Figure 171 on page 510 shows the formatted result.

## XMP

```
<!DOCTYPE DM SYSTEM>

<HELP NAME=xmp WIDTH=40 DEPTH=20>Help for the Search Function
<AREA>
<INFO>
  <P>To locate a book, type the book
  title in the "Title" field and press Enter.
  <P>Example:
  <XMP>
  Title:  THE JOY OF CODING
  </XMP>
  <P>You don't have to worry about using
  upper or lowercase letters; all text is automatically
  converted to uppercase for the search.
</INFO>
</AREA>
</HELP>
```




Figure 171. Example

---

## Part 3. Appendixes



## Appendix. Dialog Tag Language (DTL) Tags

### Tag Summary

The following table is an alphabetic summary of the supported Dialog Tag Language (DTL) tags for z/OS V1R6.0 ISPF. The table shows the tag, tells whether an end tag is required (Yes) or optional (No), and lists the tag's attributes (if any) and the tag content (if any) in italics. The table also lists which tags you can nest within the tag, as well as which tags you can code the tag within.

Table 7. Tag summary

Tag	End tag	Attributes	Nested tags	Used within
AB	Yes	MNEMGEN= <u>YES</u>   NO ABSEPSTR=ab-separator-string ABSEPCHAR=ab-separator-character	ABC	PANEL
ABC	No	HELP= <u>NO</u>   YES   help-panel-name   *help-message-id   %varname   *%varname PDCVAR=fdc-variable-name <i>choice-description-text</i>	COMMENT M PDC PDSEP SOURCE	AB
ACTION	No	RUN=internal-command-name   %varname PARM=parameters   %varname APPLCMD= <u>NO</u>   YES TYPE= <u>CMD</u>   PGM   PANEL   WSCMD   WSCMDV   EXIT NEWAPPL   NEWAPPL=application-id NEWWINDOW PASSLIB NEWPOOL SUSPEND SCRNAME=screen-name NOCHECK ADDPop OPT=option   %varname MODE= <u>LINE</u>   FSCR LANG=APL   CREX BARRIER NEST WSDIR=ws-directory WSINVOKE= <u>MODELESS</u>   MODAL WSSIZE= <u>MAX</u>   MIN WSVIEW= <u>VIS</u>   INVIS SETVAR=variable-name VALUE= <u>1</u>   string   %varname TOGVAR=variable-name VALUE1= <u>0</u>   string   %varname VALUE2= <u>1</u>   string   %varname		CHOICE PDC

## Summary of DTL Tags

Table 7. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
AREA	Yes	MARGINW= <u>1</u>   n MARGIND= <u>0</u> INDENT=n DEPTH=n   * EXTEND=OFF   ON   FORCE DIV= <u>NONE</u>   BLANK   SOLID   DASH   TEXT DIVWIDTH= <u>MAX</u>   MIN FORMAT= <u>START</u>   CENTER   END TEXT=divider-text  WIDTH=n DIR= <u>VERT</u>   HORIZ	COMMENT DA DIVIDER DTACOL DTAFLD GA GENERATE GRPHDR INFO LSTFLD PNLINST REGION SELFLD SOURCE	HELP PANEL
ASSIGNI	No	VALUE=test-value RESULT=assigned-value		ASSIGNL
ASSIGNL	Yes	DESTVAR=destination-variable-name	ASSIGNI	DTAFLD
ATTENTION	Yes	<i>text</i>	DL FIG HP LINES NOTE NOTEL NT OL P PARML PS RP SL UL XMP	LI LP P
ATTR	No	ATTRCHAR=code TYPE=DATAIN   DATAOUT   CHAR INTENS= <u>HIGH</u>   LOW   NON   %varname CAPS=OFF   ON   IN   OUT   %varname JUST=ASIS   LEFT   RIGHT   %varname PAD=NULLS   USER   char   %varname PADC=NULLS   USER   char   %varname SKIP=OFF   ON   %varname GE=OFF   ON   %varname COLOR=WHITE   RED   BLUE   GREEN   PINK   YELLOW   TURQ   %varname HILITE=USCORE   BLINK   REVERSE   %varname NUMERIC=OFF   ON   %varname FORMAT=EBCDIC   DBCS   MIX   %varname OUTLINE= <u>NONE</u>   L   R   O   U   BOX   %varname PAS=OFF   ON   %varname CKBOX=OFF   ON   %varname CUADYN=CEF   EE   LEF   NEF   VOI   LID   LI   CH   CT   DT   ET   FP   NT   PIN   PT   SAC   SI   SUC   WASL   WT   %varname CSRGRP=NO   YES   n ATTN=OFF   ON   %varname		DA

Table 7. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
BOTINST	No	COMPACT <i>instruction-text</i>	HP PS RP	PANEL
CAUTION	Yes	<i>text</i>	DL FIG HP LINES NOTE NOTEL NT OL P PARML PS RP SL UL XMP	LI LP P
CHDIV	No	TYPE= <u>NONE</u>   SOLID   DASH   TEXT GUTTER= <u>1</u>   n FORMAT= <u>START</u>   CENTER   END <i>divider-text</i>	HP	SELFLD CHOICE

## Summary of DTL Tags

Table 7. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
CHECKI	No	TYPE= RANGE PARM1=low-bound   %varname PARM2=high-bound   %varname ALPHA CHARS PARM1=EQ PARM2=character-set VALUES PARM1=EQ PARM2=value-list VALUESX PARM1=NE PARM2=value-list BIT NAME NAMEF PICT PARM1=EQ PARM2=pictstring PICTCN PARM1=mask-character PARM2=field-mask PARM3=string NUM DBCS LISTV PARM1=EQ PARM2=%varlist LISTVX PARM1=NE PARM2=%varlist ALPHAB LEN PARM1=operator   %varname PARM2=length   %varname EBCDIC ENUM DSNAME DSNAMEF DSNAMEFM DSNAMEPQ DSNAMEQ MIX HEX FILEID INCLUDE PARM1=IMBLK PARM2=ALPHA   ALPHAB   NUM PARM3=ALPHA   ALPHAB   NUM IDATE STDDATE JDATE JSTD ITIME STDTIME IPADDR4		CHECKL

Table 7. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
CHECKL	Yes	MSG=message-identifier	CHECKI	VARCLASS
CHOFLD	No	DATAVAR=field-data VARCLASS=variable-class-name HELP=NO   YES   help-panel-name   *help-message-id   %varname   *%varname USAGE=BOTH   IN   OUT REQUIRED=NO   YES MSG=message-identifier AUTOTAB=NO   YES ENTWIDTH=n FLDSPACE=n ALIGN=START   CENTER   END DISPLAY=YES   NO NOENDATTR PAD=NULLS   USER   char   %varname PADC=NULLS   USER   char   %varname OUTLINE=NONE   L   R   O   U   BOX   %varname PSVAR=point-and-shoot-variable   %varname PSVAL=point-and-shoot-value   %varname PAS=%varname EXPAND ATTRCHANGE=NO   YES   NEW INIT=initial-value IMAPNAME=image-name   %varname IMAPNAMEP=image-namep   %varname PLACE=ABOVE   BELOW   LEFT   RIGHT   %varname ATTRCHAR=code CAPS=OFF   ON <i>choice-description-text</i>	ACTION COMMENT HP PS RP SOURCE	CHOICE
CHOICE	No	NAME=choice-name HELP=NO   YES   help-panel-name   *help-message-id   %varname   *%varname CHECKVAR=variable-name MATCH=1   string NOMATCH=0   string AUTOTAB=YES   NO SELCHAR='char(s),n' PAD=NULLS   USER   char   %varname PADC=NULLS   USER   char   %varname OUTLINE=NONE   L   R   O   U   BOX   %varname HIDE HIDEX UNAVAIL=variable-name UNAVAILMAT=1   string TRUNC=n AUTOSEL=YES   NO <i>choice-description-text</i>	ACTION CHOFLD COMMENT HP PS RP SOURCE	SELFLD
CMD	No	NAME=internal-command-name ALTDESCR=command-description <i>external-command-name</i>	CMDACT T	CMDTBL

## Summary of DTL Tags

Table 7. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
CMDACT	No	ACTION= 'SELECT=select-parameters' 'ALIAS=internal-command-name parameters' PASSTHRU SETVERB BACKWARD CANCEL EXIT EXHELP FKA FORWARD HELP PANELID RETRIEVE %varname application-command ASIS		CMD
CMDAREA	No	HELP= <u>NO</u>   YES   help-panel-name   *help-message-id   %varname   *%varname PMTLOC= <u>BEFORE</u> NOINIT PAD=NULLS   USER   char   %varname PADC=NULLS   USER   char   %varname OUTLINE= <u>NONE</u>   L   R   O   U   BOX   %varname NAME=cmdarea-variable-name ENTWIDTH=n PMTTEXT= <u>YES</u>   NO CMDLOC= <u>DEFAULT</u>   ASIS CMDLEN= <u>DEFAULT</u>   MAX AUTOTAB= <u>NO</u>   YES SCROLLVAR=scroll-variable SCRVHELP= <u>NO</u>   YES   scroll-help-panel-name   *scroll-help-message-id   %varname   *%varname SCROLLTAB= <u>NO</u>   YES SCRCAPS= <u>OFF</u>   ON PSBUTTON=cmd-pb-text PSVAR=point-and-shoot-variable   %varname PSVAL=point-and-shoot-value   %varname IMAPNAME=image-name   %varname IMAPNAMEP=image-namep   %varname PLACE= <u>ABOVE</u>   BELOW   LEFT   RIGHT   %varname CAPS= <u>OFF</u>   ON NOJUMP= <u>OFF</u>   ON VARDCL= <u>YES</u>   NO command-prompt-text	HP	PANEL
CMDTBL	Yes	APPLID=application-identifier SORT= <u>NO</u>   YES	CMD	

Table 7. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
COMMENT	No	TYPE=END   CCSID   PANEL   ATTR   ABCINIT   ABCPROC   INIT   REINIT   PROC   HELP   PNTS   LIST <i>comment-text</i>		ABC AREA CHOICE DA DTACOL DTAFLD HELP LSTCOL LSTFLD LSTGRP MSGMBR PANEL PDC REGION SELFLD
COMPOPT	No	REPLACE   NOREPLACE SCREEN   DISK NODBCS   DBCS NOKANA   KANA KEYLAPPL=xxxx NOPANEL   PANEL NOMSGSUPP   MSGSUPP NOCUASUPP   CUASUPP PREP   NOPREP CUAATTR   NOCUAATTR NOLSTVIEW   LSTVIEW STATS   NOSTATS NOSCRIP   SCRIPT NOLISTING   LISTING NOFORMAT   FORMAT NOMSGEXPAND   MSGEXPAND LOGREPL   NOLOGREPL LISTREPL   NOLISTREPL ACTBAR   NOACTBAR GUI   NOGUI VERSION   NOVERSION NOMERGESAREA   MERGESAREA NODISPLAY   DISPLAY NODISPLAYW   DISPLAYW DSNCHK   NODSNCHK GRAPHIC   NOGRAPHIC ZVARS   NOZVARS NODBALIGN   DBALIGN NOMCOMMENT   MCOMMENT NOVPADC   PADC ADD RESET <i>national-language</i>	None	
COPYR	No	<i>copyright-text</i>		

## Summary of DTL Tags

Table 7. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
DA	Yes	NAME= <u>varname</u> EXTEND= <u>OFF</u>   ON   FORCE LVLIN <u>E</u> = <u>variable-name</u> SCROLL= <u>OFF</u>   ON   CMDLINE USERMOD= <u>usermod-code</u>   %varname DATAMOD= <u>datamod-code</u>   %varname DEPTH= <u>n</u>   * WIDTH= <u>n</u> SHADOW= <u>shadow-name</u> DIV= <u>NONE</u>   BLANK   SOLID   DASH   TEXT FORMAT= <u>START</u>   CENTER   END TEXT= <u>divider-text</u> SCROLLVAR= <u>scroll-variable</u> SCR <u>V</u> HELP= <u>NO</u>   YES   <u>scroll-help-panel-name</u>  * <u>scroll-help-message-id</u>   %varname   *%varname SCROLLTAB= <u>NO</u>   YES SCRCAPS= <u>OFF</u>   ON INITATTR= <u>NT</u>   CT   ET   WT   WASL HELP= <u>NO</u>   YES   <u>help-panel-name</u>   * <u>help-message-id</u>   %varname   *%varname	ATTR COMMENT SOURCE	AREA PANEL REGION
DD	No	<i>definition-description</i>	DL FIG HP LINES NOTE NOTEL NT OL P PARML PS RP SL UL XMP	DL
DDHD	No	<i>definition-description-header</i>	HP PS RP	DL
DIVIDER	No	TYPE= <u>NONE</u>   SOLID   DASH   TEXT GAP= <u>YES</u>   NO GUTTER= <u>1</u>   n NOENDATTR FORMAT= <u>START</u>   CENTER   END <i>divider-text</i>	HP	AREA DTACOL PANEL REGION

Table 7. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
DL	Yes	TSIZE= <u>10</u>   'S1, S2,... Sn' BREAK= <u>NONE</u>   FIT   ALL COMPACT NOSKIP INDENT= <u>n</u> FORMAT= <u>START</u>   CENTER   END DIVEND= <u>NO</u>   YES SPLIT= <u>NO</u>   YES	DD DDHD DLDIV DT DTHD DTDIV DTHDIV	ATTENTION CAUTION DD FIG INFO LI LINES LP NT PD WARNING XMP
DLDIV	No	TYPE= <u>NONE</u>   SOLID   DASH   TEXT GAP= <u>YES</u>   NO GUTTER= <u>1</u>   n FORMAT= <u>START</u>   CENTER   END <i>divider-text</i>	HP	DL
DT	No	FORMAT= <u>START</u>   CENTER   END NOSKIP SPLIT= <u>NO</u>   YES <i>definition-term</i>	DTSEG HP PS RP	DL
DTACOL	Yes	PMTWIDTH= <u>n</u>   *   ** ENTWIDTH= <u>n</u> DESWIDTH= <u>n</u>   * SELWIDTH= <u>n</u>   * FLDSPACE= <u>n</u> PAD=NULLS   USER   char   %varname PADC=NULLS   USER   char   %varname OUTLINE= <u>NONE</u>   L   R   O   U   BOX   %varname PMTFMT= <u>CUA</u>   ISPF   NONE   END AUTOTAB= <u>NO</u>   YES ATTRCHANGE= <u>NO</u>   YES   NEW PMTLOC= <u>BEFORE</u>   ABOVE DBALIGN= <u>YES</u>   NO   PROMPT   FIELD   FORCE VARCLASS= <u>variable-class-name</u> REQUIRED= <u>NO</u>   YES CAPS= <u>OFF</u>   ON VARDCL= <u>YES</u>   NO	COMMENT DIVIDER DTAFLD GRPHDR SELFLD SOURCE	AREA PANEL REGION

## Summary of DTL Tags

Table 7. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
DTAFLD	No	NAME=field-name DATAVAR=field-data VARCLASS=variable-class-name HELP= <u>NO</u>   YES   help-panel-name   *help-message-id   %varname   *%varname USAGE= <u>BOTH</u>   IN   OUT REQUIRED= <u>NO</u>   YES MSG=message-identifier AUTOTAB= <u>NO</u>   YES ENTWIDTH=n PMTWIDTH=n   *   ** DESWIDTH=n   * FLDSPACE=n ALIGN= <u>START</u>   CENTER   END PMTLOC= <u>BEFORE</u>   ABOVE DISPLAY= <u>YES</u>   NO NOENDATTR PAD=NULLS   USER   char   %varname PADC=NULLS   USER   char   %varname OUTLINE= <u>NONE</u>   L   R   O   U   BOX   %varname PMTFMT= <u>CUA</u>   ISPF   NONE   END PSVAR=point-and-shoot-variable   %varname PSVAL=point-and-shoot-value   %varname PAS=%varname CSRGRP= <u>NO</u>   YES   n EXPAND FLDWIDTH=n ATTRCHANGE= <u>NO</u>   YES   NEW INIT=initial-value DEPTH=n   %varname IMAPNAME=image-name   %varname IMAPNAMEP=image-namep   %varname PLACE= <u>ABOVE</u>   BELOW   LEFT   RIGHT   %varname DBALIGN= <u>YES</u>   NO   PROMPT   FIELD   FORCE PMTSKIP= <u>NO</u>   YES DESSKIP= <u>NO</u>   YES FLDTYPE= <u>CUA</u>   ISPF COLOR= <u>WHITE</u>   RED   BLUE   GREEN   PINK   YELLOW   TURQ   %varname INTENS= <u>HIGH</u>   LOW   NON   %varname HILITE= <u>SCORE</u>   BLINK   REVERSE   %varname ATTRCHAR=code CAPS= <u>OFF</u>   ON NOJUMP= <u>OFF</u>   ON AUTOTYPE= <u>PROJECT</u>   GROUP1   GROUP2   GROUP3   GROUP4   TYPE   MEMBER   DSN AUTOVOL=volser-name AUTODMEM= <u>YES</u>   NO VARDCL= <u>YES</u>   NO <i>prompt-text</i>	ASSIGNL COMMENT DTAFLDD HP PS RP SOURCE SCRFLD	AREA DTACOL PANEL REGION
DTAFLDD	No	<i>description</i>	HP PS RP	DTAFLD
DTDIV	No			DL

Table 7. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
DTHD	No	<i>definition-term-header</i>	HP PS RP	DL
DTHDIV	No			DL
DTSEG	No			DT
FIG	Yes	FRAME= <u>RULE</u>   NONE WIDTH= <u>PAGE</u>   COL NOSKIP <i>figure-content</i>	DL FIGCAP HP NOTE NOTEL NT OL P PARML PS RP SL UL XMP	ATTENTION CAUTION DD INFO LI LP NT PD WARNING
FIGCAP	No	<i>figure-caption-text</i>	HP PS RP	FIG
GA	No	NAME=graphic-area-name EXTEND= <u>OFF</u>   ON   FORCE DEPTH= <u>n</u>   * WIDTH= <u>n</u> DIV= <u>NONE</u>   BLANK   SOLID   DASH   TEXT FORMAT= <u>START</u>   CENTER   END TEXT=divider-text LVLIN=variable-name		AREA PANEL REGION
GENERATE	Yes	SUBSTITUTE= <u>NO</u>   YES	ATTR COMMENT SOURCE	AREA HELP PANEL REGION
GRPHDR	No	FORMAT= <u>START</u>   CENTER   END   NONE WIDTH= <u>n</u> FMTWIDTH= <u>n</u> INDENT= <u>n</u> HEADLINE= <u>NO</u>   YES DIV= <u>NONE</u>   BLANK   SOLID   DASH DIVLOC= <u>AFTER</u>   BEFORE   BOTH COMPACT STRIP <i>group-heading-text</i>	HP PS RP	AREA DTACOL PANEL REGION

## Summary of DTL Tags

Table 7. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
HELP	Yes	NAME=help-panel-name HELP=hhhelp-panel-name   %varname HELPDEF=helpdef-id WIDTH=50   n   FIT DEPTH=10   n   FIT CCSID=n TUTOR KEYLIST=key-list-name KEYLTYPE=PRIVATE   SHARED APPLID=application-id EXPAND=xy WINTITLE=window-title APPTITLE=application-title MERGESAREA=NO   YES MSGLINE=YES   NO IMAPNAME=image-name   %varname IMAPROW=n   %varname IMAPCOL=n   %varname ZUP=zup-id ZCONT=zcont-id <i>help-panel-title</i>	AREA COMMENT DIVIDER GENERATE HP INFO REGION SOURCE TEXTLINE	
HELPDEF	No	ID=helpdef-id HELP=hhhelp-panel-name   %varname WIDTH=n   FIT DEPTH=n   FIT CCSID=n KEYLIST=key-list-name KEYLTYPE=PRIVATE   SHARED APPLID=application-id EXPAND=xy WINTITLE=window-title APPTITLE=application-title MERGESAREA=NO   YES IMAPNAME=image-name   %varname IMAPROW=n   %varname IMAPCOL=n   %varname		
H1	No	COMPACT <i>heading-text</i>		INFO
H2/H3/H4	No	COMPACT <i>heading-text</i>	HP PS RP	INFO

Table 7. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
HP	Yes	TYPE=ET   CH   CT   FP   LEF   LI   NT   PT   SAC   TEXT   WASL   WT COLOR=WHITE   RED   BLUE   GREEN   PINK   YELLOW   TURQ   %varname INTENS=HIGH   LOW   NON   %varname HILITE=USCORE   BLINK   REVERSE   %varname INTENSE=varname <i>phrase-to-be-highlighted</i>		ATTENTION BOTINST CAUTION CHDIV CHOICE CMDAREA DD DDHD DIVIDER DT DTAFLD DTAFLDD DTHD FIG FIGCAP GRPHDR H2 H3 H4 HELP LI LINES LP LSTCOL LSTGRP NOTE NT P PANEL PD PNLINST PT SELFLD TOPINST WARNING XMP
INFO	Yes	WIDTH=format-width   * INDENT=n	DIVIDER DL FIG Hn LINES NOTE NOTEL NT OL P PARML SL SOURCE UL XMP	AREA HELP PANEL REGION
KEYI	No	KEY=virtual-key CMD=internal-command-name CASE=UPPER   MIXED FKA=NO   YES   LONG   SHORT PARM=parm-string <i>FKA-text</i>		KEYL

## Summary of DTL Tags

Table 7. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
KEYL	Yes	NAME=key-list-name HELP=help-panel-name ACTION= <u>UPDATE</u>   DELETE APPLID=application-id	KEYI	
LI	No	SPACE= <u>NO</u>   YES NOSKIP <i>item-text</i>	ATTENTION CAUTION DL FIG HP LINES NOTE NOTEL NT OL P PARML PS RP SL UL WARNING XMP	NOTEL OL SL UL
LINES	Yes	NOSKIP <i>text</i>	DL HP NOTE NOTEL NT OL P PARML PS RP SL UL XMP	ATTENTION CAUTION DD INFO LI LP NT PD WARNING
LIT	Yes	<i>literal-display-value</i>		XLATI
LP	No	NOSKIP <i>implied-paragraph</i>	ATTENTION CAUTION DL FIG HP LINES NOTE NOTEL NT OL P PARML PS RP SL UL WARNING XMP	NOTEL OL SL UL

Table 7. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
LSTCOL	No	DATAVAR=column-data VARCLASS=variable-class-name HELP= <u>NO</u>   YES   help-panel-name   * help-message-id   %varname   *%varname USAGE= <u>BOTH</u>   IN   OUT REQUIRED= <u>NO</u>   YES MSG=message-id COLWIDTH=data-width ALIGN= <u>START</u>   CENTER   END AUTOTAB= <u>NO</u>   YES LINE=n CLEAR POSITION=n FORMAT= <u>START</u>   CENTER   END TEXT=descriptive-text TEXTLOC= <u>BEFORE</u>   AFTER TEXTFMT= <u>START</u>   CENTER   END TEXTLEN=n TEXTSKIP= <u>NO</u>   YES NOENDATTR PAD=NULLS   USER   char   %varname PADC=NULLS   USER   char   %varname OUTLINE= <u>NONE</u>   L   R   O   U   BOX   %varname PAS= <u>OFF</u>   ON   %varname CSRGRP= <u>NO</u>   YES   n ATTRCHANGE= <u>NO</u>   YES   NEW COLSPACE=n COLTYPE= <u>CUA</u>   ISPF   EE   VOI   LID COLOR= <u>WHITE</u>   RED   BLUE   GREEN   PINK   YELLOW   TURQ   %varname INTENS= <u>HIGH</u>   LOW   NON   %varname HILITE= <u>USCORE</u>   BLINK   REVERSE   %varname CAPS= <u>OFF</u>   ON DISPLAY= <u>YES</u>   NO VARDCL= <u>YES</u>   NO <i>column-heading</i>	COMMENT HP PS RP SOURCE SCRFLD	LSTFLD LSTGRP
LSTFLD	Yes	RULES= <u>NONE</u>   HORIZ   VERT   BOTH ROWS= <u>NOSCAN</u>   SCAN   %varname DIV= <u>NONE</u>   BLANK   SOLID   DASH   char SCROLLVAR=scoll-variable SCRHELP= <u>NO</u>   YES   scroll-help-panel-name  *scroll-help-message-id   %varname   *%varname SCROLLTAB= <u>NO</u>   YES SCRCAPS= <u>OFF</u>   ON ATTRCHANGE= <u>NO</u>   YES   NEW VARDCL= <u>YES</u>   NO	COMMENT LSTCOL LSTGRP LSTVAR SOURCE	AREA PANEL REGION
LSTGRP	Yes	HEADLINE= <u>NO</u>   YES   DASH ALIGN= <u>CENTER</u>   START   END <i>column-group-heading</i>	COMMENT HP LSTCOL LSTGRP LSTVAR PS RP SOURCE	LSTFLD LSTGRP

## Summary of DTL Tags

Table 7. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
LSTVAR	No	DATAVAR=variable-model-name LINE=n <i>column-heading</i>	COMMENT HP PS RP SOURCE	LSTFLD LSTGRP
M	No	<i>mnemonic-character</i>		ABC PDC
MSG	No	SUFFIX=message-suffix-number HELP=help-panel-name   %varname   * MSGTYPE=INFO   WARNING   ACTION   CRITICAL   %varname LOCATION=AREA   MODAL   MODAL(L)   MODELESS   MODELESS (L)   %varname DISP=KANA   NOKANA ALARM=NO   YES   %varname ABBREV=NONE   KEYWORD   VALUE   BOTH FORMAT=FLOW   ASIS SMSG=short-message-text <i>message-text</i>	VARSUB	MSGMBR
MSGMBR	Yes	NAME=message-member-name CCSID=n WIDTH=76   68	COMMENT MSG	
NOTE	No	NOSKIP INDENT=n TYPE=ET   CH   CT   FP   LEF   LI   NT   PT   SAC   TEXT   WASL   WT COLOR=WHITE   RED   BLUE   GREEN   PINK   YELLOW   TURQ   %varname INTENS=HIGH   LOW   NON   %varname HILITE=USCORE   BLINK   REVERSE   %varname TEXT=alternate-note-heading <i>note-text</i>	HP PS RP	ATTENTION CAUTION DD FIG INFO LI LINES LP PD WARNING XMP
NOTEL	Yes	COMPACT NOSKIP SPACE=NO   YES INDENT=n TYPE=ET   CH   CT   FP   LEF   LI   NT   PT   SAC   TEXT   WASL   WT COLOR=WHITE   RED   BLUE   GREEN   PINK   YELLOW   TURQ   %varname INTENS=HIGH   LOW   NON   %varname HILITE=USCORE   BLINK   REVERSE   %varname TEXT=alternate-note-heading	LI LP	ATTENTION CAUTION DD FIG INFO LI LINES LP PD WARNING XMP

Table 7. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
NT	Yes	NOSKIP INDENT= <u>n</u> TYPE= <u>ET</u>   CH   CT   FP   LEF   LI   NT   PT   SAC   TEXT   WASL   WT COLOR=WHITE   RED   BLUE   GREEN   PINK   YELLOW   TURQ   %varname INTENS= <u>HIGH</u>   LOW   NON   %varname HILITE= <u>USCORE</u>   BLINK   REVERSE   %varname TEXT=alternate-note-heading <i>note-text</i>	DL FIG HP LINES OL P PARML PS RP SL UL XMP	ATTENTION CAUTION DD FIG INFO LI LINES LP PD WARNING XMP
OL	Yes	COMPACT NOSKIP SPACE= <u>NO</u>   YES INDENT= <u>n</u> TEXT=OL-heading-text	LI LP	ATTENTION CAUTION DD FIG INFO LI LINES LP NT PD WARNING XMP
P	No	COMPACT INTENSE= <u>varname</u> INDENT= <u>n</u> OFFSET= <u>n</u> SPACE= <u>NO</u>   YES <i>paragraph-text</i>	ATTENTION CAUTION HP PS RP WARNING	ATTENTION CAUTION DD FIG INFO LI LINES LP NT PD WARNING XMP

## Summary of DTL Tags

Table 7. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
PANDEF	No	ID=pandef-id HELP=help-panel-name   %varname DEPTH=n   FIT WIDTH=n   FIT   %varname KEYLIST=key-list-name KEYLTYPE=PRIVATE   SHARED APPLID=application-id CCSID=n WINDOW=YES   NO WINTITLE=window-title APPTITLE=application-title PAD=NULLS   USER   char   %varname PADC=NULLS   USER   char   %varname OUTLINE=NONE   L   R   O   U   BOX   %varname EXPAND=xy MERGESAREA=NO   YES ENTKEYTEXT=enter-key-text IMAPNAME=image-name   %varname IMAPROW=n   %varname IMAPCOL=n   %varname TMARGIN=n BMARGIN=n		

Table 7. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
PANEL	Yes	NAME=panel-name HELP=help-panel-name   %varname PANDEF=pandef-id DEPTH=22   n   FIT WIDTH=76   n   FIT   %varname KEYLIST=key-list-name KEYLTYPE=PRIVATE   SHARED APPLID=application-id CURSOR=cursor-field CSRINDEX=index-value CSRPOS=position-value CCSID=n MENU PRIME TUTOR WINDOW=YES   NO WINTITLE=window-title APPTITLE=application-title PAD=NULLS   USER   char   %varname PADC=NULLS   USER   char   %varname OUTLINE=NONE   L   R   O   U   BOX   %varname EXPAND=xy MSGLINE=YES   NO TITLINE=YES   NO CMDLINE=YES   NO ATTRUSE=NO   YES   ALL ENDATTR=DEFAULT   TEXT TYPE=BOTH   GUI   NOGUI SMSG=short-msg-fieldname LMSG=long-msg-fieldname ASIS ACTBAR MERGESAREA=NO   YES PANELSTMT=YES   NO ENTKEYTEXT=enter-key-text IMAPNAME=image-name   %varname IMAPROW=n   %varname IMAPCOL=n   %varname TMARGIN=n BMARGIN=n ERRORCHECK=NO   YES ZUP=zup-id ZCONT=zcont-id AUTONRET=NO   YES AUTOTCMD=NO   YES   PROC panel-title-text	AB AREA BOTINST CMDAREA COMMENT DA DIVIDER DTACOL DTAFLD GA GENERATE GRPHDR HP INFO LSTFLD PNLINST REGION SELFLD SOURCE TEXTLINE TOPINST	

## Summary of DTL Tags

Table 7. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
PARML	Yes	TSIZE= <u>10</u>   'S1 S2... Sn' BREAK= <u>ALL</u>   FIT   NONE COMPACT SKIP INDENT= <u>n</u> FORMAT= <u>START</u>   CENTER   END DIVEND= <u>NO</u>   YES SPLIT= <u>NO</u>   YES	PLDIV PT PTDIV PD	ATTENTION CAUTION DD FIG INFO LI LINES LP NT PD WARNING XMP
PD	No	<i>parameter-description</i>	DL FIG HP LINES NOTE NOTEL NT OL P PARML PS RP SL UL XMP	PARML
PDC	No	HELP= <u>NO</u>   YES   help-panel-name   *help-message-id   %varname   *%varname UNAVAIL=unavail-variable-name CHECKVAR=check-variable-name MATCH= <u>1</u>   match-string ACC1=key1 ACC2=key2 ACC3=key3 <i>pull-down-description-text</i>	ACTION COMMENT M SOURCE	ABC
PDSEP	No			PDC
PLDIV	No	TYPE= <u>NONE</u>   SOLID   DASH   TEXT GAP= <u>YES</u>   NO GUTTER= <u>1</u>   n FORMAT= <u>START</u>   CENTER   END <i>divider-text</i>	HP	PARML
PNLINST	No	COMPACT <i>instruction-text</i>	HP PS RP	AREA REGION PANEL

Table 7. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
PS	Yes	VAR=point-and-shoot-variable-name   %varname VALUE=point-and-shoot-value   %varname   * CSRGRP=NO   YES   n DEPTH=n   %varname IMAPNAME=image-name   %varname IMAPNAMEP=image-namep   %varname PLACE=ABOVE   BELOW   LEFT   RIGHT   %varname <i>point-and-shoot-text</i>		ATTENTION BOTINST CAUTION CHOFLD CHOICE DD DDHD DT DTAFLD DTAFLDD DTHD FIG FIGCAP GRPHDR H2 H3 H4 LI LINES LP LSTCOL LSTGRP NOTE NT P PD PNLINST PT SELFLD TOPINST WARNING XMP
PT	No	FORMAT=START   CENTER   END NOSKIP SPLIT=NO   YES <i>parameter-term</i>	HP PS PTSEG RP	PARML
PTDIV	No			PARML
PTSEG	No			PT
REGION	Yes	DIR=VERT   HORIZ INDENT=n WIDTH=n   * DEPTH=n   * EXTEND=OFF   ON   FORCE ALIGN=YES   NO GRPBOX=NO   YES GRPWIDTH=n GRPBXVAR=variable-name GRPBXMAT=1   string LOCATION=DEFAULT   TITLE <i>group-box-title</i>	COMMENT DA DIVIDER DTACOL DTAFLD GA GENERATE GRPHDR INFO LSTFLD PNLINST REGION SELFLD SOURCE	AREA HELP PANEL REGION

## Summary of DTL Tags

Table 7. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
RP	Yes	HELP= help-panel-name   help-message-id   %varname   *%varname <i>reference-phrase</i>		ATTENTION BOTINST CAUTION CHOFLD CHOICE DD DDHD DT DTAFLD DTAFLDD DTHD FIG FIGCAP GRPHDR H2 H3 H4 LI LINES LP LSTCOL LSTGRP NOTE NT P PD PNLINST PT SELFLD TOPINST WARNING XMP
SCRFLD	Yes	DISPLEN= n   %varname INDVAR=ind-var INDVAL='ind-chars' LINDVAR=lind-var LINDVAL='lind-char' RINDVAR=rind-var RINDVAL='rind-char' SINDVAR=sind-var SINDVAL='sind-chars' LCOLIND=lcol-var LCOLDISP= <u>NO</u>   YES RCOLIND=rcol-var RCOLDISP= <u>NO</u>   YES SCALE=scale-var SCROLL= <u>ON</u>   OFF   %varname FLDSPOS= <u>BELOW</u>   ABOVE	COMMENT SOURCE	DTAFLD LSTCOL

Table 7. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
SELFLD	Yes	NAME=field-name HELP= <u>NO</u>   YES   help-panel-name   *help-message-id   %varname   *%varname TYPE= <u>SINGLE</u>   MULTI   MENU   MODEL   TUTOR PMTLOC= <u>ABOVE</u>   BEFORE PMTWIDTH=n   *   ** SELWIDTH=n   * ENTWIDTH=2   n   'e1 e2...en' REQUIRED= <u>NO</u>   YES MSG=message-identifier FCHOICE=1   0 AUTOTAB= <u>YES</u>   NO DEPTH=n   * EXTEND= <u>OFF</u>   ON   FORCE TRAIL='trail-var-1 trail-var-2 ... trail-var-n' CHOICECOLS=1   n CHOICEDEPTH=n   * CWIDTHS='w1 w2...wn' PAD=NULLS   USER   char   %varname PADC=NULLS   USER   char   %varname OUTLINE= <u>NONE</u>   L   R   O   U   BOX   %varname SELMSG=selfld-msg-identifier SELMSGU=selfld-msg-unavailable INIT= <u>YES</u>   NO   init-value VERIFY= <u>YES</u>   NO REFRESH= <u>YES</u>   NO SELFMT= <u>START</u>   END CHKBOX= <u>YES</u>   NO ZGUI= <u>YES</u>   NO CSRGRP= <u>NO</u>   YES   n TSIZE='s1 s2...sn' LISTTYPE=RADIO   LISTBOX   DDLIST   COMBO LISTREF=list-name LISTDEPTH=n DBALIGN= <u>YES</u>   NO   FIELD   FORCE NOSEL=no-selection-value SELDEFAULT=x PMTSKIP= <u>NO</u>   YES FLDTYPE= <u>CUA</u>   ISPF COLOR=WHITE   RED   BLUE   GREEN   PINK   YELLOW   TURQ   %varname INTENS= <u>HIGH</u>   LOW   NON   %varname HILITE= <u>USCORE</u>   BLINK   REVERSE   %varname SELCHECK= <u>NO</u>   YES VARDCL= <u>YES</u>   NO field-prompt-text	CHDIV CHOICE COMMENT HP PS RP SOURCE	AREA DTACOL PANEL REGION

## Summary of DTL Tags

Table 7. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
SL	Yes	COMPACT NOSKIP SPACE= <u>NO</u>   YES INDENT= <u>n</u> TEXT='SL-heading-text'	LI LP	ATTENTION CAUTION DD FIG INFO LI LINES LP NT PD WARNING XMP
SOURCE	Yes	TYPE= <u>PROC</u>   REINIT   INIT   ABCINIT   ABCPROC <i>text</i>		ABC AREA CHOICE DA DTACOL DTAFLD HELP LSTCOL LSTFLD LSTGRP PANEL PDC REGION SELFLD
T	No			CMD
TEXTLINE	Yes		DTAFLD TEXTSEG	HELP PANEL
TEXTSEG	No	EXPAND= <u>AFTER</u>   BEFORE   BOTH WIDTH= <u>n</u> <i>text</i>	HP	TEXTLINE
TOPINST	No	COMPACT <i>instruction-text</i>	HP PS RP	PANEL
UL	Yes	COMPACT NOSKIP SPACE= <u>NO</u>   YES INDENT= <u>n</u> TEXT=UL-heading-text	LI LP	ATTENTION CAUTION DD FIG INFO LI LINES LP NT PD WARNING XMP

Table 7. Tag summary (continued)

Tag	End tag	Attributes	Nested tags	Used within
VARCLASS	No	NAME=variable-class-name TYPE='CHAR maximum length' 'DBCS maximum length' 'MIXED maximum length' 'ANY maximum length' 'EBCDIC maximum length' '%varname maximum length' ITIME STDTIME IDATE STDDATE JDATE JSTD 'VMASK maximum-length' 'NUMERIC total-digits <u>0</u>   fractional-digits' MSG=message-identifier	CHECKL XLATL	
VARDC	No	NAME=name VARCLASS=variable-class-name		VARLIST
VARLIST	Yes		VARDC	
VARSUB	No	VAR=variable-name		MSG
WARNING	Yes	<i>text</i>	DL FIG HP LINES NOTE NOTEL NT OL P PARML PS RP SL UL XMP	LI LP P
XLATI	No	VALUE=internal-value <i>displayed-value</i>	LIT	XLATL
XLATL	Yes	FORMAT= <u>NONE</u>   UPPER TRUNC=n   char MSG=message-identifier	XLATI	VARCLASS
XMP	Yes	NOSKIP <i>text</i>	DL HP NOTE NOTEL NT OL P PARML PS RP SL UL	ATTENTION CAUTION DD FIG INFO LI LINES LP NT PD WARNING

## Summary of DTL Tags

---

## Notices

This information was developed for products and services offered in the U.S.A.

IBM may not offer the products, services, or features discussed in this document in other countries. Consult your local IBM representative for information on the products and services currently available in your area. Any reference to an IBM product, program, or service is not intended to state or imply that only that IBM product, program, or service may be used. Any functionally equivalent product, program, or service that does not infringe any IBM intellectual property right may be used instead. However, it is the user's responsibility to evaluate and verify the operation of any non-IBM product, program, or service.

IBM may have patents or pending patent applications covering subject matter described in this document. The furnishing of this document does not give you any license to these patents. You can send license inquiries, in writing, to the IBM Director of Licensing, IBM Corporation, North Castle Drive, Armonk, NY 10504-1785, USA.

For license inquiries regarding double-byte (DBCS) information, contact the IBM Intellectual Property Department in your country or send inquiries in writing to

IBM World Trade Asia Corporation  
Licensing  
2-31 Roppongi 3-chome, Minato-ku  
Tokyo 106-0032, Japan

The following paragraph does not apply to the United Kingdom or any other country where such provisions are inconsistent with local law:

INTERNATIONAL BUSINESS MACHINES CORPORATION PROVIDES THIS PUBLICATION "AS IS" WITHOUT WARRANTY OF ANY KIND, EITHER EXPRESS OR IMPLIED, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OR NON-INFRINGEMENT, MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE. Some states do not allow disclaimer of express or implied warranties in certain transactions, therefore, this statement may not apply to you.

This information could include technical inaccuracies or typographical errors. Changes are periodically made to the information herein; these changes will be incorporated in new editions of the publication. IBM may make improvements and/or changes in the product(s) and/or the program(s) described in this publication at any time without notice.

Any references in this information to non-IBM Web sites are provided for convenience only and do not in any manner serve as an endorsement of those Web sites. The materials at those Web sites are not part of the materials for this IBM product and use of those Web sites is at your own risk.

IBM may use or distribute any of the information you supply in any way it believes appropriate without incurring any obligation to you.

Licensees of this program who wish to have information about it for the purpose of enabling: (i) the exchange of information between independently created programs and other programs (including this one) and (ii) the mutual use of the information which has been exchanged, should contact:

IBM Corporation,  
Mail Station P300  
2455 South Road  
Poughkeepsie New York 12601-5400  
U.S.A.

Such information may be available, subject to appropriate terms and conditions, including in some cases, payment of a fee.

The licensed program described in this document and all licensed material available for it are provided by IBM under terms of the IBM Customer Agreement, IBM International Program License Agreement or any equivalent agreement between us.

Information concerning non-IBM products was obtained from the suppliers of those products, their published announcements or other publicly available sources. IBM has not tested those products and cannot confirm the accuracy of performance, compatibility or any other claims related to non-IBM products. Questions on the capabilities of non-IBM products should be addressed to the suppliers of those products.

If you are viewing this information softcopy, the photographs and color illustrations may not appear.

---

## Programming Interface Information

This publication primarily documents information that is NOT intended to be used as Programming Interfaces of ISPF.

This publication also documents intended Programming Interfaces that allow the customer to write programs to obtain the services of ISPF. This information is identified where it occurs, either by an introductory statement to a chapter or section or by the following marking:

+-----Programming Interface information-----+

+-----End of Programming Interface information-----+

---

## Trademarks

The following terms are trademarks of International Business Machines Corporation in the United States, other countries, or both:

AD/Cycle	GDDM
APL2	IBM
BookManager	Language Environment
BookMaster	MVS
C++/MVS	MVS/XA
COBOL/370	OS/390
Common User Access	RACF
CUA	SAA
DFSMSrmm	Systems Application Architecture
DFSMS/MVS	Tivoli
DFSORT	VTAM
FFST	z/OS

Microsoft, Windows, and Windows NT are trademarks of Microsoft Corporation in the United States, other countries, or both.

UNIX is a registered trademark of The Open Group in the United States and other countries.

Linux is a trademark of Linus Torvalds in the United States, other countries, or both.

Other company, product, and service names may be trademarks or service marks of others.



---

# Index

## Special characters

- % keyword
  - on ENTITY statement 196
- % notation 12
- <: notation
  - in doctype declaration 16

## A

- AB (action bar) tag
  - See also action bar
  - conditions of usage 207
  - defining an action bar 34
  - description 206
  - examples
    - adding HELP attribute 36
    - application panel markup 207
    - defining help panel 37
    - markup 35
    - using mnemonic selection 38
  - how to code 35
  - syntax 206
- ABBREV attribute
  - on MSG tag 392
- ABC (action bar choice) tag
  - conditions of usage 209
  - description 209
  - examples
    - defining help panel 37
    - markup 35
    - PDCVAR attribute 209
    - using mnemonic selection 38
  - syntax 208
- ABSEPCHAR attribute on AB tag 206
- ABSEPSTR attribute on AB tag 206
- ACC1 attribute on PDC tag 430
- ACC2 attribute on PDC tag 430
- ACC3 attribute on PDC tag 430
- accelerator attributes on PDC tag 430
- ACTBAR attribute
  - on PANEL tag 419
- ACTBAR option 180
- ACTION (action) tag
  - conditions of usage 216
  - description 215
  - examples
    - defining help panel 37
    - markup 35
    - PDC tags and SETVAR attribute 216
    - using mnemonic selection 38
  - for pull-down choice 35
  - syntax 211
- ACTION attribute
  - on CMDACT tag 264
  - on KEYL tag 356
  - value ALIAS on CMDACT tag 264
  - value application-command on CMDACT tag 266

- ACTION attribute (*continued*)
  - value BACKWARD on CMDACT tag 265
  - value CANCEL on CMDACT tag 265
  - value EXHELP on CMDACT tag 265
  - value EXIT on CMDACT tag 265
  - value FKA on CMDACT tag 265
  - value FORWARD on CMDACT tag 265
  - value HELP on CMDACT tag 265
  - value PANELID on CMDACT tag 265
  - value PASSTHRU on CMDACT tag 265
  - value RETRIEVE on CMDACT tag 266
  - value SELECT on CMDACT tag 264
  - value SETVERB on CMDACT tag 265
- action bar
  - See also AB (action bar) tag
  - defining 34
  - description 6
  - providing help for 36
- action bar (AB) tag
  - conditions of usage 207
  - description 206
  - examples 207
  - syntax 206
- action bar choice
  - See ABC (action bar choice) tag
- action bar choice (ABC) tag
  - conditions of usage 209
  - description 209
  - examples 209
  - syntax 208
- action message
  - defining 157
  - description 157
- activities
  - nesting xxii
- ADDPPOP attribute on ACTION tag 214
- ALARM attribute
  - on MSG tag 392
- alerting users
  - using the ATTENTION tag 136
  - using the CAUTION tag 136
  - using the NT tag 136
  - using the WARNING tag 136
- ALIAS command action
  - defining 163
  - description 163
- ALIGN attribute
  - on CHOFLD tag 251
  - on DTAFLD tag 310
  - on LSTCOL tag 369
  - on LSTGRP tag 382
  - on REGION tag 447
  - using 86

- ALPHA test
  - description 67
  - example 67
  - specifying on CHECKI tag 240
- ALPHAB test
  - description 72
  - example 72
  - specifying on CHECKI tag 244
- alphabetic test
  - description 67
  - example 67
- ALTDESCR attribute on CMD tag 263
- APPLCMD attribute on ACTION tag 213
- application command table
  - See also commands
  - defining commands 161
  - defining with CMDTBL tag 161
  - overview 8
- application panel
  - action bar 6
  - bottom instruction 6
  - command area 7
  - defining a command area 51
  - defining a panel ID 28
  - defining a region 48
  - defining action bar and pull-downs 34
  - defining an area divider 46
  - defining common attributes and values 53
  - defining common elements 27
  - defining cursor placement 30
  - defining panel width and depth 29
  - defining the panel title 29
  - defining top and bottom instructions 39
  - defining with the PANEL tag 27
  - description of PANEL tag 421
  - examples of PANEL tag 422
  - function key area 7
  - layout 5
  - overview 5
  - panel body 6
  - panel title 6
  - providing help for 30
  - specifying a key mapping list 29
  - syntax for PANEL tag 413
  - top instruction 6
- application-id
  - ISPx 161
  - option 179
  - using with CMDTBL tag 161
- APPLID attribute
  - description 161
  - on CMDTBL tag 273
  - on HELP TAG 338
  - on HELPDEF TAG 344
  - on KEYL TAG 356
  - on PANDEF TAG 410
  - on PANEL TAG 417

- APPTITLE attribute
    - on HELP TAG 338
    - on HELPDEF TAG 345
    - on PANDEF tag 410
    - on PANEL tag 418
  - AREA (area) tag
    - conditions of usage 220
    - defining panel text portion 40
    - description 219
    - examples 40, 221
    - syntax 217
  - area divider (DIVIDER) tag
    - conditions of usage 290
    - description 290
    - examples 291
    - syntax 289
  - area divider (DLDIV) tag
    - conditions of usage 297
    - description 297
    - examples 297
  - ASIS attribute
    - on PANEL tag 419
  - ASSIGNI (assignment list item) tag
    - conditions of usage 224
    - description 224
    - examples 224
    - syntax 223
  - ASSIGNL (assignment list) tag
    - conditions of usage 225
    - description 225
    - examples 225
    - syntax 225
  - assignment list (ASSIGNL) tag
    - conditions of usage 225
    - description 225
    - examples 225
    - syntax 225
  - assignment list item (ASSIGNI) tag
    - conditions of usage 224
    - description 224
    - examples 224
    - syntax 223
  - ATTENTION (attention) tag
    - conditions of usage 226
    - description 226
    - syntax 226
  - attention message
    - description
    - format 139
  - ATTENTION tag
    - description 139
  - ATTN attribute
    - on ATTR tag 231
  - ATTR (attribute) tag
    - conditions of usage 231
    - description 231
    - examples 232
    - syntax 228
  - ATTRCHANGE attribute
    - description 100
    - data field 87
    - list field 105
    - on CHOFLD tag 252
    - on DTACOL tag 303
    - on DTAFLD tag 311
    - on LSTCOL tag 371
    - on LSTFLD tag 379
  - ATTRCHANGE attribute (*continued*)
    - using 87, 105
  - ATTRCHAR attribute
    - description
    - data field 88
    - on ATTR tag 229
    - on DTAFLD tag 313
    - using 88
  - attribute
    - description 11
    - tag 11
  - attribute (ATTR) tag
    - conditions of usage 231
    - description 231
    - examples 232
    - syntax 228
  - attributes and values, coding 11
  - ATTRUSE attribute
    - on PANEL tag 419
  - AUTODMEM attribute
    - description
    - data field 88
    - on DTAFLD tag 314
    - using 88
  - AUTONRET attribute
    - on PANEL tag 421
  - AUTOSEL attribute
    - on CHOICE tag 259
  - AUTOTAB 97
  - AUTOTAB attribute
    - description 100, 105
    - on CHOFLD tag 250
    - on CHOICE tag 258
    - on CMDAREA tag 269
    - on DTACOL tag 303
    - on DTAFLD tag 309
    - on LSTCOL tag 369
    - on SELFLD tag 469
    - using 105
  - AUTOTCMD attribute
    - on PANEL tag 421
  - AUTOTYPE attribute
    - description
    - data field 88
    - on DTAFLD tag 313
    - using 88
  - AUTOVOL attribute
    - description
    - data field 88
    - on DTAFLD tag 314
    - using 88
- ## B
- BARRIER attribute on ACTION tag 214
  - BIT test
    - description 74
    - example 74
    - specifying on CHECKI tag 242
  - BMARGIN attribute
    - on PANDEF TAG 411
    - on PANEL TAG 420
  - BOTINST (bottom instruction) tag
    - conditions of usage 232
    - defining instruction text 39
    - description 232
    - examples 40, 233
- ## C
- CAPS attribute
    - description 100
    - data field 88
    - input-only 105
    - input/output 105
    - on ATTR tag 229
    - on CMDAREA tag 271
    - on DTACOL tag 303
    - on DTAFLD tag 313
    - on LSTCOL tag 372
    - using 88
  - CASE attribute on KEYI tag 353
  - CAUTION (caution) tag
    - conditions of usage 234
    - description 140, 234
    - example 140
    - examples 235
    - syntax 234
  - CCSID attribute
    - on HELP tag 338, 395
    - on HELPDEF tag 344
    - on PANDEF tag 410
    - on PANEL tag 417
  - CDATA keyword
    - on ENTITY statement 196
  - character variables 59
  - CHARS test
    - specifying on CHECKI tag 240
  - CHDIV (choice divider) tag
    - conditions of usage 237
    - description 237
    - examples
      - solid and blank 237
    - syntax 236
  - check list
    - example 158
    - specifying message for 158
  - CHECKI (validity check item) tag
    - conditions of usage 246
    - description 246
    - examples 246
    - syntax 238
  - checking values within a numeric range, range test 67
  - CHECKL (validity check list) tag
    - conditions of usage 247

- CHECKL (validity check list) tag
  - (*continued*)
  - description 247
  - examples 248
  - syntax 247
  - using MSG attribute 157
- CHECKVAR attribute
  - description 37
  - example 38
  - on CHOICE tag 256
  - on PDC tag 429
- CHKBOX attribute
  - description 98
  - on SELFLD tag 471
  - using 98
- CHOFLD (choice data field) tag
  - conditions of usage 253
  - description 253
  - examples 254
  - syntax 248
- CHOFLD (choice field) tag
  - using MSG attribute 157
- choice 95
  - See* selection field
- CHOICE (selection choice) tag
  - conditions of usage 260
  - defining a selection field 89
  - description 259
  - examples 261
  - syntax 255
- choice data field (CHOFLD) tag
  - conditions of usage 253
  - description 253
  - examples 254
  - syntax 248
- choice divider (CHDIV) tag
  - conditions of usage 237
  - description 237
  - examples 237
  - syntax 236
- CHOICECOLS attribute
  - description 98
  - on SELFLD tag 470
  - using 98
- CHOICEDEPTH attribute
  - description 98
  - on SELFLD tag 470
  - using 98
- CKBOX attribute
  - on ATTR tag 230
- CLEAR attribute
  - description 105
  - on LSTCOL tag 369
- CMD (command definition) tag
  - assigning function key 167
  - conditions of usage 263
  - description 263
  - examples 263
  - syntax 262
  - using to define a command 161
- CMD attribute on KEYI tag 353
- CMDACT (command action) tag
  - conditions of usage 266
  - description 266
  - examples 266
  - syntax 264
- CMDAREA (command area) tag
  - conditions of usage 272
  - defining a command area 51
  - description 271
  - examples
    - defining 52
    - in an application panel markup 272
    - specifying the command prompt text 52
  - syntax 267
- CMDLEN attribute
  - on CMDAREA tag 269
- CMDLINE attribute
  - on PANEL tag 418
- CMDLOC attribute
  - on CMDAREA tag 269
- CMDTBL (command table) tag
  - assigning function key 167
  - conditions of usage 274
  - description 274
  - examples 275
  - syntax 273
  - using to define a command table 161
- coding an action bar definition 35
- COLOR attribute
  - description 99, 106
  - data field 88
  - on ATTR tag 230
  - on DTAFLD tag 313
  - on HP tag 349
  - on LSTCOL tag 372
  - on NOTE tag 397
  - on NOTEL tag 400
  - on NT tag 402
  - on SELFLD tag 474
  - using 88, 99
- COLSPACE attribute
  - description 106
  - on LSTCOL tag 371
- COLTYPE attribute
  - description 106
  - on LSTCOL tag 371
- column data 99
- column, defining widths 99, 105
- COLWIDTH attribute on LSTCOL tag 369
  - See* commands
- command
  - See* commands
- command action (CMDACT) tag
  - conditions of usage 266
  - description 266
  - examples 266
  - syntax 264
  - using to define a command action 163
- command area
  - defining 51
  - defining cursor placement 31
  - description 7
- command area (CMDAREA) tag
  - conditions of usage 272
  - description 271
  - examples 272
  - syntax 267
- command definition (CMD) tag
  - conditions of usage 263
- command definition (CMD) tag
  - (*continued*)
  - description 263
  - examples 263
  - syntax 262
- command table
  - See* application command table
- command table (CMDTBL) tag
  - conditions of usage 274
  - description 274
  - examples 275
  - syntax 273
- command-prompt-text attribute
  - on CMDAREA tag 271
- commands
  - application command table 161
  - declaring variables for 57
  - defining a command area 51
  - defining application command table 161
  - defining with CMDTBL tag 161
  - description of application command table 8
  - nesting xxii
  - specifying command action 163
  - specifying with the RUN attribute 36
  - truncating 164
- comment (COMMENT) tag
  - examples 276
  - syntax 275
- COMMENT (comment) tag
  - examples 276
  - syntax 275
- comment delimiter
  - description 17
  - example 17
  - using 17
- comments
  - examples 17
  - including in generated panel 15
  - including in source files 16
- COMPACT attribute
  - on BOTINST tag 232
  - on DL tag 292
  - on GRPHDR tag 333
  - on NOTEL tag 399
  - on OL tag 404
  - on P tag 407
  - on PARML tag 425
  - on PNLINST tag 436
  - on SL tag 480
  - on TOPINST tag 488
  - on UL tag 491
  - using in a note list 399
  - using in a simple list 123
  - using in an ordered list 127
  - using in an unordered list 125
- compact for simple list 123
- compact lists
  - note 122
  - ordered 127
  - simple 123
  - unordered 125
- compiler options (COMPOPT) tag
  - syntax 277
- COMPOPT (compiler options) tag
  - examples 278

COMPOPT (compiler options) tag  
 (continued)  
 syntax 277

compopt (COMPOPT) tag  
 examples 278

considerations, compatibility for AREA  
 tag 219

conversion utility  
 ACTBAR option 180  
 converting multiple source files 176  
 CUAATTR option 179  
 CUASUPP option 179  
 DBALIGN option 182  
 DBCS option 178  
 DISK option 178  
 DISPLAY option 181  
 DISPLAYW option 181  
 DSNCHK option 182  
 FORMAT option 180  
 GRAPHIC option 182  
 GUI option 181  
 help 176  
 installing 187  
 invocation panel input fields 172  
 invocation panel options 173  
 invocation panels 171  
 KANA option 179  
 KEYAPPL option 179  
 LISTING option 180  
 LISTREPL option 180  
 LOGREPL option 180  
 LSTVIEW option 179  
 MCOMMENT option 182  
 MERGESAREA option 181  
 messages 186  
 MSGEXPAND option 180  
 MSGSUPP option 179  
 NOACTBAR option 180  
 NOCUAATTR option 179  
 NOCUASUPP option 179  
 NODBALIGN option 182  
 NODBCS option 178  
 NODISPLAY option 181  
 NODISPLAYW option 181  
 NODSNCHK option 182  
 NOFORMAT option 180  
 NOGRAPHIC option 182  
 NOGUI option 181  
 NOKANA option 179  
 NOLISTING option 180  
 NOLISTREPL option 180  
 NOLOGREPL option 180  
 NOLSTVIEW option 179  
 NOMCOMMENT option 182  
 NOMERGESAREA option 181  
 NOMSGEXPAND option 180  
 NOMSGSUPP option 179  
 NOPANEL option 179  
 NOPLEB option 182  
 NOPREP option 179  
 NOREPLACE option 178  
 NOSCRIPT option 179  
 NOSTATS option 179  
 NOV3PADC option 183  
 NOVERSION option 181  
 NOZVARS option 182  
 overview 9

conversion utility (continued)  
 PANEL option 179  
 PLEB option 182  
 PREP option 179  
 PROFDDN option 183  
 PROFILE option 183  
 REPLACE option 178  
 SCREEN option 178  
 SCRIPT option 179  
 STATS option 179  
 supporting keys help 169  
 syntax 177  
 using 171  
 V3PADC option 183  
 VERSION option 181  
 ZVARS option 182

converting DTL source files 171

COPYR (copyright) tag  
 examples 280  
 syntax 279

copyright  
 including in generated panel 15

copyright (COPYR) tag  
 examples 280

copyright (COPYRIGHT) tag  
 syntax 279

CSRGRP attribute  
 description 99, 106  
 data field 87  
 on ATTR tag 231  
 on DTAFLD tag 311  
 on LSTCOL tag 371  
 on PS tag 439  
 on SELFLD tag 472  
 using 87, 99

CSRINDEX attribute  
 example 32  
 on PANEL tag 417

CSRPOS attribute  
 example 32  
 on PANEL tag 417

CUAATTR option 179

CUADYN attribute  
 on ATTR tag 230

CUASUPP option 179

CURSOR attribute  
 example 31  
 on PANEL tag 417

cursor field  
 on PANEL tag 417

cursor placement  
 ABC 30  
 characteristics 30  
 CHOICE 30  
 DTAFLD 30  
 in command area 30  
 in data field 30  
 in list field 30  
 in selection field 30  
 LSTCOL 30  
 SELFLD 30

CWIDTHS attribute  
 CWIDTHS attribute on SELFLD  
 tag 470  
 description 98  
 using 98

## D

DA (dynamic area) tag  
 conditions of usage 284  
 description 284  
 examples 285  
 syntax 280  
 using 45

data column  
 defining 99  
 example 99

data column (DTACOL) tag  
 conditions of usage 304  
 description 99, 304  
 examples 305  
 syntax 300

data field  
 attributes 86  
 defining a field prompt 79  
 defining alignment of data 86  
 defining an associated message 86,  
 97  
 defining cursor placement 30  
 defining data columns 99  
 defining help for 85  
 defining input/output 82  
 defining width 84  
 examples 82  
 providing descriptive text 84  
 tailoring 86, 97

data field (DTAFLD) tag  
 conditions of usage 314  
 description 314  
 examples 315  
 syntax 306

data field description (DTAFLDD) tag  
 conditions of usage 316  
 description 84, 316  
 example 84  
 examples 317  
 syntax 316

DATAMOD attribute  
 on DA tag 282

DATAVAR attribute  
 description 58  
 on CHOFLD tag 249  
 on DTAFLD tag 308  
 on LSTCOL tag 368  
 on LSTVAR tag 385

DBALIGN attribute  
 description 99, 100  
 data field 88  
 on DTAFLD tag 312  
 on SELFLD tag 473  
 using 88, 99

DBALIGN option 182

DBCS  
 option 178  
 restrictions for leading and trailing  
 blanks 13

DBCS test  
 specifying on CHECKI tag 243  
 test  
 description 71  
 example 71

DD (definition description) tag  
 conditions of usage 286  
 description 128, 285

- DD (definition description) tag
  - (*continued*)
  - examples
    - basic 129
    - BREAK=ALL attribute 130
    - BREAK=FIT attribute 131
    - help panel markup 286
  - syntax 285
- DDHD (definition description header) tag
  - conditions of usage 288
  - description 128, 288
  - examples 131, 288
  - syntax 287
- declaring variables 57
- default keylist, key mappings 168
- defining help for key list 169
- definition description (DD) tag
  - conditions of usage 286
  - description 285
  - examples
    - basic 129
    - BREAK=ALL attribute 130
    - BREAK=FIT attribute 131
    - help panel markup 286
  - syntax 285
- definition description header (DDHD) tag
  - conditions of usage 288
  - description 288
  - examples 288
  - syntax 287
- definition list (DL) tag
  - conditions of usage 293
  - description 293
  - examples
    - basic 129
    - BREAK=ALL attribute 130
    - BREAK=FIT attribute 131
    - default BREAK value of NONE 294
  - syntax 292
  - using to define a definition list 128
- definition term (DT) tag
  - conditions of usage 299
  - description 299
  - examples
    - basic 129
    - BREAK=ALL attribute 130
    - BREAK=FIT attribute 131
    - help panel markup 299
  - syntax 298
- definition term divider (DTDIV) tag
  - conditions 318
  - description 318
  - syntax 318
- definition term header (DTHD) tag
  - conditions of usage 319
  - description 319
  - examples 320
  - syntax 319
- definition term header divider (DTHDIV) tag
  - conditions 321
  - description 321
  - syntax 321
- definition term segment (DTSEG) tag
  - conditions 322
  - syntax 322
- delimiter symbol 11
- depth and width, defining with PANDEF tag 53
- DEPTH attribute
  - defining application panel depth 29
  - description 97
    - data field 88
  - on AREA tag 218
  - on DA tag 282
  - on DTAFLD tag 312
  - on GA tag 328
  - on HELP tag 337
  - on HELPDEF tag 344
  - on PANDEF tag 410
  - on PANEL tag 415
  - on PS tag 439
  - on REGION tag 447
  - on SELFLD tag 469
    - using 88, 97
- DESSKIP attribute
  - description
    - data field 88
  - on DTAFLD tag 313
    - using 88
- DESTVAR attribute, on ASSIGNL tag 225
- DESWIDTH attribute
  - description 99
  - on DTACOL tag 301
  - on DTAFLD tag 309
- dialog element
  - creating 11
  - help panel 7
- dialog elements
  - application command table 8
  - description 5
  - description of application panel 5
  - description of help panel 7
  - key mapping list 9
  - messages 8
  - types 5
  - variable classes 9
  - variables 9
- Dialog Tag Language (DTL)
  - advantages 3
  - coding attributes and values 11
  - coding tag text 12
  - comments 15, 16
  - copyright statements 15
  - delimiters 11
  - document type declaration 16
  - entities 18
  - introduction 3
  - nesting tags 15
  - parameter entities 22
  - predefined symbols 25
  - relationship to CUA 4
  - results of converting 187
  - return codes 187
  - similarity to BookMaster 4
  - source file 11
  - syntax conventions 11
    - using 11
- dialog variable
  - See* variables
- DIR attribute
  - on AREA tag 219
- DIR attribute (*continued*)
  - on REGION tag 447
- DISK option 178
- DISP attribute
  - on MSG tag 392
- DISPLAY attribute
  - description 87
  - input-only 106
  - input/output 106
  - on CHOFLD tag 251
  - on DTAFLD tag 310
  - on LSTCOL tag 372
    - using 87
- DISPLAY option 181
- DISPLAYW option 181
- DISPLEN attribute
  - on SCRFLD tag 457
- DIV attribute
  - on AREA tag 218
  - on DA tag 282
  - on GA tag 328
  - on GRPHDR tag 333
  - on LSTFLD tag 378
- DIVEND attribute
  - on DL tag 293
  - on PARML tag 425
- DIVIDER (area divider) tag
  - conditions of usage 290
  - defining a divider 46
  - description 290
  - examples
    - solid and blank 50, 291
    - TYPE attribute 47
    - within a horizontal REGION tag 50
    - within vertical REGION tag 48
  - syntax 289
  - within a REGION tag 50
- DIVLOC attribute
  - on GRPHDR tag 333
- DIVWIDTH attribute
  - on AREA tag 219
- DL (definition list) tag
  - conditions of usage 293
  - description 128, 293
  - examples
    - basic 129
    - BREAK=ALL attribute 130
    - BREAK=FIT attribute 131
    - default BREAK value of NONE 294
  - syntax 292
  - using to define a definition list 128
- DLDIV (area divider) tag
  - conditions of usage 297
  - description 297
  - examples
    - solid and blank 297
- DLDIV tag
  - syntax 296
- DM application, providing help for 146
- DOCTYPE statement
  - declaring document type 16
  - description 195
  - document type declaration 16
  - parameters 195
  - syntax 195

- document type declaration
    - description 195
    - types supported by DTL 16
  - double-byte characters, permitting usage through variables 59
  - DSNAME test
    - description 69
    - example 69
    - specifying on CHECKI tag 244
  - DSNAMEF test
    - description 69
    - example 69
    - specifying on CHECKI tag 244
  - DSNAMEFM test
    - description 69
    - example 69
    - specifying on CHECKI tag 244
  - DSNAMEPQ test
    - description 70
    - example 70
    - specifying on CHECKI tag 244
  - DSNAMEQ test
    - description 70
    - example 70
    - specifying on CHECKI tag 244
  - DSNCHK option 182
  - DT (definition term) tag
    - conditions of usage 299
    - description 128, 299
    - examples
      - basic 129
      - BREAK=ALL attribute 130
      - BREAK=FIT attribute 131
      - help panel markup 299
    - syntax 298
  - DTACOL (data column) tag
    - conditions of usage 304
    - description 304
    - examples 305
    - syntax 300
  - DTAFLD (data field) tag
    - See also* data field
    - conditions of usage 314
    - description 314
    - examples 315
    - syntax 306
    - using 82
    - using MSG attribute 157
  - DTAFLDD (data field description) tag
    - See also* data field
    - conditions of usage 316
    - description 316
    - examples 317
    - syntax 316
  - DTDIV (definition term divider) tag
    - conditions 318
    - description 318
    - syntax 318
  - DTHD (definition term header) tag
    - conditions of usage 319
    - description 128, 319
    - examples 131, 320
    - syntax 319
  - DTHDIV (definition term header divider) tag
    - conditions 321
    - description 321
  - DTHDIV (definition term header divider) tag *(continued)*
    - syntax 321
  - DTL
    - macros 202
    - results of converting 187
    - return codes 187
    - source files, converting 171
  - DTSEG (definition term segment) tag
    - conditions 322
    - syntax 322
  - dynamic area (DA) tag
    - conditions of usage 284
    - description 284
    - examples 285
    - syntax 280
    - using 45
- ## E
- EBCDIC test
    - description 71
    - example 71
    - specifying on CHECKI tag 244
  - embedding source files 23
  - emphasizing panel text
    - description 141
    - HP (Highlighted phrase) 141
    - restriction 141
    - RP (reference phrase) 141
  - end tag delimiters 11
  - ENDATTR attribute
    - on PANEL tag 419
  - entity
    - defining 18
    - description 18
    - examples
      - changing text 19
      - declaring a different name 22
      - declaring a file 20
      - declaring name and text string 18
      - naming conventions 19
      - specifying a name in text 19
      - using a text string in source file 21
      - using to embed external files 23
    - naming conventions 18
    - parameter 22
    - predefined 25
    - using to embed external files 23
  - entity declarations
    - conditions of usage 197
    - description 196, 197
    - example 198
  - entity definitions
    - example 199
  - ENTITY keyword
    - on ENTITY statement 196
  - ENTITY statement
    - parameters 196
    - syntax 196
  - entity-name
    - on ENTITY statement 196
  - entity-text
    - on ENTITY statement 197
  - ENTKEYTEXT attribute
    - on PANDEF TAG 411
  - ENTKEYTEXT attribute *(continued)*
    - on PANEL TAG 420
  - ENTWIDTH attribute
    - description 97, 99
    - on CHOFLD tag 251
    - on CMDAREA tag 269
    - on DTACOL tag 301
    - on DTAFLD tag 309
    - on SELFLD tag 468
    - using 97
  - ENUM 74
  - ENUM test
    - specifying on CHECKI tag 244
  - error messages 186
  - ERRORCHECK attribute
    - on PANEL tag 420
  - example (XMP) tag
    - conditions of usage 509
    - description 509
    - examples 118, 509
    - syntax 508
    - using to define an example 118
  - EXPAND attribute
    - description
      - data field 87
    - on CHOFLD tag 252
    - on DTAFLD tag 311
    - on HELP TAG 338
    - on HELPDEF TAG 344
    - on PANDEF TAG 411
    - on PANEL tag 418
    - using 87
  - EXTEND attribute
    - description 98
    - on AREA tag 218
    - on DA tag 281
    - on GA tag 328
    - on REGION tag 447
    - on SELFLD tag 469
    - using 98
- ## F
- FCHOICE attribute
    - description 97
    - on SELFLD tag 469
    - using 97
  - field
    - defining 79
    - defining a data field message 86, 97
    - defining a list field message 106
    - defining data field 82
    - defining data field columns 99
    - defining list field 101
    - defining multiple-choice selection fields 91
    - defining selection fields 89
    - defining single-choice fields 90
    - interactive 79
    - providing additional information 145
    - types 79
  - field prompt
    - attributes 79
    - defining 79
    - example 79
    - specifying width 81

- field-level help
  - on LSTCOL tag 368
  - on SELFLD tag 466
- FIG (figure) tag
  - conditions of usage 325
  - description 324
  - examples 119, 325
  - syntax 324
  - using to define a figure 119
- FIGCAP (figure caption) tag
  - conditions of usage 326
  - description 326
  - examples 120, 327
  - syntax 326
- figure (FIG) tag
  - conditions of usage 325
  - description 324
  - examples 119, 325
  - syntax 324
  - using to define a figure 119
- figure caption (FIGCAP) tag
  - conditions of usage 326
  - description 326
  - examples 120, 327
  - syntax 326
- FileID test 69
- FILEID test
  - specifying on CHECKI tag 245
- files for installing the product 187
- filespec
  - on ENTITY statement 197
- FKA attribute on KEYI tag 353
- FLDSPACE attribute
  - description 87, 100
  - on CHOFLD tag 251
  - on DTACOL tag 302
  - on DTAFLD tag 310
  - using 87
- FLDSPOS attribute
  - on SCRFLD tag 459
- FLDTYPE attribute
  - description 99
  - data field 88
  - on DTAFLD tag 313
  - on SELFLD tag 473
  - using 88, 99
- FLDWIDTH attribute
  - description
    - data field 87
  - on DTAFLD tag 311
  - using 87
- FMTWIDTH attribute
  - on GRPHDR tag 333
- FORMAT attribute
  - description 106
  - on AREA tag 219
  - on ATTR tag 230
  - on CHDIV tag 236
  - on DA tag 283
  - on DIVIDER tag 290, 297
  - on DL tag 293
  - on GRPHDR tag 332
  - on LSTCOL tag 370
  - on MSG tag 392
  - on PARML tag 425
  - on PLDIV tag 434
  - on XLATL tag 506

- FORMAT option 180
- formatting panel text
  - Asian rules 13
  - English rules 13
- FRAME attribute on FIG tag 324
- function key area
  - defining 167
  - description 7

## G

- GA (graphic area) tag
  - conditions of usage 329
  - description 329
  - examples 330
  - syntax 327
  - using 46
- GAP attribute
  - on DIVIDER tag 289
  - on DLDIV tag 296
  - on PLDIV tag 434
- GE attribute
  - on ATTR tag 230
- generate (GENERATE) tag
  - conditions of usage 330
  - description 330
  - examples 331
  - syntax 330
- GENERATE (generate) tag
  - conditions of usage 330
  - description 330
  - syntax 330
- GENERATE (generate)tag
  - examples 331
- generated panel comments
  - comments 15
- generated panel statements
  - copyright 15
- graphic area (GA) tag
  - conditions of usage 329
  - description 329
  - examples 330
  - syntax 327
  - using 46
- GRAPHIC option 182
- group header (GRPHDR) tag
  - conditions of usage 334
  - description 333
  - examples 334
  - syntax 332
- GRPBOX attribute on REGION tag 447
- GRPBXMAT attribute on REGION tag 448
- GRPBXVAR attribute on REGION tag 448
- GRPHDR (group header) tag
  - additional attributes for 107
  - conditions of usage 334
  - description 333
  - description of attributes 107
  - examples 334
  - syntax 332
- GRPWIDTH attribute on REGION tag 447
- GUI option 181
- GUTTER attribute
  - on CHDIV tag 236

- GUTTER attribute (*continued*)
  - on DIVIDER tag 289
  - on DLDIV tag 296
  - on PLDIV tag 434

## H

- heading
  - in the information region 116
  - levels 116
- heading (Hn) tag
  - conditions of usage 347
  - description 347
  - examples 116, 347
  - syntax 346
  - using to define a heading 116
- HEADLINE attribute
  - on GRPHDR tag 333
  - on LSTGRP tag 382
- help
  - defining a help pull-down 37
  - defining for a data field 85
  - defining help panels 146
  - field-level 466
  - for action bar 36
  - for application panels 30
  - for selection choice 95
  - for selection field 95
  - for the conversion utility 176
- HELP (help panel) tag
  - conditions of usage 341
  - description 339
  - examples 341
  - syntax 335
- HELP attribute
  - on ABC tag 208
  - on CHOFLD tag 250
  - on CHOICE tag 256
  - on CMDAREA tag 268
  - on DA tag 284
  - on DTAFLD tag 308
  - on HELP tag 337
  - on HELPDEF tag 344
  - on KEYL tag 356
  - on LSTCOL tag 368
  - on MSG tag 391
  - on PANDEF tag 409
  - on PANEL tag 415
  - on PDC tag 429
  - on RP tag 454
  - on SELFLD tag 466
- help default (HELPDEF) tag
  - conditions of usage 346
  - description 345
  - examples 346
  - syntax 343
- help panel
  - defining for a data field 85
  - defining help panel text 147
  - function key area 8
  - layout 7
  - overview 7
  - panel body 8
  - panel title 7
  - title 7
  - types of help 7

- help panel (*continued*)
    - using HELP attribute of PANEL tag 30
  - help panel (HELP) tag
    - conditions of usage 341
    - description 339
    - examples 341
    - syntax 335
  - help panel tag, using 146
  - help panels
    - defining 146
    - defining areas and regions 147
    - using the INFO tag with 147
  - help pull-down, defining 37
  - HELP tag 146
  - HELPDEF (help default) tag
    - conditions of usage 346
    - description 345
    - examples 346
    - syntax 343
  - HELPDEF attribute on HELP tag 337
  - HEX test
    - description 75
    - example 75
    - specifying on CHECKI tag 245
  - HIDE attribute on CHOICE tag 258
  - HIDEX attribute on CHOICE tag 259
  - highlighted phrase (HP) tag 455
    - conditions of usage 349
    - description 349
    - examples 349
    - syntax 348
  - HILITE attribute
    - description 99, 106
      - data field 88
    - on ATTR tag 230
    - on DTAFD tag 313
    - on HP tag 349
    - on LSTCOL tag 372
    - on NOTE tag 397
    - on NOTEL tag 400
    - on NT tag 402
    - on SELFLD tag 474
    - using 88, 99
  - Hn (heading) tag
    - conditions of usage 347
    - description 347
    - examples 116, 347
    - syntax 346
    - using to define a heading 116
  - horizontal region 49
  - HP (Highlighted phrase) tag
    - conditions of usage 349
    - description 141, 349
    - examples 141, 349
    - restriction 141
    - syntax 348
- I**
- ID attribute
    - on HELPDEF tag 344
    - on PANDEF tag 409
  - ID panel 28
  - IDATE attribute
    - value IDATE on CHECKI tag 245
  - IDATE test
    - description 75
    - example 75
  - IMAPCOL attribute
    - on HELP tag 339
    - on HELPDEF tag 345
    - on PANDEF tag 411
    - on PANEL tag 420
  - IMAPNAME attribute
    - description
      - data field 88
    - on CHOFLD tag 252
    - on CMDAREA tag 271
    - on DTAFD tag 312
    - on HELP tag 339
    - on HELPDEF tag 345
    - on PANDEF tag 411
    - on PANEL tag 420
    - on PS tag 439
    - using 88
  - IMAPNAMEP attribute
    - description
      - data field 88
    - on CMDAREA tag 271
    - on DTAFD tag 312
    - on PS tag 439
    - using 88
  - IMAPROW attribute
    - on HELP tag 339
    - on HELPDEF tag 345
    - on PANDEF tag 411
    - on PANEL tag 420
  - immediate-action, for pull-down
    - choice 35
  - INCLUDE test
    - description 75
    - example 75
    - specifying on CHECKI tag 245
  - INDENT attribute
    - on AREA tag 218
    - on DL tag 293
    - on GRPHDR tag 333
    - on OL tag 405
    - on P tag 407
    - on PARML tag 425
    - on REGION tag 447
    - on SL tag 480
    - on UL tag 491
  - index value
    - on PANEL tag 417
  - INDVAL attribute
    - on SCRFLD tag 458
  - INDVAR attribute
    - on SCRFLD tag 457
  - INFO (information region) tag
    - conditions of usage 351
    - description 351
    - examples 113, 351
    - syntax 350
    - using to define an information region 113
  - information message
    - defining 156
    - description 156
    - providing for fields 145
  - information region
    - defining 113
  - information region (*continued*)
    - defining text 114
    - definition lists 128
    - examples (XMP tag) 118
    - figure captions 120
    - figures 119
    - headings 116
    - list part 134
    - ordered lists 126
    - paragraphs 114
    - parameter lists 132
    - providing information for fields 145
    - simple lists 122
    - tags for text 113
    - unformatted text 117
    - unordered lists 124
  - information region (INFO) tag
    - conditions of usage 351
    - description 351
    - examples 113, 351
    - syntax 350
    - using to define an information region 113
  - INIT attribute
    - description 98
      - data field 88
    - on CHOFLD tag 252
    - on DTAFD tag 312
    - on SELFLD tag 471
    - using 88, 98
  - initialization syntax, source-filespec 177
  - input/output data field 82
  - installing the conversion utility 187
  - instruction text 40
  - instructions, top and bottom 39
  - INTENS attribute
    - description 99, 106
      - data field 88
    - on ATTR tag 229
    - on DTAFD tag 313
    - on HP tag 349
    - on LSTCOL tag 372
    - on NOTE tag 397
    - on NOTEL tag 400
    - on NT tag 402
    - on SELFLD tag 474
    - using 88, 99
  - INTENSE attribute
    - on HP tag 349
    - on P tag 407
  - IPADDR4
    - description 77
    - example 77
  - IPADDR4 attribute
    - value IPADDR4 on CHECKI tag 246
  - IPADDR4 test
    - specifying on CHECKI tag 246
  - ISP application identifier 161
  - ISPCMDTB 161, 274
  - ISPD TLC
    - overview 9
    - using ? 177
    - using command 171
  - ISPKYLST
    - description 168
    - key mappings list 168
    - using 168

ISPx application identifier 161  
item translate list  
  description 61  
  example 62  
ITIME attribute  
  value ITIME on CHECKI tag 245  
ITIME test  
  description 76  
  example 76

## J

JDATE attribute  
  value JDATE on CHECKI tag 245  
JDATE test  
  description 76  
  example 76  
JSTD attribute  
  value JSTD on CHECKI tag 245  
JSTD test  
  description 76  
  example 76  
jump function xxii  
JUST attribute  
  on ATTR tag 230

## K

KANA option 179  
KEY attribute on KEYI tag 352  
key item (KEYI) tag  
  conditions of usage 354  
  description 354  
  examples 354  
  syntax 352  
  using to define a key item 167  
key list, defining help 169  
key mapping list  
  defining 167  
  defining with PANDEF tag 53  
  overview 9  
  using KEYLIST attribute of PANEL tag 29  
key mapping list (KEYL) tag  
  conditions of usage 357  
  description 356  
  examples 357  
  syntax 355  
KEYAPPL option 179  
KEYI (key item) tag  
  conditions of usage 354  
  description 167, 354  
  examples 354  
  syntax 352  
  using to define a key item 167  
KEYL (key mapping list) tag  
  conditions of usage 357  
  description 167, 356  
  examples 357  
  syntax 355  
  using 167  
KEYLIST attribute  
  examples 29  
  on HELP TAG 338  
  on HELPDEF TAG 344  
  on PANDEF tag 410

KEYLIST attribute (*continued*)  
  on PANEL tag 416  
KEYLTYPE attribute  
  on HELP TAG 338  
  on HELPDEF tag 344  
  on PANDEF tag 410  
  on PANEL tag 417  
keys  
  *See also* function key area  
  assigning actions 167  
  default keylist 168  
  defining 168  
  defining key mapping lists 167  
  displaying 168

## L

LANG attribute on ACTION tag 214  
LCOLDISP attribute  
  on SCRFLD tag 459  
LCOLIND attribute  
  on SCRFLD tag 459  
LEN test  
  description 73  
  example 73  
  specifying on CHECKI tag 244  
LI (list item) tag  
  conditions of usage 359  
  description 358  
  examples  
    basic unordered list 124  
    help panel with unordered list 360  
    list part (LP) tag 134  
    nested unordered 125  
    nesting ordered list 126  
    note list 122  
    paragraph nested in a list 133  
    simple list 122  
  syntax 358  
LINDVAL attribute  
  on SCRFLD tag 458  
LINDVAR attribute  
  on SCRFLD tag 458  
LINE attribute  
  description 106  
  on LSTCOL tag 369  
  on LSTVAR tag 385  
LINES (lines) tag  
  conditions of usage 361  
  description 361  
  examples 117, 361  
  syntax 360  
  using to define unformatted text 117  
list column 32  
  defining width 105  
  truncating 105  
list column (LSTCOL) tag  
  conditions of usage 373  
  description 372  
  examples 373  
  syntax 366  
list field  
  additional attributes for 105  
  auto-tab attribute 105  
  defining 101  
  defining alignment of data 105

list field (*continued*)  
  defining an associated message 106  
  defining cursor placement 30  
  defining required input for 107  
  description 101  
  example 102  
  specifying help for 106  
  tailoring 105  
list field (LSTFLD) tag  
  conditions of usage 379  
  description 379  
  examples 380  
  syntax 377  
list group (LSTGRP) tag  
  conditions of usage 383  
  description 383  
  example 384  
  syntax 382  
list item (LI) tag  
  conditions of usage 359  
  description 358  
  examples  
    basic 122  
    COMPACT attribute on simple list 123  
    compact ordered list 127  
    help panel with unordered list 360  
  syntax 358  
list part (LP) tag  
  conditions of usage 365  
  description 365  
  examples 134, 365  
  syntax 364  
  using to define a list part 134  
list variable (LSTVAR) tag  
  conditions of usage 386  
  description 385  
  example 386  
  syntax 385  
LISTDEPTH attribute  
  description 99  
  on SELFLD tag 472  
  using 99  
LISTING option 180  
LISTREF attribute  
  description 99  
  on SELFLD tag 472  
  using 99  
LISTREPL option 180  
lists  
  definition 128  
  list part 134  
  nesting lists within lists 135  
  note 122  
  ordered 126  
  parameter 132  
  simple 122  
  types 121  
  unordered 124  
LISTTYPE attribute  
  description 99  
  on SELFLD tag 472  
  using 99  
LISTV test  
  description 73  
  example 73

- LISTV test (*continued*)
  - specifying on CHECKI tag 243
- LISTVX test
  - description 73
  - example 73
  - specifying on CHECKI tag 243
- LIT (literal) tag
  - conditions of usage 363
  - description 363
  - examples 363
  - syntax 362
- literal (LIT) tag
  - conditions of usage 363
  - description 363
  - examples 363
  - syntax 362
- LMSG attribute
  - on PANEL tag 419
- LOCATION attribute
  - on MSG tag 391
  - on REGION tag 448
- LOGREPL option 180
- LookAt message retrieval tool xi
- LP (list part) tag
  - conditions of usage 365
  - description 365
  - examples 134, 365
  - syntax 364
  - using to define a list part 134
- LSTCOL (list column) tag
  - additional attributes for 105
  - conditions of usage 373
  - description 101, 372
  - description of attributes 105
  - examples 373
  - syntax 366
  - using MSG attribute 157
- LSTFLD (list field) tag
  - conditions of usage 379
  - description 101, 379
  - examples 380
  - syntax 377
- LSTGRP (list group) tag
  - conditions of usage 383
  - description 101, 383
  - example 384
  - syntax 382
- LSTVAR (list variable) tag
  - conditions of usage 386
  - description 101, 385
  - example 386
  - syntax 385
- LSTVIEW option 179
- LVLIN attribute
  - on DA tag 281
  - on GA tag 329

## M

- M (mnemonic) tag
  - conditions of usage 389
  - description 389
  - example 389
  - parameters 388
  - syntax 388
- macros
  - DTL 202

- MARGIN attribute on AREA tag 218
- MARGINW attribute
  - example 41
  - on AREA tag 218
- markup declarations
  - comments 16
  - defining entities and parameter entities 18
  - document type declaration 16
  - entity declarations 18
  - types supported by DTL 16
- markup language
  - advantages 4
  - description 3
- markup, coding 11
- MATCH attribute
  - description 37
  - example 38
  - on CHOICE tag 257
  - on PDC tag 429
- MCOMMENT option 182
- MENU attribute
  - on PANEL tag 417
- MERGESAREA attribute
  - on HELP TAG 338
  - on HELPDEF TAG 345
  - on PANDEF TAG 411
  - on PANEL tag 419
- MERGESAREA option 181
- message
  - declaring variables for 57
  - defining 155
  - defining for a data field 86, 97
  - defining for a list field 106
  - example 8
  - for check list 158
  - member 155
  - specifying a variable in text 160
  - specifying type 156
  - types 155
- message (MSG) tag
  - conditions of usage 393
  - description 393
  - examples 156, 393
  - MSG SUFFIX attribute 156
  - syntax 390
  - using to define a message 155
- message identifier 156
- message member 155
- message member (MSGMBR) tag
  - conditions of usage 395
  - description 395
  - examples
    - basic 155
    - defining a message member 395
    - specifying type 156
  - syntax 394
  - using to define a message member 155
- message retrieval tool, LookAt xi
- messages
  - assigning for check list 157
  - assigning for data field 157
  - assigning for failing specified translation 157
  - assigning for failing validity check 157

- messages (*continued*)
  - assigning for list column 157
  - conversion utility 186
  - defining 155
  - description 155
  - error 186
  - overview 8
  - warning 186
- MIX test
  - description 71
  - example 71
  - specifying on CHECKI tag 245
- MNEMGEN attribute on AB tag 206
- mnemonic (M) tag
  - conditions of usage 389
  - description 389
  - example 389
  - parameters 388
  - syntax 388
- mnemonic choice selection
  - from pull-downs and action bars 38
  - support of 38
- MODE attribute on ACTION tag 214
- MSG (message) tag
  - conditions of usage 393
  - description 393
  - examples 156, 393
  - MSG SUFFIX attribute 156
  - syntax 390
  - using to define a message 155
- MSG attribute
  - on CHECKL tag 247
  - on DTAFD tag 309
  - on LSTCOL tag 368
  - on SELFLD tag 469
  - on VARCLASS tag 496
  - on XLATL tag 507
  - using 86, 97
- MSGEXPAND option 180
- MSGLINE attribute
  - on HELP tag 339
  - on PANEL tag 418
- MSGMBR (message member) tag
  - conditions of usage 395
  - description 395
  - examples
    - basic 155
    - defining a message member 395
    - specifying type 156
  - syntax 394
  - using to define a message member 155
- MSGSUPP option 179
- MSGTYPE attribute on MSG tag 391
- multiple-choice selection field
  - defining 91
  - discussion 91
  - example 91
- MVS naming conventions 187

## N

- NAME attribute
  - identifying variables 77
  - on CHOICE tag 256
  - on CMD tag 262
  - on CMDAREA tag 269

- NAME attribute (*continued*)
    - on DA tag 281
    - on DTAFD tag 307
    - on GA tag 328
    - on HELP tag 336
    - on KEYL tag 356
    - on MSGMBR tag 394
    - on PANEL tag 414
    - on SELFLD tag 466
    - on VARCLASS tag 494
    - on VARDCL tag 497
    - rules for variable names 205
    - using with the PANEL tag 28
  - NAME test
    - description 70
    - example 70
    - specifying on CHECKI tag 242
  - NAMEF test
    - description 71
    - example 71
    - specifying on CHECKI tag 242
  - naming conventions for MVS 187
  - NEST attribute on ACTION tag 214
  - nested commands xxii
  - nesting 139
    - lists within lists 135
    - ordered lists 126, 127
    - simple list 123
    - tags within lists 133
    - unordered lists 125
  - NEWAPPL attribute on ACTION tag 213
  - NEWPOOL attribute on ACTION tag 213
  - NEWWINDOW attribute on ACTION tag 213
  - NOACTBAR option 180
  - NOCHECK attribute on ACTION tag 214
  - NOCUAATTR option 179
  - NOCUASUPP option 179
  - NODBALIGN option 182
  - NODBCS option 178
  - NODISPLAY option 181
  - NODISPLAYW option 181
  - NODSNCHK option 182
  - NOENDATTR attribute
    - description 87, 106
    - on CHOFLD tag 251
    - on DIVIDER tag 290
    - on DTAFD tag 310
    - on LSTCOL tag 371
    - using 87
  - NOFORMAT option 180
  - NOGRAPHIC option 182
  - NOGUI option 181
  - NOINIT attribute
    - on CMDAREA tag 269
  - NOJUMP attribute
    - description
      - data field 88
      - on CMDAREA tag 271
      - on DTAFD tag 313
      - using 88
  - NOKANA option 179
  - NOLISTING option 180
  - NOLISTREPL option 180
  - NOLOGREPL option 180
  - NOLSTVIEW option 179
  - NOMATCH attribute on CHOICE tag 257
  - NOMCOMMENT option 182
  - NOMERGESAREA option 181
  - NOMSGEXPAND option 180
  - NOMSGSUPP option 179
  - NOPANEL option 179
  - NOPLB option 182
  - NOPREP option 179
  - NOREPLACE option 178
  - NOSCRIP option 179
  - NOSEL attribute
    - description 99
    - on SELFLD tag 473
    - using 99
  - NOSKIP attribute
    - on DL tag 293
    - on FIG tag 324
    - on LINES tag 360
    - on NOTE tag 397
    - on NOTEL tag 399
    - on NT tag 402
    - on OL tag 404
    - on SL tag 480
    - on UL tag 491
    - on XMP tag 509
  - NOSTATS option 179
  - NOTE (note) tag
    - conditions of usage 398
    - description 398
    - examples 398
    - syntax 396
  - note (NT) tag
    - conditions of usage 403
    - description 403
    - examples 403
    - syntax 402
  - note list (NOTEL) tag
    - conditions of usage 400
    - description 400
    - examples 401
    - syntax 399
  - NOTE tag
    - description 136
    - example 136
  - NOTEL (note list) tag
    - conditions of usage 400
    - description 136, 400
    - examples 137, 401
    - syntax 399
  - NOV3PADC option 183
  - NOVERSION option 181
  - NOZVARS option 182
  - NT (note) tag
    - conditions of usage 403
    - description 136, 403
    - example 138
    - examples 403
    - syntax 402
  - NUM test
    - description 74
    - example 74
    - specifying on CHECKI tag 243
  - NUMERIC attribute
    - on ATTR tag 230
  - numeric variables
    - converting 60
    - description 60
    - uses 60
- ## O
- OFFSET attribute
    - on P tag 407
  - OL (ordered list) tag
    - conditions of usage 405
    - description 405
    - examples
      - COMPACT attribute 127
      - list part (LP) tag 134
      - nested with paragraph 406
      - nesting 126
      - paragraph nested in a list 133
      - syntax 404
      - using to define an ordered list 126
  - OPT attribute on ACTION tag 214
  - ordered list (OL) tag
    - conditions of usage 405
    - description 405
    - examples
      - COMPACT attribute 127
      - list part (LP) tag 134
      - nested with paragraph 406
      - nesting 126
      - paragraph nested in a list 133
      - syntax 404
      - using to define an ordered list 126
  - OUTLINE attribute
    - description
      - data field 87
      - DTACOL tag 100
      - LSTCOL tag 106
      - selection field 98
    - on ATTR tag 230
    - on CHOFLD tag 252
    - on CHOICE tag 258
    - on CMDAREA tag 269
    - on DTACOL tag 302
    - on DTAFD tag 311
    - on LSTCOL tag 371
    - on PANDEF tag 410
    - on PANEL tag 418
    - on SELFLD tag 471
    - using 87, 98
  - output data field 82
  - overriding variable classes 77
- ## P
- P (paragraph) tag
    - conditions of usage 407
    - description 407
    - examples
      - basic 114
      - defining information region
        - width 408
      - formatting of 115
      - nested in an ordered list 133
      - syntax 406
      - using to define a paragraph 114

- PAD attribute
  - description
    - data field 87
    - DTACOL tag 100
    - LSTCOL tag 106
    - selection field 98
  - on ATTR tag 230
  - on CHOFLD tag 251
  - on CHOICE tag 258
  - on CMDAREA tag 269
  - on DTACOL tag 302
  - on DTAFLD tag 310
  - on LSTCOL tag 371
  - on PANDEF tag 410
  - on PANEL tag 418
  - on SELFLD tag 471
  - using 87, 98
- PADC attribute
  - description
    - data field 87
    - DTACOL tag 100
    - LSTCOL tag 106
    - selection field 98
  - on ATTR tag 230
  - on CHOFLD tag 251
  - on CHOICE tag 258
  - on CMDAREA tag 269
  - on DTACOL tag 302
  - on DTAFLD tag 310
  - on LSTCOL tag 371
  - on PANDEF tag 410
  - on PANEL tag 418
  - on SELFLD tag 471
  - using 87, 98
- PANDEF (panel default) tag
  - conditions of usage 412
  - defining panel defaults 53
  - description 411
  - examples
    - overriding a value 55
    - referring to default definitions 412
    - shared panel dimensions only 54
    - shared panel values 54
  - syntax 409
- PANDEF attribute
  - on PANEL tag 415
- panel 7
  - declaring variables for 57
  - defining fields 79
  - defining with the PANEL tag 27
- PANEL (panel) tag
  - conditions of usage 421
  - defining a panel ID 28
  - defining an application panel 27
  - defining cursor placement 30
  - defining panel NAME value 28
  - defining the panel title 29
  - defining the panel width and depth 29
  - description 421
  - examples
    - CURSOR attribute 31
    - HELP attribute 30
    - KEYLIST attribute 29, 422
    - start and end tags 28
    - WIDTH and DEPTH attributes 29
- PANEL (panel) tag (*continued*)
  - specifying a key mapping list 29
  - specifying a KEYLIST attribute 29
  - specifying associated help panel 30
  - syntax 413
- panel body 6
- panel default (PANDEF) tag
  - conditions of usage 412
  - description 411
  - examples 412
  - syntax 409
- panel defaults 53
- panel instruction (PNLINST) tag
  - conditions of usage 436
  - description 436
  - examples 437
  - syntax 436
- PANEL option 179
- panel region, defining 48
- panel title
  - defining 29
  - description 6
  - for help panels 7
- panel-title-text attribute
  - on PANEL tag 421
- PANELSTMT attribute
  - on PANEL tag 420
- paragraph (P) tag
  - conditions of usage 407
  - description 407
  - examples
    - basic 114
    - defining information region width 408
    - formatting of 115
    - nested in an ordered list 133
    - syntax 406
    - using to define a paragraph 114
- parameter description (PD) tag
  - conditions of usage 427
  - description 427
  - examples 132, 427
  - syntax 427
- parameter entity
  - description 22
  - examples 22
  - naming conventions 23
  - syntax 196
- parameter list (PARML) tag
  - conditions of usage 425
  - description 425
  - examples 426
  - syntax 424
  - using to define a parameter list 132
- parameter list divider (PLDIV) tag
  - syntax 434
- parameter term (PT) tag
  - conditions of usage 442
  - description 442
  - examples 132, 442
  - syntax 441
- parameter term divider (PTDIV) tag
  - conditions of usage 443
  - description 443
  - examples 443
  - syntax 443
- parameter term segment (PTSEG) tag
  - conditions 445
  - syntax 445
- PARM attribute
  - on ACTION tag 212
  - on KEYI tag 353
- parm list divider (PLDIV) tag
  - conditions of usage 435
  - description 434
  - examples 435
- PARML (parameter list) tag
  - conditions of usage 425
  - description 425
  - examples 132, 426
  - syntax 424
  - using to define a parameter list 132
- PAS attribute
  - description 107
  - data field 87
  - on ATTR tag 230
  - on CHOFLD tag 252
  - on DTAFLD tag 311
  - on LSTCOL tag 371
  - using 87
- PASSLIB attribute on ACTION tag 213
- PASSTHRU 163
- PD (parameter description) tag
  - conditions of usage 427
  - description 427
  - examples 132, 427
  - syntax 427
- PDC (pull-down choice) tag
  - conditions of usage 430
  - description 430
  - examples
    - basic 431
    - defining help panel 37
    - markup 35
    - using mnemonic selection 38
  - syntax 428
- PDCVAR attribute on ABC tag 209
- PDSEP (pull-down separator) tag
  - conditions of usage 432
  - description 432
  - example 432
  - syntax 432
- phrase-to-be-highlighted attribute
  - on HP tag 349
- PICT test
  - description 72
  - example 72
  - specifying on CHECKI tag 242
- PICTCN test
  - description 72
  - example 72
  - specifying on CHECKI tag 242
- PLACE attribute
  - description
    - data field 88
  - on CMDAREA tag 271
  - on DTAFLD tag 312
  - on PS tag 439
  - using 88
- PLDIV (parm list divider) tag
  - conditions of usage 435
  - description 434

- PLDIV (parm list divider) tag *(continued)*
    - examples
      - solid and blank 435
      - syntax 434
    - PLEB option 182
  - PMTFMT attribute
    - description 100
      - data field 87
      - on DTACOL tag 302
      - on DTAFLD tag 311
    - using 87
  - PMTLOC attribute
    - description 100
      - on CMDAREA tag 268
      - on DTAFLD tag 310
      - on SELFLD tag 467
    - using 79
  - PMTSKIP attribute
    - description 99
      - data field 88
      - on DTAFLD tag 312
      - on SELFLD tag 473
    - using 88, 99
  - PMTTEXT attribute
    - on CMDAREA tag 269
  - PMTWIDTH attribute
    - description 99
      - on DTACOL tag 301
      - on DTAFLD tag 309
      - on SELFLD tag 467
    - using 79
  - PNLINST (panel instruction) tag
    - conditions of usage 436
    - description 436
    - examples 437
    - syntax 436
  - point-and-shoot (PS) tag
    - conditions of usage 440
    - description 439
    - example 440
    - syntax 438
  - pop-up window, displaying messages
    - on 155
  - POSITION attribute
    - description 107
      - on LSTCOL tag 369
  - position value
    - on PANEL tag 417
  - predefined entities 25
  - predetermined tag attributes 12
  - PREP option 179
  - preselected pull-down choice 37
  - PRIME attribute
    - on PANEL tag 418
  - PROFDDN option 183
  - PROFILE option 183
  - prompt
    - See* field prompt
  - prompt-width, specifying for data field 81
  - PS (point-and-shoot) tag
    - conditions of usage 440
    - description 439
    - example 440
    - syntax 438
  - PSBUTTON attribute
    - on CMDAREA tag 270
  - PSVAL attribute
    - description
      - data field 87
      - on CHOFLD tag 252
      - on CMDAREA tag 270
      - on DTAFLD tag 311
    - using 87
  - PSVAR attribute
    - description
      - data field 87
      - on CHOFLD tag 252
      - on CMDAREA tag 270
      - on DTAFLD tag 311
    - using 87
  - PT (parameter term) tag
    - conditions of usage 442
    - description 442
    - examples 132, 442
    - syntax 441
  - PTDIV (parameter term divider) tag
    - conditions of usage 443
    - description 443
    - examples 443
    - syntax 443
  - PTSEG (parameter term segment) tag
    - conditions 445
    - syntax 445
  - pull-down choice (PDC) tag
    - conditions of usage 430
    - description 430
    - examples 431
    - syntax 428
    - actions 36
    - defining 34
    - example 36
    - preselected 37
    - providing help for 36
  - pull-down separator (PDSEP) tag (PDSEP) tag
    - conditions of usage 432
    - description 432
    - example 432
    - syntax 432
  - pull-down, defining 34
- R**
- RANGE test
    - checking values within a numeric range 67
    - description 67
    - specifying on CHECKI tag 239
  - RCOLDISP attribute
    - on SCRFLD tag 459
  - RCOLIND attribute
    - on SCRFLD tag 459
  - reference phrase (RP) tag
    - conditions of usage 455
    - description 455
    - examples 455
    - syntax 454
  - REFRESH attribute
    - description 98
      - on SELFLD tag 471
    - using 98
  - REGION (region) tag
    - conditions of usage 448
    - defining a region 48
    - description 448
    - examples
      - DIR attribute 48
      - horizontal and vertical 50, 449
    - syntax 446
  - REPLACE keyword
    - on ENTITY statement 196
  - REPLACE option 178
  - REQUIRED attribute
    - description 100
      - data field 86
      - LSTCOL tag 107
      - selection field 97
    - on CHOFLD tag 250
    - on DTACOL tag 303
    - on DTAFLD tag 308
    - on LSTCOL tag 368
    - on SELFLD tag 469
    - using 86, 97
  - RESULT attribute on ASSIGNI tag 223
  - return codes, results of converting with DTL 187
  - RINDVAL attribute
    - on SCRFLD tag 458
  - RINDVAR attribute
    - on SCRFLD tag 458
  - risk (attention statement) 139
  - risk (warning statement) 139
  - ROWS attribute
    - on LSTFLD tag 378
  - RP (Reference phrase) tag
    - conditions of usage 455
    - description 143, 455
    - example 143
    - examples 455
    - restriction 143
    - syntax 454
  - rules
    - for variable names 205
    - formatting Asian panel text 13
    - formatting English panel text 13
  - RULES attribute
    - on LSTFLD tag 377
  - RUN attribute
    - example 162
    - on ACTION tag 212
    - specifying a command 36, 162
- S**
- SCALE attribute
    - on SCRFLD tag 459
  - SCRCAPS attribute
    - on CMDAREA tag 270
    - on DA tag 283
    - on LSTFLD tag 379
  - SCREEN option 178
  - SCRFLD (scrollable field) tag
    - conditions of usage 462
    - description 460
    - examples 462
    - syntax 456
  - SCRIPT option 179

- SCRNAME attribute on ACTION tag 213
  - SCROLL attribute
    - on DA tag 282
    - on SCRFLD tag 459
  - scrollable fields
    - defining 108
    - SCRFLD tag 456
  - SCROLLTAB attribute
    - on CMDAREA tag 270
    - on DA tag 283
    - on LSTFLD tag 379
  - SCROLLVAR attribute
    - on CMDAREA tag 269
    - on DA tag 283
    - on LSTFLD tag 378
  - SCRVHELP attribute
    - on CMDAREA tag 270
    - on DA tag 283
    - on LSTFLD tag 378
  - SELCHAR attribute on CHOICE tag 258
  - SELCHECK parameter 99
  - SELDEFAULT attribute
    - description 99
    - on SELFLD tag 473
    - using 99
  - selection choice (CHOICE) tag
    - conditions of usage 260
    - description 259
    - examples 261
    - syntax 255
  - selection choice, defining space for 95
  - selection field
    - attributes 97
    - defining 89
    - defining a field prompt 79
    - defining cursor placement 30
    - defining space for choice 95
    - help for 95
    - using the CHOICE tag 89
  - selection field (SELFLD) tag
    - conditions of usage 475
    - description 474
    - examples 476
    - syntax 464
  - selection list, defining cursor placement 32
  - selection width, defining 97
  - SELFLD (selection field) tag
    - conditions of usage 475
    - description 474
    - examples 476
    - syntax 464
    - using MSG attribute 157
  - SELFMT attribute
    - description 98
    - on SELFLD tag 471
    - using 98
  - SELMSG attribute
    - description 98
    - on SELFLD tag 471
    - using 98
  - SELMSGU attribute
    - description 98
    - on SELFLD tag 471
    - using 98
  - SELWIDTH attribute
    - defining space for 95
    - description 95, 99
    - on DTACOL tag 302
    - on SELFLD tag 467
    - using 95
  - SETVAR attribute on ACTION tag 215
  - SETVERB 163
  - SHADOW attribute
    - on DA tag 282
  - simple list (SL) tag
    - conditions of usage 480
    - description 480
    - examples
      - basic 122
      - compact and nested 481
      - COMPACT attribute 123
    - syntax 480
    - using to define a simple list 122
  - SINDVAL attribute
    - on SCRFLD tag 458
  - SINDVAR attribute
    - on SCRFLD tag 458
  - single-choice selection field
    - defining 90
    - discussion 90
    - example 90
  - SKIP attribute
    - on ATTR tag 230
    - on PARML tag 425
  - SL (simple list) tag
    - conditions of usage 480
    - description 480
    - examples
      - basic 122
      - compact and nested 481
      - COMPACT attribute 123
    - syntax 480
    - using to define a simple list 122
  - SMSG attribute
    - on MSG tag 392
    - on PANEL tag 419
  - SORT attribute on CMDTBL tag 274
  - source (SOURCE) tag
    - example 483
  - SOURCE (source) tag
    - example 483
  - SOURCE (Source) tag
    - conditions of usage 483
    - description 482
    - syntax 482
  - source file
    - defining dialog elements 11
    - defining entities and parameter entities 18
    - DOCTYPE declaration 195
    - embedding 23
    - frequently used words (entities) 18
    - including comments 15, 16
    - including copyright statements 15
  - source-filespec, for system 178
  - SPACE attribute
    - on LI tag 358
    - on OL tag 404
    - on P tag 407
    - on SL tag 480
    - on UL tag 491
  - SPACE keyword
    - on ENTITY statement 196
  - specifying
    - a list of values to match value of user input 67
    - a list of valuesx to match value of user input 68
    - calling the conversion utility 178
    - source-filespec 178
  - SPLIT attribute
    - on DL tag 293
    - on PARML tag 425
  - start tag delimiters 11
  - STATS option 179
  - STDDATE attribute
    - value STDDATE on CHECKI tag 245
  - STDDATE test
    - description 75
    - example 75
  - STDTIME attribute
    - value STDTIME on CHECKI tag 246
  - STDTIME test
    - description 76
    - example 76
  - STRIP attribute
    - on GRPHDR tag 333
  - SUBSTITUTE attribute
    - on GENERATE tag 330
  - SUFFIX attribute on MSG tag 391
  - SUSPEND attribute on ACTION tag 213
  - suspending an activity xxii
  - syntax diagrams, reading 193
  - SYSTEM keyword
    - on ENTITY statement 197
- ## T
- T (truncation) tag
    - conditions of usage 484
    - description 484
    - examples 164, 484
    - syntax 484
    - using to define command truncation 164
  - tag
    - attributes 11
    - coding text 12
    - delimiters 11
    - description 11
    - nesting 15
    - rules for coding values 12
    - text 12
    - values 11
  - tags
    - AB 206
    - ABC 208
    - ACTION 211
    - ASSIGNI 223
    - ASSIGNL 225
    - ATTENTION 136, 226
    - ATTR 228
    - BOTINST 232
    - CAUTION 136
    - CHDIV 236
    - CHECKI 238
    - CHECKL 247
    - CHOFLD 248

## tags (continued)

CHOICE 255  
 CMD 262  
 CMDACT 264  
 CMDAREA 267  
 CMDTBL 273  
 COMMENT 275  
 COMPOPT 277  
 COPYRIGHT 279  
 DA 280  
 DD 285  
 DDHD 287  
 DIVIDER 289  
 DL (definition list) 292  
 DLDIV 296  
 DT 298  
 DTACOL 300  
 DTAFLD 306  
 DTAFLDD 316  
 DTDIV 318  
 DTHD 319  
 DTHDIV 321  
 DTSEG 322  
 FIG 324  
 FIGCAP 326  
 for information region 113  
 GA 327  
 GENERATE 330  
 GRPHDR 332  
 HELP 335  
 HELPDEF 343  
 Hn 346  
 HP 348  
 INFO 350  
 KEYI 352  
 KEYL 355  
 LI 358  
 LINES 360  
 LIT 362  
 LP 364  
 LSTCOL 366  
 LSTFLD 377  
 LSTGRP 382  
 LSTVAR 385  
 M 388  
 mnemonic 388  
 MSG 390  
 MSGMBR 394  
 nesting 135  
 NOTE 396  
 NOTEL 399  
 NT 136, 402  
 OL 404  
 P 406  
 PANDEF 409  
 PANEL 413  
 PARM 424  
 PD 427  
 PDC 428  
 PDSEP 432  
 PLDIV 434  
 PNLINST 436  
 PS 438  
 PT 441  
 PTDIV 443  
 PTSEG 445  
 REGION 446

## tags (continued)

RP 454  
 SCRFLD 456  
 SELFLD 464  
 SL 480  
 SOURCE 482  
 T 484  
 TEXTLINE 485  
 TEXTSEG 485  
 TOPINST 488  
 UL 491  
 VARCLASS 493  
 VARDCL 497  
 VARLIST 499  
 VARSUB 500  
 WARNING 136, 502  
 XLATI 504  
 XLATL 506  
 XMP 508

text

- adding to a list 134
- defining for information region 114
- help 147
- providing attention to user 139
- providing caution 140
- providing notes to user 136
- providing warning to user 139
- static 113
- tag 12
- tags used to define 113
- using the example tag 118
- using the figure tag 119
- using the heading tags 116
- using the LINES tag 117
- using the paragraph tag 114

TEXT attribute

- description 107
- on AREA tag 219
- on LSTCOL tag 370
- on NOTE tag 397
- on NOTEL tag 400
- on NT tag 402
- on OL tag 405
- on SL tag 480
- on UL tag 491

text line (TEXTLINE) tag

- conditions of usage 485
- description 485
- examples 485
- syntax 485

text segment (TEXTSEG) tag

- conditions of usage 486
- description 486
- examples 486
- syntax 485

TEXTFMT attribute

- description 107
- on LSTCOL tag 370

TEXTLEN attribute

- description 107
- on LSTCOL tag 370

TEXTLINE (text line) tag

- conditions of usage 485
- description 485
- syntax 485

TEXTLINE (text line)tag

- examples 485

TEXTLOC attribute

- description 107
- on LSTCOL tag 370

TEXTSEG (text segment) tag

- conditions of usage 486
- description 486
- syntax 485

TEXTSEG(text segment)tag

- examples 486

TEXTSKIP attribute

- description 107
- on LSTCOL tag 370

title, panel 29

TITLELINE attribute

- on PANEL tag 418

TMARGIN attribute

- on PANDEF TAG 411
- on PANEL TAG 420

TOGVAR attribute on ACTION tag 215

top instruction

- defining 39
- description 6

top instruction (TOPINST) tag

- conditions of usage 488
- description 488
- examples 489
- syntax 488

TOPINST (top instruction) tag

- conditions of usage 488
- defining instruction text 39
- description 488
- examples 40, 489
- syntax 488

TRAIL attribute

- description 98
- on SELFLD tag 470
- using 98

translate item (XLATI) tag

- conditions of usage 505
- description 505
- examples 505
- syntax 504

translate list (XLATL) tag

- conditions of usage 507
- description 507
- examples 508
- syntax 506

translate lists

- defining 61
- types 61

translation

- defining items for 61
- example 62, 63

TRUNC attribute

- on CHOICE tag 259
- on XLATL tag 507

truncation (T) tag

- conditions of usage 484
- description 484
- examples 164, 484
- syntax 484
- using to define command truncation 164

TSIZE attribute

- description 99
- on DL tag 292
- on PARM 424

- TSIZE attribute (*continued*)
  - on SELFLD tag 472
  - using 99
- TUTOR attribute
  - on HELP tag 338
  - on PANEL tag 418
- tutor-choice fields 95
- TYPE attribute
  - description 89
  - on ACTION tag 213
  - on ATTR tag 229
  - on CHDIV tag 236
  - on CHECKI tag 239
  - on COMMENT tag 275
  - on DIVIDER tag 289
  - on DLDIV tag 296
  - on HP tag 348
  - on NOTE tag 397
  - on NOTEL tag 400
  - on NT tag 402
  - on PANEL tag 419
  - on PLDIV tag 434
  - on SELFLD tag 467
  - on SOURCE tag 482
  - on VARCLASS tag 494
  - using 89
  - value %varname on VARCLASS tag 494
  - value ALPHA on CHECKI tag 240
  - value ALPHAB on CHECKI tag 244
  - value ANY on VARCLASS tag 494
  - value BIT on CHECKI tag 242
  - value CHAR on VARCLASS tag 494
  - value CHARS on CHECKI tag 240
  - value DBCS on CHECKI tag 243
  - value DBCS on VARCLASS tag 494
  - value DSNAME on CHECKI tag 244
  - value DSNAMEF on CHECKI tag 244
  - value DSNAMEFM on CHECKI tag 244
  - value DSNAMEPQ on CHECKI tag 244
  - value DSNAMEQ on CHECKI tag 244
  - value EBCDIC on CHECKI tag 244
  - value EBCDIC on VARCLASS tag 494
  - value ENUM on CHECKI tag 244
  - value FILEID on CHECKI tag 245
  - value HEX on CHECKI tag 245
  - value IDATE on VARCLASS tag 495
  - value INCLUDE on CHECKI tag 245
  - value IPADDR4 on CHECKI tag 246
  - value ITIME on VARCLASS tag 495
  - value JDATE on VARCLASS tag 495
  - value JSTD on VARCLASS tag 495
  - value LEN on CHECKI tag 244
  - value LISTV on CHECKI tag 243
  - value LISTVX on CHECKI tag 243
  - value MIX on CHECKI tag 245
  - value MIXED on VARCLASS tag 494
  - value NAME on CHECKI tag 242
  - value NAMEF on CHECKI tag 242
  - value NUM on CHECKI tag 243
  - value NUMERIC on VARCLASS tag 495
- TYPE attribute (*continued*)
  - value PICT on CHECKI tag 242
  - value PICTCN on CHECKI tag 242
  - value RANGE on CHECKI tag 239
  - value STDDATE on VARCLASS tag 495
  - value STDTIME on VARCLASS tag 495
  - value VALUES on CHECKI tag 241
  - value VALUESX on CHECKI tag 241
  - value VMASK on VARCLASS tag 495
- U**
  - UL (unordered list) tag
    - conditions of usage 492
    - description 492
    - examples
      - basic 124
      - basic and nested 492
      - nested 125
    - syntax 491
    - using to define an unordered list 124
  - UNAVAIL attribute
    - on CHOICE tag 259
    - on PDC tag 429
  - UNAVAILMAT attribute on CHOICE tag 259
  - unformatted text
    - using the example tag 118
    - using the figure tag 119
    - using the LINES tag 117
  - unordered list (UL) tag
    - conditions of usage 492
    - description 492
    - examples
      - basic 124
      - basic and nested 492
      - nested 125
    - syntax 491
    - using to define an unordered list 124
  - upper translate list
    - example 61
    - translating a value to uppercase 61
  - USAGE attribute
    - description 101
    - on CHOFLD tag 250
    - on DTAFD tag 308
    - on LSTCOL tag 368
  - USERMOD attribute
    - on DA tag 282
- V**
  - V3PADC option 183
  - validity check item (CHECKI) tag
    - conditions of usage 246
    - description 246
    - examples 246
    - syntax 238
  - validity check list (CHECKL) tag
    - conditions of usage 247
    - description 247
    - examples 158, 248
    - syntax 247
  - validity checks
    - description 66
    - types 66
    - using 66
    - using CHECKL and CHECKI tags 66
  - value
    - description 11
    - tag 11
  - VALUE attribute
    - on ACTION tag 215
    - on ASSIGNI tag 223
    - on PS tag 439
    - on XLATI tag 504
  - VALUE1 attribute on ACTION tag 215
  - VALUE2 attribute on ACTION tag 215
  - VALUES test
    - description 67
    - example 67
    - specifying on CHECKI tag 241
  - VALUESX test
    - description 68
    - example 68
    - specifying on CHECKI tag 241
  - VAR attribute
    - on PS tag 439
    - on VARSUB tag 500
  - VARCLASS (variable class) tag
    - conditions of usage 496
    - description 496
    - examples 496
    - syntax 493
    - using MSG attribute 158
    - using to define a variable class 59
  - VARCLASS attribute
    - description 87, 100
    - input-only 107
    - input/output 107
    - on CHOFLD tag 249
    - on DTAFD tag 308
    - on LSTCOL tag 368
    - on VARDCL tag 497
    - using 87
  - VARDCL (variable declaration) tag
    - conditions of usage 498
    - description 497
    - examples 58, 498
    - syntax 497
  - VARDCL attribute
    - description
      - data field 88
    - on CMDAREA tag 271
    - on DTACOL tag 304
    - on DTAFD tag 314
    - on LSTCOL tag 372
    - on LSTFLD tag 379
    - on SELFLD tag 474
    - using 88
  - variable class
    - associating translate list 61
    - defining 58
    - defining character variables 59
    - defining translate list 506
    - description 57
    - overriding 77
    - overriding the data variable 107
    - overview 9

- variable class (VARCLASS) tag
  - conditions of usage 496
  - description 496
  - examples 496
  - syntax 493
- variable data
  - aligning 86, 105
  - description 105
- variable declaration (VARDCL) tag
  - conditions of usage 498
  - description 497
  - examples 498
  - syntax 497
- variable list
  - defining 57
- variable list (VARLIST) tag
  - conditions of usage 499
  - description 499
  - examples 499
  - syntax 499
- variable names
  - as a tag value, assigning 12
  - rules 205
  - rules for %varname as a tag value 205
- variable substitution (VARSUB) tag
  - conditions of usage 501
  - description 501
  - examples 160, 501
  - syntax 500
  - using to substitute a variable 160
- variable translate list
  - defining 61
  - relation to VARCLASS definition 61
  - types 61
- variable validation 61
- variables
  - character 59
  - declaring 57
  - defining a variable class 58
  - in data fields 82
  - item translating 62
  - numeric 60
  - overview 9
  - rules for naming 205
  - specifying in message text 160
  - translate list 61
  - translating 61, 62
  - validating 61
  - validity checks 66
- VARLIST (variable list) tag
  - conditions of usage 499
  - description 499
  - examples 58, 499
  - syntax 499
  - using 57
- VARSUB (variable substitution) tag
  - conditions of usage 501
  - description 501
  - examples 501
  - syntax 500
- VERIFY attribute
  - description 98
  - on SELFLD tag 471
  - using 98
- VERSION option 181
- vertical region 48

## W

- WARNING (warning) tag
  - conditions of usage 503
  - description 503
  - examples 227, 504
  - syntax 502
- warning message
  - defining 156
  - description
    - format 139
    - information messages 156
    - ISPF conversion utility messages 186
    - example 139
- WARNING tag
  - description 139
  - example 139
- width and depth, defining with PANDEF tag 53
- WIDTH attribute
  - defining application panel width 29
  - on AREA tag 219
  - on DA tag 282
  - on FIG tag 324
  - on GA tag 328
  - on GRPHDR tag 333
  - on HELP tag 337
  - on HELPDEF tag 344
  - on INFO TAG 350
  - on MSGMBR tag 395
  - on PANDEF tag 410
  - on PANEL tag 416
  - on REGION tag 447
- window
  - layout 5
- WINDOW attribute
  - on PANDEF tag 410
  - on PANEL tag 418
- WINTITLE attribute
  - on HELP TAG 338
  - on HELPDEF TAG 345
  - on PANDEF tag 410
  - on PANEL tag 418
- word-wrapping
  - data field width 84
  - on DESWIDTH attribute 84
- WSDIR attribute on ACTION tag 214
- WSINVOKE attribute on ACTION tag 214
- WSSIZE attribute on ACTION tag 214
- WSVIEW attribute on ACTION tag 214

## X

- XLATI (translate item) tag
  - conditions of usage 505
  - description 505
  - examples 505
  - syntax 504
- XLATL (translate list) tag
  - conditions of usage 507
  - description 507
  - examples 508
  - syntax 506
  - using MSG attribute 158

- XMP (example) tag
  - conditions of usage 509
  - description 509
  - examples 118, 509
  - syntax 508
  - using to define an example 118

## Z

- ZCMD system variable
  - for PASSTHRU 163
  - for SETVERB 163
- ZCONT attribute
  - on PANEL tag 420
- ZGUI attribute
  - description 98
  - on SELFLD tag 472
  - using 98
- ZKEYHELP, using 169
- ZUP attribute
  - on PANEL tag 420
- ZVARS option 182
- ZVERB system variable for SETVERB 163



---

# Readers' Comments — We'd Like to Hear from You

Interactive System Productivity Facility (ISPF)  
Dialog Tag Language Guide and Reference  
z/OS Version 1 Release 6.0

Publication No. SC34-4824-03

Overall, how satisfied are you with the information in this book?

	Very Satisfied	Satisfied	Neutral	Dissatisfied	Very Dissatisfied
Overall satisfaction	<input type="checkbox"/>				

How satisfied are you that the information in this book is:

	Very Satisfied	Satisfied	Neutral	Dissatisfied	Very Dissatisfied
Accurate	<input type="checkbox"/>				
Complete	<input type="checkbox"/>				
Easy to find	<input type="checkbox"/>				
Easy to understand	<input type="checkbox"/>				
Well organized	<input type="checkbox"/>				
Applicable to your tasks	<input type="checkbox"/>				

Please tell us how we can improve this book:

Thank you for your responses. May we contact you?  Yes  No

When you send comments to IBM, you grant IBM a nonexclusive right to use or distribute your comments in any way it believes appropriate without incurring any obligation to you.

---

Name

---

Address

---

Company or Organization

---

---

Phone No.

---



Fold and Tape

Please do not staple

Fold and Tape




NO POSTAGE  
NECESSARY  
IF MAILED IN THE  
UNITED STATES

# BUSINESS REPLY MAIL

FIRST-CLASS MAIL PERMIT NO. 40 ARMONK, NEW YORK

POSTAGE WILL BE PAID BY ADDRESSEE

IBM Corporation  
Department J87/D325  
555 Bailey Avenue  
San Jose, CA  
U.S.A. 95141-9989



Fold and Tape

Please do not staple

Fold and Tape





File Number: S370/4300-39  
Program Number: 5694-A01

Printed in USA

SC34-4824-03

